



Micro Focus RM/COBOL

RM/InfoExpress User's Guide

Micro Focus
The Lawn
22-30 Old Bath Road
Newbury, Berkshire RG14 1QN
UK
<http://www.microfocus.com>

© Copyright 2017-2021 Micro Focus or one of its affiliates.

The only warranties for products and services of Micro Focus and its affiliates and licensors (“Micro Focus”) are as may be set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Micro Focus shall not be liable for technical or editorial errors or omissions contained herein. The information contained herein is subject to change without notice.

Revised 2021-05-18 for version 12.18

Contents

- Preface 1**
 - Welcome to RM/InfoExpress..... 1
 - About Your Documentation..... 1
 - Related Publications..... 2
 - Conventions and Symbols..... 3
 - Customer Care 3
 - Support Guidelines 4
 - Test Cases 4

- Chapter 1: Installation and Verification 7**
 - System Requirements..... 7
 - RM/InfoExpress Server Program..... 7
 - Required Hardware..... 7
 - Required Software 8
 - RM/InfoExpress Client Program 8
 - Setup and Installation..... 8
 - RM/InfoExpress Servers..... 9
 - Setting Up the TCP/IP Package for RM/InfoExpress Servers on Windows and UNIX 9
 - Installing RM/InfoExpress Server on Windows 9
 - Software Licenses and Downloads Installation for Windows 10
 - CD-ROM Installation 11
 - Installing RM/InfoExpress Server on UNIX 12
 - Software Licenses and Downloads Installation for UNIX 13
 - Uninstallation for UNIX..... 13
 - License File 14
 - RM/InfoExpress Clients 14
 - Setting Up the TCP/IP Package for RM/InfoExpress Clients on Windows and UNIX 14
 - Installing RM/InfoExpress Clients on Windows and UNIX 14
 - Verification / Quick Start..... 15
 - Verifying the RM/InfoExpress Server 15
 - Windows Server 15
 - Starting the RM/InfoExpress server: 15
 - Windows: 15
 - Unix:..... 16
 - Server Display 16
 - Starting on Windows:..... 16
 - Starting on 17
 - UNIX:..... 17
 - Using: 17
 - Verifying WinSock on the RM/InfoExpress Windows Client..... 17
 - Verifying RM/InfoExpress Windows Client and Server Communication..... 18

Verifying the RM/InfoExpress UNIX Client.....	20
Verifying RM/InfoExpress UNIX Client and Server Communication.....	21

Chapter 2: Configuring and Running the RM/InfoExpress Server ... 23

Server Configuration Options.....	23
Starting the RM/InfoExpress UNIX Server Program	23
UNIX Server Command Line Options	24
UNIX Server Display Command Line Option.....	25
Starting and Stopping the RM/InfoExpress Windows Server Program	25
Starting/Stopping the Server.....	25
RM/InfoExpress Server Display Program.....	26
Configuring the RM/InfoExpress Windows Server Program	26
Disabling the service or setting it to start manually.....	26
Running Under a Specific Log On Account.....	27
Windows Server Command Line Options	27
Windows Server Display Command Line Option	28

Chapter 3: Using RM/InfoExpress with RM/COBOL for Windows Programs 29

Accessing the RM/InfoExpress Windows Client Program	29
Pointing to Network Data Files.....	29
Specifying Synonyms	30
Specifying RUNPATH Environment Variables	31
Specifying Explicit Pathnames in the RM/COBOL Program.....	31
Specifying Complete Pathnames Using RM/COBOL Data-Names	31
Executing RM/COBOL Programs	32

Chapter 4: Using RM/InfoExpress with RM/COBOL for UNIX Programs 33

Accessing the RM/InfoExpress UNIX Client Program	33
Pointing to Network Data Files.....	33
Specifying Synonyms	34
Specifying RUNPATH Environment Variables	34
Specifying Explicit Pathnames in the RM/COBOL Program.....	34
Specifying Complete Pathnames Using RM/COBOL Data-Names	35
Executing RM/COBOL Programs	35

Chapter 5: RM/InfoExpress Server Operations 37

Keyboard Functions.....	37
Server Display Screen Format	38
Server Display Commands	38
Client Information	40
File Information.....	41
Open Log Information	43
Error Log Information	44
Termination of Communication Activity.....	45
Termination of Server Display	46
Termination of Client Communications	46
Termination of the Server.....	46
Quit When Idle	46
Quit in a While	47
Quit Now	47

Chapter 6: File Security on the RM/InfoExpress UNIX Server 49

UNIX System Security	49
RM/InfoExpress File Security	49
RM/InfoExpress UNIX Server Security Levels.....	50
Server-User-Name	51
Default Server User	51
.rhosts File Entry.....	52
ixpwwfile File Entry.....	52
User Password	53
Additional Parameters Needed for Non-UNIX Clients	53
Client Validation by the Server at Different Security Levels	53
Server Compatibility with Older and Newer Clients	53
Older Clients with the New Server	53
New Clients with an Older Server	53
Setting Up the Network to Run RM/InfoExpress with Security Enabled.....	54
Setup for Running RM/InfoExpress at Server Security Level 0.....	55
Setup for Running RM/InfoExpress at Server Security Level 1.....	56
Setup for Running RM/InfoExpress at Server Security Level 2.....	57
Setup for Running RM/InfoExpress at Server Security Level 3.....	57
Setup for Running RM/InfoExpress at Server Security Level 4.....	58
Setup for Running RM/InfoExpress at Server Security Level 5.....	59
Setup Differences Between Server Security Levels	60

Appendix A: Messages..... 63

Error Message Types	63
Permanent Error Types	64
RM/InfoExpress API-Generated Error Codes	65
RM/InfoExpress-Generated Error Codes.....	67
RM/InfoExpress WinSock Error Codes.....	71
RM/InfoExpress Windows Sockets Interface Error Codes.....	73

Appendix B: Limits and Ranges 75

Limits and Ranges	75
-------------------------	----

Appendix C: Troubleshooting RM/InfoExpress 77

Failure to Locate File or Path.....	77
RM/InfoExpress Client Entries Not Terminating	77
Removing IPC Objects After Server Failure	78

Appendix D: Configuring RM/InfoExpress 79

Configuration Files and Options.....	79
Sample Configuration File.....	80
Common Configuration Options.....	81
Client-Specific Configuration Options	84
Sample RM/InfoExpress Windows Client Configuration File	86
Common Server-Specific Configuration Options.....	86
UNIX Server-Specific Configuration Options.....	89
Sample RM/InfoExpress UNIX Server Configuration File.....	89
Windows Server-Specific Configuration Options.....	89
Sample RM/InfoExpress Windows Server Configuration File.....	91

Appendix E: RM/InfoExpress Security Parameter File Update Utility	93
.....	
Using the Utility.....	93
Adding a New Entry	94
Modifying an Existing Entry	95
Deleting an Existing Entry	95
Listing All Entries.....	96
Appendix F: Using RM/InfoExpress with Relativity	99
Changes to Relativity Configuration for 32-Bit Windows Clients	99
Create a Configuration File.....	99
Configure Relativity to Use RM/InfoExpress.....	100
Appendix G: Summary of Enhancements	103
Version 12 Enhancements.....	103
Version 11 Enhancements.....	104
Version 10 Enhancements.....	104
Version 9 Enhancements.....	104
Version 8 Enhancements.....	104
Support for Large Files.....	104
Atomic I/O Support for File Version Level 4.....	105
Limited Automatic Session Reconnection.....	105
Client Path Prefix Inclusion and Exclusion	106
Version 2.1 Enhancements.....	106
RM/InfoExpress Server Now Supported on Windows NT Version 4.0	106
File Security on the RM/InfoExpress UNIX Server	106
New Utility to Update RM/InfoExpress Parameter File	106
Improved Server Screens.....	106
Optional Message Compression	107
Optional Message Encoding	107
Initialization File Support	107
-m Server Option Obsolete	107
Use Count Check by the Server.....	107
New File Count Option.....	107
New Option to Handle the Display of Long Filenames	107
Version 2.0.2 Enhancements.....	108
New Server Option Enables the RM/plusDB Interface	108
Version 2.0 Enhancements.....	108
RM/InfoExpress UNIX Server Filename Case-Sensitivity.....	108
RM/InfoExpress UNIX Server Configuration Option	108
RM/InfoExpress UNIX Server Runs as a Daemon.....	108
RM/InfoExpress Screen Handler Program	108
Changes in the Default Behavior.....	109
New Screens	109
More COBOL Information Added to Existing Screens.....	109
Improved Error Handling.....	109
KEEPSESSION Configuration Option.....	109
Index	111

List of Figures

Figure 1: RM/InfoExpress Client WinSock Info Message Box.....	18
Figure 2: Server Display Screen Format.....	38
Figure 3: Server Display Main Screen.....	39
Figure 4: Client Information Screen.....	40
Figure 5: Client Files Screen.....	41
Figure 6: File Information Screen.....	42
Figure 7: File Clients Screen.....	42
Figure 8: Open Log Screen.....	43
Figure 9: Open Log Screen (Toggled).....	44
Figure 10: Error Log Screen.....	44
Figure 11: Error Log Screen (Toggled).....	45
Figure 12: Terminate Command Line.....	45
Figure 13: Quit Command Line.....	46
Figure 14: Quit in a While Command Line.....	47
Figure 15: Security Parameter File Update Utility Main Screen.....	94
Figure 16: Add Entry Screen.....	94
Figure 17: Modify Entry Screen.....	95
Figure 18: Delete Entry Screen.....	96
Figure 19: List Entries Screen.....	96

List of Tables

Table 1: RM/InfoExpress UNIX Server Security Levels.....	50
Table 2: Summary of Setup Differences Between Server Security Levels.....	60
Table 3: Error Types and Associated Error Codes.....	64
Table 4: Error Codes Generated by Windows Sockets.....	71
Table 5: Error Codes Generated by the RM/InfoExpress Windows Sockets Interface.....	73

Preface

Welcome to RM/InfoExpress

RM/InfoExpress is a file management system designed to optimize RM/COBOL data file access on various local area networks (LANs) and wide area networks (WANs). Implementation is available for TCP/IP (Transmission Control Protocol/Internet Protocol).

The *RM/InfoExpress User's Guide* is intended for commercial application developers who have a basic understanding of RM/COBOL, Microsoft Windows, UNIX, and TCP/IP. The information in this preface outlines the contents of this manual, defines typographic and programming conventions used in the documentation, and provides information about obtaining Customer Care.

The new features and significant changes for the most recent release of RM/InfoExpress are described in [Appendix G: Summary of Enhancements](#) (on page 103).

Note The term “Windows” in this document refers to Microsoft 32-bit and 64-bit Windows operating systems, including Microsoft Windows 2000, Windows XP, Windows Server 2003, Windows Vista, Windows 7, Windows 8, Windows Server 2008, Windows Server 2012, Windows Server 2016, or Windows Server 2019, unless specifically stated otherwise.

About Your Documentation

The RM/InfoExpress documentation consists of a user's guide, which is distributed electronically in Portable Document Format (PDF) as part of the RM/InfoExpress software distribution. It is also available on the Micro Focus web site at <https://supportline.microfocus.com>.

Note To view and print PDF files, you need to install Adobe Acrobat Reader, a free program available from Adobe's web site at <http://www.adobe.com>.

This user's guide is divided into the following parts:

Chapter 1—Installation and Verification lists hardware and software requirements, and provides procedures for installing RM/InfoExpress on both clients and servers for a specific LAN or WAN type. Also included are procedures for verifying that both client and server software are properly installed and communicating with one another.

Chapter 2—Configuring and Running the RM/InfoExpress Server describes the procedures required to configure and run RM/InfoExpress servers for UNIX and Windows.

Chapter 3—Using RM/InfoExpress with RM/COBOL for Windows Programs describes how to access the RM/InfoExpress Windows client program, how RM/COBOL for Windows programs point to network data files, and explains how to execute RM/COBOL for Windows programs for use with RM/InfoExpress.

Chapter 4—Using RM/InfoExpress with RM/COBOL for UNIX describes how to access the RM/InfoExpress UNIX client program, how RM/COBOL for UNIX programs point to network data files, and how to execute RM/COBOL for UNIX programs for use with RM/InfoExpress.

Chapter 5—RM/InfoExpress Server Operations describes the RM/InfoExpress server commands. This chapter also describes the information displayed by the server during RM/InfoExpress execution.

Chapter 6—File Security on the RM/InfoExpress UNIX Server describes the implementation of file security on the RM/InfoExpress UNIX server.

Appendix A—Messages lists and defines the information and error messages that may be generated during an RM/InfoExpress session.

Appendix B—Limits and Ranges lists the logical and physical limits and ranges of RM/InfoExpress.

Appendix C—Troubleshooting RM/InfoExpress describes problems that you may encounter during an RM/InfoExpress session and provides solutions.

Appendix D—Configuring RM/InfoExpress describes various configuration parameters for RM/InfoExpress client and server components.

Appendix E—RM/InfoExpress Security Parameter File Update Utility describes how to use the utility program (**ixsecure.cob**) to update the parameter file (**ixpwwfile**) with security-related information that is used by the server to authenticate the clients.

Appendix F—Using RM/InfoExpress with Relativity describes how to access Relativity files using RM/InfoExpress.

Appendix G—Summary of Enhancements provides an overview of the new features in the current release, and reviews the changes and enhancements that were added to earlier releases of RM/InfoExpress.

The *RM/InfoExpress User's Guide* also includes an index.

Related Publications

The following documents contain information necessary for a complete understanding of RM/InfoExpress as used in conjunction with a specific operating system and a local area network (LAN) or wide area network (WAN):

- *RM/COBOL User's Guide*
- *Relativity Installation Guides*

Contact the appropriate vendor for other publications:

Microsoft products are available from Microsoft Corporation.

Conventions and Symbols

The following symbols and conventions are used or followed throughout this manual.

1. Text that you enter or that is displayed on your screen is indented and appears in a monospaced font. This type style is also used for sample command lines, program code and file listing examples, and sample sessions.
2. Variable information, for which you substitute a specific value, is printed in italics. For example:

```
runcobol name [options]
```

Italic type also identifies the titles of other manuals and the chapter names in this guide, and occasionally it is used for emphasis.

3. Program names, directory names, filenames, and commands appear in bold type and lowercase text. You can type program names, directory names, filenames, and commands in uppercase or lowercase letters, except where otherwise stated.

Bold type is also used for emphasis on some types of lists, and for anything you must type exactly as it appears.
4. Key combinations are connected by a plus sign (+), for example, Ctrl + X. This notation indicates that you press and hold down the first key while you press the second key. For example, “press Ctrl + X” indicates to press and hold down the Ctrl key while pressing the X key. Then release both keys.
5. RM/COBOL Compile and Runtime Command line options may be specified either with or without a hyphen. If any option on a command line is preceded by a hyphen, then a leading hyphen is required for all options. When assigning a value to an option, the equal sign is optional if leading hyphens are used.
6. Note the distinction of the following terminology:
 - The term “window” refers to a delineated area of the screen, normally smaller than the full screen.
 - In this document, the term “Windows” refers to the following Microsoft Windows operating systems: Microsoft Windows 7, Windows 8, Windows 10, Windows Server 2008, Windows Server 2012, Windows Server 2016, or Windows Server 2019, unless specifically stated otherwise.

Note

- RM/InfoExpress 12.18 no longer supports earlier Microsoft Windows operating systems, including Microsoft Windows XP, Windows Vista, or Windows Server 2003.

Additionally, in this document, any references to those versions, or to the shorthand notation “Windows 9x-class” or “Windows NT-class” referring to those operating systems, are included for historical purposes only.

Customer Care

Micro Focus is dedicated to helping you achieve the highest possible performance from the Micro Focus family of products, including RM/COBOL. The Micro Focus Customer Care

team is committed to providing you prompt and professional service when you have problems or questions about your Micro Focus products.

Support is subject to Micro Focus' prices, terms, and conditions in place at the time the service is requested.

While it is not possible to maintain and support specific releases of all software indefinitely, we offer priority support for the most current release of each product. For customers who elect not to upgrade to the most current release of the products, support is provided on a limited basis, as time and resources allow.

Support Guidelines

When you need assistance, you can expedite your call by having the following information available for the Micro Focus Customer Care representative:

1. Company name and contact information.
2. Micro Focus RM/COBOL product serial number (found in the Electronic Software Delivery email, on the media label, or in the product banner message).
3. Product version number.
4. Operating system and version number.
5. Hardware, related equipment, and terminal type.
6. Exact message appearing on screen.
7. Concise explanation of the problem and process involved when the problem occurred.

Test Cases

You may be asked for an example (test case) that demonstrates the problem. Please remember the following guidelines when submitting a test case:

- The smaller the test case is, the faster we will be able to isolate the cause of the problem.
- Do not send full applications.
- Reduce the test case to the smallest possible combination of components required to reproduce the problem.
- If you have very large data files, write a small program to read in your current data files and to create new data files with as few records as necessary to reproduce the problem.
- Test the test case before sending it to us to ensure that you have included all the necessary components to recompile and run the test case. You may need to include an RM/COBOL configuration file.

When submitting your test case, please include the following items:

1. **README text file that explains the problems.** This file must include information regarding the hardware, operating system, and versions of all relevant software (including the operating system and all Micro Focus products). It must also include step-by-step instructions to reproduce the behavior.
2. **Program source files.** We require source for any program that is called during the course of the test case. Be sure to include any copy files necessary for recompilation.

3. **Data files required by the programs.** These files should be as small as possible to reproduce the problem described in the test case.

Chapter 1: Installation and Verification

This chapter lists the hardware and software required to use RM/InfoExpress for TCP/IP (Transmission Control Protocol/Internet Protocol), detailing the differences between the server and client program requirements. Chapter 1 also provides instructions for setting up and installing RM/InfoExpress on Windows and UNIX, and outlines procedures for verifying that RM/InfoExpress is properly installed.

System Requirements

This section describes the requirements necessary for installing the RM/InfoExpress server and client components. The version of RM/InfoExpress that you have purchased is for a particular combination of hardware and operating systems. Several items listed below vary depending on the actual version of the product that you have purchased.

Before you can use RM/InfoExpress, your personal computer configuration must meet or exceed the requirements set forth in this section.

RM/InfoExpress Server Program

The following sections list the minimum hardware and software requirements for running the RM/InfoExpress server program.

Required Hardware

One of the following hardware systems is required to install the RM/InfoExpress server program:

- An IBM PC or compatible machine capable of running Microsoft Windows Server 2008.
- A machine capable of running a supported UNIX or Linux operating system.

Required Software

The RM/InfoExpress server program is supported on the following operating systems:

- Microsoft Server 2008 R2 or later, Windows 7 SP 1 or later.
- UNIX (or UNIX-based) servers:
 - HP-UX 11.31
 - IBM AIX 7.2
 - Linux (5.5 kernel or later, 32-bit and 64-bit)
 - On Linux, ncurses 5 is required. Note that in later versions of Linux, ncurses 5 is no longer automatically installed with the installation of Linux and will require a manual installation of ncurses 5.
 - Sun Solaris SPARC (5.10) and Intel x86-64 (5.10)

RM/InfoExpress consists of two server programs:

- The RM/InfoExpress for Microsoft Windows server software contains the following files:
 - the main program, **rmsrvtcp.exe**
 - the server display (or screen handler) program, **rmdistcp.exe**
- The RM/InfoExpress for UNIX server software contains the following files:
 - the main program, **rmservtcp**
 - the server display (or screen handler) program, **rmdisptcp**
 - a file security parameter file update utility program, **ixsecure.cob**

RM/InfoExpress Client Program

By default, the RM/InfoExpress client program (**rmtcp32.dll** on Windows or **librminfox.so** on UNIX) is installed by the standard installation procedure for RM/COBOL for Windows and RM/COBOL for UNIX. The hardware and software system requirements for the RM/InfoExpress client program are exactly the same as the system requirements for the RM/COBOL runtime system (**runcobol**). For more information, see the appropriate chapters on installation and system considerations for UNIX and Microsoft Windows in the *RM/COBOL User's Guide*.

Setup and Installation

The section includes setup guidelines and instructions for installing the RM/InfoExpress server and client components.

The RM/InfoExpress for TCP/IP media contains a number of individual files and programs. The media contains a README file, which lists the actual files and programs delivered. For a list of known problems and recovery tips, refer to the section “Problems in This Release” in the README file.

Note The RM/InfoExpress server software should be installed only on the machine on which it is to run. If appropriately licensed, the RM/COBOL runtime system with the

RM/InfoExpress client software may be installed on a UNIX server machine or a Windows server machine.

RM/InfoExpress Servers

This section describes how to set up and install the RM/InfoExpress server software on Windows servers and UNIX server machines.

Setting Up the TCP/IP Package for RM/InfoExpress Servers on Windows and UNIX

Before you install the RM/InfoExpress server program, you must first ensure that the complete TCP/IP package has been installed and set up on your Windows and UNIX server machines.

Make certain that the **hosts** and **services** files are included. On Windows, these files are usually in the `\windows-directory\system32\drivers\` directory, where *windows-directory* is the name of the directory where Windows is installed. On UNIX, the files are usually named `/etc/hosts` and `/etc/services`.

- The **hosts** file lists the IP (Internet Protocol) addresses and host name(s) of all machines (clients and servers) that are connected to your network. As an alternative to using a **hosts** file on every machine, you can use DSN (Domain Name Service). One machine or a few machines run DNS; all of the other machines on the network access DNS to resolve names to IP addresses.

CAUTION On some machines, the RM/InfoExpress server program may terminate with a “Signal (11) caught” (segmentation fault) error message when accessed by a client if the `/etc/hosts` file on the server machine does not contain the entries required by RM/InfoExpress. The client would most likely receive a “COBOL I/O error 30, Runtime Library error 12006.” The solution to the problem is to add the entries to the `/etc/hosts` file.

- The **services** file lists the service name and port number/protocol of all available services on both Windows (`c:\Windows\System32\drivers\etc\services`) and UNIX (`/etc/services`) servers. On Windows, the installation updates this file. On UNIX, the **rmaddsvc** program will update the **services** file during setup in order to add the following line:

```
RMFileServer 21069/tcp
```

No other line may contain `RMFileServer` (in any mixture of uppercase or lowercase letters), and no other line may contain the port number 21069. If port number 21069 is already in use, select another unused port number. We recommend that you choose a port number between 5000 and 32000.

Note The user must ensure that the `RMFileServer` line in the **services** file is identical on every machine (clients and servers) on the network.

Installing RM/InfoExpress Server on Windows

You can install the RM/InfoExpress server program on Windows by using the following methods:

- [Software Licenses and Downloads for Windows](#) (as described below)

- [CD-ROM Installation](#) (on page 11)

To verify that the installation was successful, see [Verifying the RM/InfoExpress Server](#) (on page 15) and [Verifying RM/InfoExpress Windows Client and Server Communication](#) (on page 18).

Software Licenses and Downloads Installation for Windows

Note You must have an Internet connection and an Internet browser installed to proceed with this latter method of installation.

The email containing notification of your Software Licenses and Downloads contains an attachment, a file named **liant.lic**. This file is a license certificate authorizing you to install the purchased software. We recommend that you create a directory on your machine to store the license certificates for your Micro Focus products and save the **liant.lic** attachment to this directory with a name that is meaningful to you.

The RM/InfoExpress server program is available as a download from the Micro Focus Software Licenses and Downloads web site in two formats: Windows Self-Extracting EXE and ISO CD Image. From the web site, simply follow the download and decompress instructions for the file format selected, and then perform the installation instructions for that format, as outlined below.

- **Windows Self-Extracting EXE.** After downloading and decompressing the deliverables, and creating the installation components directory from the Windows Self-Extracting EXE format, follow these steps to install the RM/InfoExpress server program on Windows:

Note When the Windows Self-Extracting EXE is decompressed and the installation components directory is created, the **RM-Install** program should start automatically. If this is the case, proceed to step 6. Otherwise, begin with step 1. Be sure to login as Administrator and close any other applications that may be running before you begin.

1. Place a copy of your RM/InfoExpress license certificate, **liant.lic**, in the directory containing the installation components.
2. Click **Start**, and then click **Run**. In the Run dialog box, click the **Browse** button.
3. In the Browse dialog box, navigate to the directory containing the installation components.
4. Click on the file, **RM-Install**, and then click **Open**.
5. In the Run dialog box, click **OK**.
6. The **RM-Install** program begins executing. Follow the instructions presented on the screen and press the **Next** button to advance through the various pages.
7. On the Software License Agreement page, you must click “I accept the terms in the license agreement” in order to continue with the installation.
8. On the License Certificates page, the license certificate file for the product being installed is displayed. Do one of the following:
 - If the license certificate for RM/InfoExpress server software being installed is present in the list area, press the **Next** button.
 - If the license certificate for the RM/InfoExpress server software being installed is *not* present in the list area:
 - a. Press the **Add** button.

- b. In the Select License Certificates dialog box, navigate to the directory containing the license certificate file for the RM/InfoExpress server software being installed and select the filename for the license certificate. (This license file, named **liant.lic**, is attached to the original electronic software delivery email for the product.)
 - c. Press the **Open** button and then press **Next**.
 9. On the Installation Type page, do one of the following:
 - Select the “Standard Installation” option to install all the components of all the license certificates listed on the License Certificates page immediately, using their default settings. Press the **Install** button.
 - Select the “Custom Installation” option to select specific components (for those products with multiple components) of all license certificates listed on the License Certificates page, and install them, changing their default installation settings, as necessary.Follow the custom installation instructions presented on the remaining pages. On the Ready to Begin Installations page, press the **Install** button.
When the installation for the RM/InfoExpress server components starts, follow the additional instructions presented by the installation program.
 10. When either the standard or custom installation is complete, click the **Finished** button on the Installation Status page.

Note The RM/InfoExpress server is installed and run as a Windows service.

- **ISO CD Image.** The download format for ISO CD Image contains the full RM/InfoExpress product CD. Use CD-ROM Burning software to create the physical CD-ROM media or mount the iso with other appropriate software. Follow the instructions described in [CD-ROM Installation](#) (on page 11) to install your product.

CD-ROM Installation

After downloading and decompressing the deliverables, and creating the installation components directory from the ISO CD Image format, follow these steps to install the RM/InfoExpress server program on Windows:

1. Log in as Administrator. Micro Focus also recommends that you close any other applications that may be running.
2. Insert the RM/InfoExpress Server Program CD-ROM in the appropriate CD-ROM drive.
3. Do one of the following:
 - If the installation program starts automatically, proceed to Step 4.
 - If the installation program does *not* start automatically, click **Start**, and then click **Run**. In the Open text box of the Run dialog box, type the following:

```
d:RM-Install
```

where, *d* is the drive letter of the CD-ROM drive. Click **OK**.
4. The **RM-Install** program begins executing. Follow the instructions presented on the screen and press the **Next** button to advance through the various pages.

5. On the Software License Agreement page, you must click “I accept the terms in the license agreement” in order to continue with the installation.
6. On the License Certificates page, the license certificate for the product being installed is displayed. Do one of the following:
 - If the license certificate for the RM/InfoExpress server software being installed is present in the list area, press the **Next** button.
 - If license certificates for any products you do *not* wish to install are present in the list area, select them and press the **Remove** button. Then, press the **Next** button.
 - If the license certificate for the RM/InfoExpress server software being installed is *not* present in the list area:
 - a. Press the **Add** button.
 - b. In the Select License Certificates dialog box, navigate to the directory containing the license certificate file for the RM/InfoExpress server software being installed and select the filename for the license certificate.

This license file, usually named **liant.lic**, is included on the license Software Activation Information email.
 - c. Press the **Open** button and then press **Next**.

Note The **liant.lic** license certificate file can be copied to a location on a hard drive and that location can be specified during installation. We recommend that you create a separate directory on your machine to store the license certificate files for all of your Micro Focus products and save those files with a name that is meaningful to you.

7. On the Installation Type page, do one of the following:
 - Select the “Standard Installation” option to install all the components of all the license certificates listed on the License Certificates page immediately, using their default settings. Press the **Install** button.
 - Select the “Custom Installation” option to select specific components (for those products with multiple components) of all license certificates listed on the License Certificates page, and install them, changing their default installation settings, as necessary.

Follow the custom installation instructions presented on the remaining pages. On the Ready to Begin Installations page, press the **Install** button.

When the installation for the RM/InfoExpress components starts, follow the additional instructions presented by the installation program.
8. When either the standard or custom installation is complete, click the **Finished** button on the Installation Status page.

Note The RM/InfoExpress server is installed and run as a Windows service.

Installing RM/InfoExpress Server on UNIX

You can install the RM/InfoExpress server program on UNIX by using the following methods:

- [Software Licenses and Downloads Installation for UNIX](#) (as described below)

To verify that the installation was successful, see [Verifying the RM/InfoExpress Server](#) (on page 15) and [Verifying RM/InfoExpress UNIX Client and Server Communication](#) (on page 21).

Software Licenses and Downloads Installation for UNIX

Note You must have an Internet connection and an Internet browser installed to proceed with this latter method of installation.

The email containing notification of your Software Licenses and Downloads contains an attachment, a file named **liant.lic**. This file is a license certificate authorizing you to install the purchased software. We recommend that you create a directory on your machine to store the license certificates for your Micro Focus products and save the **liant.lic** attachment to this directory with a name that is meaningful to you.

The RM/InfoExpress server program is available as a download from the Micro Focus Electronic Software Delivery web site in two formats: UNIX GUNZIP TAR and ISO CD Image. From the web site, simply follow the download and decompress instructions for the file format selected, and then perform the installation instructions for that format, as outlined below.

- **UNIX GUNZIP TAR.** After downloading and decompressing the deliverables, and creating the installation components directory from the UNIX GUNZIP TAR format, follow these steps to install the RM/InfoExpress server program on UNIX:
 1. Place a copy of your RM/InfoExpress license certificate, **liant.lic**, in the directory containing the installation components.
 2. Change to the directory containing the installation components. For example, enter:

```
cd /RMStage
```

3. Execute the installation script using the following command:

```
sh ./install.sh
```

4. Follow the prompts and instructions on the screen to complete the installation.

Messages are displayed periodically indicating the status of the installation. Following the installation, the RM/InfoExpress server will be configured to autostart when the UNIX machine is rebooted, and the installation will automatically start it.

RM/InfoExpress is distributed with a default configuration that will satisfy your system requirements. Additional configuration options for your system are discussed in [Appendix D: Configuring RM/InfoExpress](#) (see page 79).

Uninstallation for UNIX

To remove an installation of RM/InfoExpress on UNIX, perform the following steps:

1. Login as root.
2. Change directory to the direction in which the RM/InfoExpress server was installed.
3. Execute the following command:

```
sh ./uninstall.sh
```

The uninstall script will shut down the server (if it is running), remove the auto start scripts, uninstall the licenses, remove the entry in the services file (if it was modified), and remove the files and the installation directory. Any files in the installation directory that were modified after the installation will not be deleted.

License File

The Micro Focus license file, **liant.lic**, is a license certificate authorizing you to install the purchased software.

RM/InfoExpress Clients

This section describes how to set up and install the RM/InfoExpress client software on Windows and UNIX workstations.

Setting Up the TCP/IP Package for RM/InfoExpress Clients on Windows and UNIX

In order for RM/InfoExpress clients to access the RM/InfoExpress server, you must make sure that you have installed and configured the TCP/IP communication protocol package correctly on Windows and UNIX client workstations.

For both Windows and UNIX implementations, you may need to modify the **hosts** file and **services** file:

- The **hosts** file lists the IP (Internet Protocol) addresses and host name(s) of machines . This is as an alternative to using DNS (Domain Name Service).
- The **services** file lists the service name and port number/protocol of all available services. The following is the entry that should have been placed in the services file:
RMCFileServer 21069/tcp

On UNIX, the **rmaddsvc** program will automatically update the services file during setup.

On Windows, the installation will modify the **windows\system32\drivers\etc\services** file with the server and port information.

If this is a reinstallation or you have problems with the Verify process, check that no other line contains RMCFileServer (in any mixture of uppercase or lowercase letters) and that no other line contains the port number 21069. If port number 21069 is already in use, select another unused port number. We recommend that you choose a port number between 5000 and 32000.

Note Ensure that the RMCFileServer line in the **services** file is identical on every machine (clients and servers) on the network.

Installing RM/InfoExpress Clients on Windows and UNIX

The RM/InfoExpress Windows client program (**rmtcp32.dll**) is installed by default when you select the “Standard Installation” option when installing the RM/COBOL Runtime System for Windows. However, if you did not install it, run the RM/COBOL Runtime System installation procedure again, selecting the “Custom Installation” option to install only the

External Access Method feature under the Runtime feature. If you wish to run the client verification program, choose the Verification Suite option also. To verify that the installation was successful, see [Verifying the RM/InfoExpress Windows Client](#) (on page 17).

The RM/InfoExpress UNIX client program (**librminfo.so**) is installed by default with RM/COBOL Runtime system for UNIX. The RM/COBOL for UNIX runtime uses the **librminfo.so** support module (a shared object) to provide access to the RM/InfoExpress server. To verify that the installation was successful, see [Verifying RM/InfoExpress UNIX Client and Server Communication](#) (on page 21).

Verification / Quick Start

For both the RM/InfoExpress client and server software components, the first step in system verification is to confirm that the TCP/IP network software is running correctly on the client machine as well as the server machine.

For RM/InfoExpress client verification, follow all the vendor's recommendations making sure you have properly configured the TCP/IP network and that the software is running correctly. System utilities, such as **ping**, can help ensure proper configuration and/or communication between the client and server machines.

Verifying the RM/InfoExpress Server

The following procedures verify that the RM/InfoExpress server programs have been installed correctly for Windows and UNIX operating systems, and that they can run properly.

Note Only *one* RM/InfoExpress server program may be active on any given server machine.

Windows Server

The RM/InfoExpress server for Windows is installed as, and is intended to be run as, a Windows service, under the direction of the Windows Service Control Manager (SCM).

The RM/InfoExpress server is configured to start *automatically* using the *System* account. The RM/InfoExpress server can be reconfigured to start manually if desired. This is controlled by the standard *startup property* on the service's properties pane.

The user that the service runs as can also be configured on the service's properties pane.

Note For information on specifying server configuration options on Windows, see the following topics:

- [Windows Server Command Line Options](#) (on page 27)
- [Windows Server Display Command Line Option](#) (on page 28)
- [Appendix D: Configuring RM/InfoExpress](#) (on page 79)

Starting the RM/InfoExpress server:

Windows:

Start the **RM/InfoExpress** or **RM/InfoExpress-64** service by doing one of the following:

- Use the Services panel to start/stop/restart the service
- Or, as administrator run the following command

```
net start RMInfoExpress
```

or

```
net start RMInfoExpress64
```

- Or, as administrator invoke the start menu shortcut



The service runs the `rmsrvtcp.exe` located in the `RMInfoExpressv12[-64]` directory as the specified user.

The RM/InfoExpress server program for Windows, runs under the System account by default and has access to any resources that this account is permitted to use. To change the account under which the server program runs, see [Configuring the RM/InfoExpress Windows Server Program](#) (on page 26).

Unix:

On the UNIX server machine, the RM/InfoExpress UNIX server program, **rmservertcp**, has been configured by the installation to automatically start. The autostart script is installed in the proper directory for the version of UNIX. For example, on Linux, this is in the `/etc/rc.d/init.d` directory with the name `rmservertcp`:

```
/etc/rc.d/init.d/rmservertcp
```

This script accepts the following commands as a single argument:

start – Starts the RM/InfoExpress server program

stop – Stops the RM/InfoExpress server program

status – Displays the status of the RM/InfoExpress server program's processes

restart – Stops the RM/InfoExpress server program and then starts it again.

condrestart – If the RM/InfoExpress server program is currently running, it will be stopped and started.

Use the restart option after configuration changes to cause the changes to take effect.

Server Display

Starting on Windows:

The Server Display can be started a couple of ways. We suggest one of the following:

- Run the command with the start menu shortcut



- Run the `rmdistcp.exe` from the RMInfoExpress installation directory
Note: run with the `-t` option if you wish to be able to issue a terminate server command. Run with the `-p` option if the ini files have specified using a port other than the default.

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (see page 38). This indicates that the server is running and ready to process requests.

Note: The Server Display only allows monitor the activity on the server. It does not affect the communication between the client and server. It does not need to be running for the server to function.

Starting on UNIX:

On the UNIX server machine, start the RM/InfoExpress Server Display program, `rmdisptcp`, by entering the following commands:

```
/usr/rminfo/rmdisptcp -t
```

Using:

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (see page 38). The server is ready to process requests from client machines. If the server main screen does not appear, check that no other RM/InfoExpress server program is already running on the machine. If other messages are displayed, contact Micro Focus Customer Care.


Note For information on specifying server configuration options on UNIX, see the following topics:

- [UNIX Server Command Line Options](#) (on page 24)
- [UNIX Server Display Command Line Option](#) (on page 25)
- [Appendix D: Configuring RM/InfoExpress](#) (on page 79)

Verifying WinSock on the RM/InfoExpress Windows Client

If you choose both the External Access Method and Verification Suite features when installing RM/COBOL for Windows, a program-item icon labeled **ixverify** is created in the RM Runtime V12 [(64-bit)] start menu folder. Choose this icon to invoke the RM/InfoExpress Windows client verification program. The RM/InfoExpress Client WinSock Info message box is displayed in the center of the screen, as illustrated in [Figure 1](#).

Figure 1: RM/InfoExpress Client WinSock Info Message Box



If no message box appears, the RM/InfoExpress Windows client software is not properly installed or started. Check that the RM/InfoExpress Windows client DLL file (**rmtcp32.dll**) exists in your application installation directory.

Note This client verification does not attempt to connect to any server. It simply verifies that the Windows Sockets implementation is sufficient to allow the RM/InfoExpress Windows client DLL to be loaded and run.

Verifying RM/InfoExpress Windows Client and Server Communication

The following procedures verify that the RM/InfoExpress Windows client program can correctly communicate with the RM/InfoExpress server program using the TCP/IP communication protocol. We recommend that you first read Chapter 3: *Installation and System Considerations for Microsoft Windows*, in the *RM/COBOL User's Guide*, for more information.

1. Configure and start the RM/InfoExpress server program on the server machine:
 - a. Edit the `rmixsrvr.ini` file
 - If the server is a windows machine, then the `rmixsrvr.ini` file will be located in the `%ALLUSERSPROFILE%` directory (usually `c:\ProgramData`) at the path `Micro Focus\RM\RMInfoExpressv12 [-64]` along with the client configuration file (`rmixclnt.ini`).
Previous versions had placed these files in the program directories. This has been changed due to the unwritable nature of program directories.
 - On UNIX, the `rmixsrvr.ini` file is installed in the installation directory (usually `/usr/rminfox`)

The Server inifile needs to be configured to identify the location of the Shared drive and folder. Edit the file by removing the comment character (`:`) from the entry in the [Sharing] section for *Shared*.

```
Shared=c:\myshare
```

The default directory for the verification demo is set to `c:\myshare`, but you may change this if you like.

Save the `rmixsrvr.ini` file.

- b. Ensure that the directory specified for *Shared* in `rmixsrvr.ini` is created and that it is writable by the Server process's user (typically System).
The directory must exist on the server machine, and the RM/InfoExpress server user must have read and write permissions to it for the demo to succeed.

- c. Start / restart the server to incorporate configuration file changes:
see [Starting the RM/InfoExpress server](#)
2. On the Windows client (which can be the same machine as the server for verification purposes), ensure that RM/COBOL is installed. The RM/InfoExpress client is installed with RM/COBOL runtime. The client consists of the rmtcp32.dll in the RM/COBOL installation directory and the rmixclnt.ini installed in
`%ALLUSERSPROFILE%\Micro Focus\RM\RMInfoExpressv12[-64]`

On the Windows client, run the *infoxmo* program from the RM/COBOL start menu




You should first get the *WinSock Info* message (as described in [Verifying the RM/InfoExpress Windows Client](#) on page 17) indicating that the rmtcp32.cfg file was found in the expected location.

This message box is displayed because the `OPTIONS='I'` keyword is specified on the `EXTERNAL-ACCESS-METHOD` configuration record in the rmtcp32.cfg file. In a production environment, omit `OPTIONS='I'` so that the message box will not be displayed.

If the WinSock Info message did not appear, examine rmtcp32.cfg file and the *infoxmo* shortcut's properties. Below are some default values for 32 bit and 64 bit installations if files were installed with the standard setup. Check that the files specified exist.

- 32-bit *infoxmo* short cut (assumes 32-bit RM/COBOL): "`C:\Program Files (x86)\Micro Focus\RM\RMCOBOLv12\runcobol.exe`"
"`C:\Users\Public\Documents\Micro Focus\RM\InfoExpress\infoxmo.cob`"
`x="C:\Users\Public\Documents\Micro Focus\RM\InfoExpress\rmtcp32.cfg`
- 64-bit *infoxmo* short cut (assumes 64-bit RM/COBOL as well): "`C:\Program Files\Micro Focus\RM\RMCOBOLv12-64\runcobol.exe`"
"`C:\Users\Public\Documents\Micro Focus\RM-64\InfoExpress\infoxmo.cob`"
`x="C:\Users\Public\Documents\Micro Focus\RM-64\InfoExpress\rmtcp32.cfg`

3. The *infoxmo* program will display.



4. Enter "2" to Verify RM/InfoExpress
Selecting option 2, will result in the prompt:
Enter remote directory where files are to be created
(Example: `\\Server\InfoxDir`)
5. Enter *localhost*, the DNS name or the IP address of the remote server in place of *Server*. Use *Shared* as the directory (if you did not change the default name in the ini file we edited above), and hit return.

For example: \\localhost\Shared

6. Expected output.
The infoxmo verification program creates one indexed file (inxfl) and performs five tests.

The resulting output should inform you of timings associated with 5 operations (WRITE-SEQ, READ-SEQ, READ-RNDM, REWRITE-RNDM, DELETE-RNDM).

If you get an error, unfortunately that will terminate the demo. You should be able to get some valuable information from the pop-up window and the message on the bottom of the application's screen.
7. When the five tests are complete, the "Type any key to continue . . ." prompt is displayed. At this point, RM/InfoExpress Windows client and server communication verification is successfully complete.

You may run other tests (*) in the verification program, run test number 2 specifying a different server, or exit the program.

* If the program was not run as administrator (which it does not need to be for the InfoExpress verification), running test "1" may result in an error as it will try write a file in the "current directory" which will probably not be writable.

Troubleshooting

Some common problems and the resulting error message that would be displayed by the infoxmo program:

- a. If a "COBOL I/O error 30, Runtime Library error 11004" is displayed, the server name has probably been entered incorrectly. Click OK or press Enter. Return to Step 2 and then specify the correct server name in Step 5. If the server name was correct, check that the **hosts** file (or DNS) contains the server name and that the **services** file contains the proper [RMCFfileServer line](#) (see page 14).
- b. If "COBOL procedure error 204" is displayed, the server name is correct but the remaining path is incorrect. Click OK or press Enter. Return to Step 2 and then specify the correct pathname in Step 5.
- c. Other return code values and other error codes are described in the *RM/COBOL User's Guide*, and in [Appendix A: Messages](#) (see page 63) of this manual. If an error message occurs, check the following:
 - The status of the RM/InfoExpress server. (Is it still running?)
 - The share on the server machine of the **infoxmo** verification program.
 - The server name in your **hosts** file.
 - The RMCFfileServer entry in your **services** file.

If you cannot determine the cause of the problem and correct it, contact Micro Focus Customer Care.

Verifying the RM/InfoExpress UNIX Client

To verify that the RM/InfoExpress UNIX client shared object program can be loaded, execute the RM/COBOL runtime with the -v option to display the banner with a list of support modules loaded by the RM/COBOL runtime system.

```
runcobol xxx -v
```

The shared object, **librminfo.so**, should be listed under the “Dynamic libraries loaded” section, as illustrated below.

```
RM/COBOL Runtime - Version nn.nn for IBM AIX.  
RM/COBOL Runtime System issued to any Company Name.  
Configured for one user.  
Copyright (c) 1985-2nnn by Micro Focus. All rights reserved.  
Registration Number: 8C-1000-15537-0001  
  
RM/COBOL: Dynamic libraries loaded:  
($EXEDIR=.)  
$EXEDIR/librmterm.so - Termino Terminal Interface - Version nn.nn.  
$EXEDIR/librminfo.so - RM/InfoExpress Client - Version nn.nn.
```

If the **librminfo.so** shared object does not appear in the Dynamic libraries loaded list, then the RM/InfoExpress UNIX client is not properly installed. Check that the RM/InfoExpress UNIX client shared object (**librminfo.so**) exists in the same directory as the RM/COBOL runtime (**runcobol**).

Verifying RM/InfoExpress UNIX Client and Server Communication

The following procedures verify that the RM/InfoExpress UNIX client program can correctly communicate with the RM/InfoExpress server program using the TCP/IP communication protocol. We recommend that you first read Chapter 2: *Installation and System Considerations for UNIX*, in the *RM/COBOL User's Guide*, for more information.

1. Start the RM/InfoExpress server program running on the server machine, as described in [Verifying the RM/InfoExpress Server](#) (on page 15).
2. Run the verification program, **infoxdmo**, using the RM/InfoExpress UNIX client program, **librminfo.so**, by entering the following command:

```
runcobol infoxdmo
```

The shared object, **librminfo.so**, will be loaded automatically by the RM/COBOL runtime system (**runcobol**).

3. Check that your PATH environment variable is set to point to the directory where **librminfo.so** and **runcobol** are installed, and the RUNPATH environment variable is pointing to the directory where **infoxdmo.cob** is present.

Note The **infoxdmo.cob** utility program is installed with the RM/COBOL runtime. On Windows, there is a **infoxdmo** shortcut to run it.

The **infoxdmo** verification program window displays the following information:

```
RM/InfoExpress Verification Program  
1. RM/COBOL File Test  
2. RM/InfoExpress File Test  
3. Exit Program  
  
Enter test number
```

- a. If a “COBOL I/O error 30” is displayed, look at the explanation in [Appendix A: Messages](#) (on page 63) or in the *RM/COBOL User’s Guide*, for the corresponding error.
- b. For any RM/InfoExpress error, check the following:
 - The status of the RM/InfoExpress server. (Is it still running?)
 - The server name in your **hosts** file.
 - The [RMCFileServer entry](#) (see page 14) in your **services** file.

If you cannot determine the cause of the problem and correct it, contact Micro Focus Customer Care for assistance.

4. At the “Enter test number” prompt, type 2 and press Enter. The following prompt is displayed:

```
Enter remote directory where files are to be created.
```

5. Enter the name of the directory on the RM/InfoExpress server where the files are to be created. For example:

```
//server/usr/rminfox
```

Note You may type either backslashes (\) or forward slashes (/) to separate the edgenames of the path, but do not mix them. Notice the double backslashes or double forward slashes at the beginning. Substitute the actual machine name (in uppercase) of your server machine (where the RM/InfoExpress server program is running as described in Step 1) for *server*. This name is usually displayed as Machine ID at the bottom of the server main screen, but it is whatever name is specified in your **hosts** file or known to your DNS that maps to the Internet Protocol address of the server machine.

The directory must already exist on the server machine and the RM/InfoExpress server must have read and write permissions to it.

The **infoxdmo** verification program creates one indexed file (**inxfl**) and performs five tests: write sequential, read sequential, read random, rewrite random, and delete random. Timing information for each test is shown.

6. When the five tests are complete, the “Type any key to continue...” prompt is displayed. At this point, RM/InfoExpress client and server communication verification is complete.

You may run other tests in the verification program, run test number 2 specifying a different server, or exit the program.

Chapter 2: Configuring and Running the RM/InfoExpress Server

This chapter describes the procedures required to configure and run (start) the RM/InfoExpress servers for UNIX and Windows.

Server Configuration Options

RM/InfoExpress server configuration options can be set either in the server configuration file (**rmixsrvr.ini**) or on the command line. The command line specification overrides the configuration file setting. While Micro Focus recommends that you specify the configuration options in the server configuration file, the ability to specify configuration options on the command line ensures backward compatibility with previous releases, and enables special, temporary invocations of the server without affecting the settings in the configuration file. For example, there may be times when it would be helpful to specify the **-d** option in order to create a debug file to send to Micro Focus Customer Care.

All command line options have a configuration file equivalent. However, starting with version 2.1, all new program options must be specified in the configuration file. There is no command line equivalent.

For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 79).

Starting the RM/InfoExpress UNIX Server Program

On the UNIX server machine, start the RM/InfoExpress UNIX server and server display (screen handler) programs, **rmservertcp** and **rmdisptcp**, by entering:

```
/usr/rminfox/rmservertcp [-option]
```

```
/usr/rminfox/rmdisptcp [-option]
```

Notes

- The RM/InfoExpress UNIX server display program, **rmdisptcp**, monitors the server activity and does not affect the communication between the client and server. On some machines, the server daemon may take a few seconds to initialize the underlying network. If the server display (**rmdisptcp**) is invoked immediately after the server is started, the server display program will wait until the network initialization is complete.
- If you start **rmservertcp** in a UNIX window opened using a telnet session on your workstation, then you may not be able to close the telnet session until the server is terminated. Always start the server from a terminal connected to the UNIX machine.

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (on page 38). The server is ready to process requests from client machines. If the server main screen does not display, follow the instructions in [Verifying the RM/InfoExpress Server](#) (on page 15).

The following sections describe the server program and server display program command line options.

UNIX Server Command Line Options

Command line options of the RM/InfoExpress UNIX server program (**rmservertcp**) can be any of the following:

- **-c n|u|l**. Indicates how the cases of pathnames from the clients are converted. The **-c** option has three values:
 - **-c n**. Indicates that no filename mapping is performed. This is the default value.
 - **-c u**. Indicates that the entire filename is mapped to uppercase before the Open request is attempted. The option may be specified as **-c upper**, if desired.
 - **-c l**. Indicates that the entire filename is mapped to lowercase before the Open request is attempted. The option may be specified as **-c lower**, if desired.

Note The **-c** command line option is equivalent to the `ConvertFileName` configuration option, which is discussed in [UNIX Server-Specific Configuration Options](#) (on page 89). The command line option overrides the configuration option.

- **-d pathname**. This option causes the file *pathname* to be created and trace information to be written into it. After the RM/InfoExpress server program is terminated, send this file to Micro Focus Customer Care for further investigation. Use this option only when you are investigating a problem with the help of Micro Focus Customer Care. Under normal conditions, using this option affects server operations negatively.

Note The **-d** command line option is equivalent to the `InfoxDebug` configuration option, as described in [Common Configuration Options](#) (on page 81). The command line option overrides the configuration option.

- **-k dddd**. Indicates the maximum number of clients to be served. If more clients are to be served, the server should be brought down and started again. The default value is 50. This value cannot be greater than the number of clients for which the server is licensed.

Note The **-k** command line option is equivalent to the `UseCount` configuration option, which is described in [Common Server-Specific Configuration Options](#) (on page 86). The command line option overrides the configuration option.

- **-p nnnnn**. Indicates the common buffer pool size. Do not change the default value for this parameter unless instructed by Micro Focus Customer Care.

Note The `-p` command line option is equivalent to the FileBufferPool configuration option, as explained in [Common Server-Specific Configuration Options](#) (on page 86). The command line option overrides the configuration option.

- `-z nnnnn`. Indicates the maximum amount of data that can be handled by the TCP `send` function. The default value is system-dependent and has been set by Micro Focus. Do not specify this parameter unless instructed to do so by Micro Focus Customer Care.

Note The `-z` command line option is equivalent to the MaxSendSize configuration option, which is discussed in [Common Configuration Options](#) (on page 81). The command line option overrides the configuration option.

UNIX Server Display Command Line Option

The following is an option for the RM/InfoExpress UNIX server display (screen handler) program, `rmdisptcp`:

- `-t`. Indicates that the user is requesting to terminate the server or communication to a particular client. If this option is not specified, the user can terminate only the server display program. Because the server display program does not support any configuration file, this option must be specified on the command line.

For example, the following command will allow the user to terminate the server program:

```
rmdisptcp -t
```

Starting and Stopping the RM/InfoExpress Windows Server Program

On the Windows server machine, use the Services app to start and stop the RM/InfoExpress server software. By default, the server is now (v12.18) configured to be started automatically. It can be disabled or set to manual, as described in [Configuring the RM/InfoExpress Windows Server Program](#) (on page 26).

Note See the description of the command line options for the [InfoExpress server](#) and the [Windows Server Display](#) programs, beginning on page 28.

Starting/Stopping the Server

To start/stop/restart the RM/InfoExpress server for Windows:

1. Start the Windows Services app. There are a number of ways to bring this up, and each version of Windows might have a slight variation.
2. Select the **RM/InfoExpress[-64] Server** in the list of services.
3. You will have different options depending on the services current state. Select the appropriate one (Start, Stop, Restart)

Note: The server can also be terminated from within the RM/InfoExpress Server Display program (`rmdistcp.exe`) when that program is started with the `-t` option. When halted in this manner, it is possible that the Service app will not detect that the server has terminated. To

restart the server, first stop the service and then start the service again, using the methods described.

The RM/InfoExpress server program initially runs under the System account and has access to any resources that this account is permitted to use. (Most systems use the System account, rather than a user account.) To change the account under which the server program runs, see [Configuring the RM/InfoExpress Windows Server Program](#) (on page 26).

RM/InfoExpress Server Display Program

Running this program is not mandatory, but provides a nice way to view if the server is functioning correctly.

The Server Display can be started from a shortcut in the RM/InfoExpress Server group, or with the executable installed in the RMInfoExpressv12[-64] directory.

In the RM/InfoExpress folder, double-click on the **rmdistcp** icon to start the RM/InfoExpress Server Display program.

The RM/InfoExpress server main screen is displayed, as illustrated in [Figure 3: Server Display Main Screen](#) (on page 38). The server is ready to process requests from client machines. (The RM/InfoExpress Windows Server Display program, **rmdistcp.exe**, monitors the server activity and does not affect the communication between the client and server.)

Note The shortcut does run the Server Display program with the -t command line option. The -t option allows you to terminate a server or the communication to a particular client when the Server Display program is terminated.

If the server main screen does not appear, check that no other RM/InfoExpress server program is already running on the machine. If other messages are displayed, contact Micro Focus Customer Care.

Note The RM/InfoExpress Windows server program also can be launched in user mode using the icon created by default in the RM/InfoExpress program folder. To start the server, simply double-click on the RM/InfoExpress Windows server icon. (You may wish to add command line options to the Target command line in the Shortcut tab of the Properties dialog box for the icon, or you may use the command line options from a DOS command line. For more information about Windows shortcuts, see “Creating a Windows Shortcut” in Chapter 3: *Installation and System Considerations for Microsoft Windows*, in the *RM/COBOL User’s Guide*.) The server will run using the current account and will be terminated when you log out. When launched in this mode, there is also a small, 10- to 20-second delay before the server becomes active.

Configuring the RM/InfoExpress Windows Server Program

By default, the RM/InfoExpress server service is set to start automatically when Windows is started. The default user for the service is System.

Disabling the service or setting it to start manually

By default, the installation sets the RM/InfoExpress server to start automatically when Windows is started. You can disable it or set it to manual by opening the Services app, display the properties for the RM/InfoExpress Service, and set the startup type to the

appropriate value. The properties screen also has a “Log On” tab that allows you to specify a different user to run the process.

Running Under a Specific Log On Account

To configure the server to run under a specific account, take the following steps:

1. Start the Services app and find the RM/InfoExpress server in the list of services.
2. Display the properties for the RM/InfoExpress service.
3. In the Properties dialog box, select the **Log On** tab.
4. Under the **Log On As** option, select either the **Local System Account** option to run the server under the default account, or enter the name and password of a selected account to run under another account.

* On the start menu, there is a shortcut to start/restart the service as well. This shortcut should be invoked with administrator privileges.

Windows Server Command Line Options

Command line options for the RM/InfoExpress Windows server program (**rmsrvtcp.exe**), when launched from the icon or from a DOS command line, can be any of the following:

- **-d *pathname***. This option causes the file *pathname* to be created and trace information to be written into it. After the RM/InfoExpress server program is terminated, send this file to Micro Focus Customer Care for further investigation. Use this option only when you are investigating a problem with the help of Micro Focus Customer Care. Under normal conditions, using this option affects server operations negatively.

Note The **-d** command line option is equivalent to the InfoxDebug configuration option, as described in [Common Configuration Options](#) (on page 81). The command line option overrides the configuration option.

- **-k *dddd***. Indicates the maximum number of clients to be served. If more clients are to be served, the server should be brought down and started again. The default value is 50. This value cannot be greater than the number of clients for which the server is licensed.

Note The **-k** command line option is equivalent to the UseCount configuration option, which is described in [Common Server-Specific Configuration Options](#) (on page 86). The command line option overrides the configuration option.

- **-p *nnnnn***. Indicates the common buffer pool size. Do not change the default value for this parameter unless instructed by Micro Focus Customer Care.

Note The **-p** command line option is equivalent to the FileBufferPool configuration option, as explained in [Common Server-Specific Configuration Options](#) (on page 86). The command line option overrides the configuration option.

- **-z *nnnnn***. Indicates the maximum amount of data that can be handled by the TCP **send** function. The default value is system-dependent and has been set by Micro Focus. Do not specify this parameter unless instructed to do so by Micro Focus Customer Care.

Note The **-z** command line option is equivalent to the MaxSendSize configuration option, which is discussed in [Common Configuration Options](#) (on page 81). The command line option overrides the configuration option.

Windows Server Display Command Line Option

The following are options for the RM/InfoExpress Windows Server Display program, **rmdistcp.exe**:

- **-t** : Indicates that the user is requesting to terminate the server or communication to a particular client. If this option is not specified, the user can terminate only the screen display program. Because the Server Display program does not support any configuration file, this option must be specified on the command line.

For example, the following command will allow the user to terminate the server program:

```
rmdistcp.exe -t
```

- **-p** : Set when server was run with PortNumberOverride. Without this flag, while running on other than the default port, the display program will report that the server is not running, even when it is.

Chapter 3: Using RM/InfoExpress with RM/COBOL for Windows Programs

This chapter describes the procedures required to use RM/InfoExpress with RM/COBOL for Windows programs, including how to access the RM/InfoExpress Windows client program, how RM/COBOL for Windows programs point to network data files, and how to execute RM/COBOL for Windows programs for use with RM/InfoExpress.

Note For information on how to start the RM/InfoExpress server programs on either Windows or UNIX, refer to the appropriate sections in [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 23).

Accessing the RM/InfoExpress Windows Client Program

The RM/InfoExpress Windows client program is **rmtcp32.dll**. The RM/COBOL runtime system for Windows (**runcobol**) invokes the client program automatically when an EXTERNAL-ACCESS-METHOD record, specifying NAME=RMTCP32, is included in the RM/COBOL configuration file. See the EXTERNAL-ACCESS-METHOD configuration record section in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*, for more information.

Note The OPTIONS='I' keyword, which causes an informative message box to be displayed, normally should not be specified on the EXTERNAL-ACCESS-METHOD configuration record. Other client-specific configuration options are described in [Appendix D: Configuring RM/InfoExpress](#) (on page 79).

Pointing to Network Data Files

This section describes several different methods that can be used in an RM/COBOL for Windows program to specify the pathnames of remote network data files, which are to be accessed by RM/InfoExpress.

Specifying Synonyms

Generally, RM/COBOL programs contain synonyms in the *file-access-name* field of the SELECT clause. For example:

```
SELECT INX-FILE ASSIGN TO RANDOM, "inxfl"
```

The synonyms are mapped to the actual pathname before executing the RM/COBOL program.

Synonym specification depends on the operating system on which the runtime system application and the RM/InfoExpress client software are running. If you are using RM/COBOL for Windows, synonyms are specified by setting properties.

For example, to access a file on a UNIX server from a Windows client, set the following synonym:

```
inxfl=\\Unix_server\usr\infox\inxfl
```

In this example, the synonym **inxfl** points to a file **inxfl** in directory **infox** of directory **usr** on a UNIX server, **Unix_server**. It is also possible to use DOS environment variables (created with the DOS SET command) as synonyms if the Windows runtime system is started with a command line from a DOS box running under Windows. For more information, refer to the "Directory Search Sequences" section in Chapter 3: *Installation and System Considerations for Microsoft Windows*, of the *RM/COBOL User's Guide*.

Here are three examples using synonyms:

Example 1

```
inxfl=\\Unix_server\usr\infox\inxfl
```

Example 2

```
relfl=Q:\usr\infox\relfl
```

Example 3

```
inxfl=\\Win_server\SharedFiles\inxfl
```

where,

inxfl and **relfl** (specified on the left side of the SET expression) are both synonyms.

Unix_server is the name of the UNIX server accessed by RM/InfoExpress, as shown in the **hosts** file or as known by DNS.

Q is a drive letter mapped to a UNIX server.

\usr\infox\inxfl and **\usr\infox\relfl** are the pathnames on the server.

Win_server is the name of the Windows server, as shown in the **hosts** file or as known by DNS.

SharedFiles is the share name known to the Windows server running on *Win_server*.

In Examples 1 and 3, RM/InfoExpress is able to process the **inxfl** file because the pathname begins with double backslashes (\\). It could also begin with double forward slashes (//).

In Example 2, RM/InfoExpress is unable to process the **relfl** file because it is not using the appropriate naming convention. Processing, however, is handled through conventional network access.

Thus, for RM/COBOL files specified by filename only, you may access server files by using a synonym that points to a server directory.

Specifying RUNPATH Environment Variables

Specifying an RM/InfoExpress server in one of the RUNPATH components causes RM/COBOL to access the file using RM/InfoExpress. For example:

```
RUNPATH=C:\prog;N:\data;\\Unix_server\usr\data;
        \\Win_server\Shares\data
```

causes RM/COBOL to search for a file first in the directory **prog** on the local disk C; then in the directory **data** on the network drive **N**: (assuming that drive N is mapped to a network volume) using conventional network access; next in the subdirectory **data** of directory **usr** on the server **Unix_server** using RM/InfoExpress; and lastly, in the directory **data** in whatever directory is associated with the **Shares** share name on **Win_server** using RM/InfoExpress.

For more information on the RUNPATH environment variable specification, refer to the “Locating RM/COBOL Files” section in Chapter 3 of the *RM/COBOL User's Guide*.

Specifying Explicit Pathnames in the RM/COBOL Program

You must change the pathname in the SELECT clause of the RM/COBOL program for filenames that include drive specifiers, computer names, or directory paths, and that do not already point to a server directory. For example:

```
SELECT DATA-FILE ASSIGN TO RANDOM,
        "\\Unix_server\usr\infox\data.fil"
```

This type of pathname specification makes the program less portable, however, because whenever the location of the file **data.fil** changes (from one server to another), you must recompile the source program.

Specifying Complete Pathnames Using RM/COBOL Data-Names

Some RM/COBOL programs use data-names to change pathnames dynamically. For example, the SELECT statement:

```
SELECT INX-FILE ASSIGN TO RANDOM, DATA-FIL
```

In this example, DATA-FIL is the data-name defined in the DATA DIVISION, and it contains the complete pathname of the file at the time the file was opened. These data-names

must include the name of a UNIX machine or the Windows server on which an RM/InfoExpress server is running. For example, DATA-FIL could contain the following:

```
\\Unix_server\usr\infox\data.fil
```

Executing RM/COBOL Programs

Execute your RM/COBOL program by entering the following command line, as described in the “System Configuration” section of Chapter 3: *Installation and System Considerations for Microsoft Windows*, of the *RM/COBOL User’s Guide*.

```
runcobol name [option]
```

where,

name points to RM/COBOL object files.

option is any valid RM/COBOL Runtime Command option.

Before executing the **runcobol** command, set up the environment to create and access files on the server machine, and create a configuration file to define the external access method.

Execute the RM/COBOL verification suite for Windows, as described in Chapter 5: *System Verification*, of the *RM/COBOL User’s Guide*.

Chapter 4: Using RM/InfoExpress with RM/COBOL for UNIX Programs

This chapter describes the procedures required to use RM/InfoExpress with RM/COBOL for UNIX programs, including:

- How to access the RM/InfoExpress UNIX client program.
- How RM/COBOL for UNIX programs point to network data files.
- How to execute RM/COBOL for UNIX programs for use with RM/InfoExpress.

Note For information on how to start the RM/InfoExpress server programs on either UNIX or Windows, refer to the appropriate sections in [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 23).

Accessing the RM/InfoExpress UNIX Client Program

The RM/InfoExpress client shared object for UNIX is named **librminfo.so**.

By specifying the keyword NAME=NONE on the EXTERNAL-ACCESS-METHOD record in the configuration file, you can bypass the RM/InfoExpress UNIX client code in **librminfo.so**. See the EXTERNAL-ACCESS-METHOD configuration record section in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*, for more information.

Pointing to Network Data Files

This section describes several different methods that can be used in an RM/COBOL for UNIX program to specify the pathnames of remote network data files, which are to be accessed by RM/InfoExpress.

Specifying Synonyms

Generally, RM/COBOL programs contain synonyms in the *file-access-name* field of the SELECT clause. For example:

```
SELECT INX-FILE ASSIGN TO RANDOM, "inxfl"
```

The synonyms are mapped to the actual pathname before executing the RM/COBOL program.

Synonym specification depends on the operating system on which the runtime system application and the RM/InfoExpress client software are running. For example, to access a file on a UNIX server from a UNIX client, execute the following command (assuming Bourne shell) prior to invoking the client:

```
inxfl=//UNIX_SERVER/usr/infox/inxfl; export inxfl
```

In this example, the synonym **inxfl** points to a file **inxfl** in directory **infox** of directory **usr** on a UNIX server, **UNIX_SERVER**. See also the description of synonyms in the “Directory Search Sequences” section in Chapter 2: *Installation and System Considerations for UNIX*, of the *RM/COBOL User’s Guide*.

Specifying RUNPATH Environment Variables

Specifying an RM/InfoExpress server in one of the RUNPATH components causes RM/COBOL to access the file using RM/InfoExpress. For example:

```
RUNPATH=/usr/local/infox://UNIX_SERVER/usr/data://  
Win_server/Shares/data
```

causes RM/COBOL to search for a file first in the directory **/usr/local/infox** on the local disk using conventional network access; then in the directory **data** in directory **usr** on **UNIX_SERVER** using RM/InfoExpress; and lastly, in the directory **data** in whatever directory is associated with the **Shares** share name on **Win_server** using RM/InfoExpress.

For more information on the RUNPATH environmental variable specification, refer to the “Locating RM/COBOL Files” section in Chapter 2 of the *RM/COBOL User’s Guide*.

Specifying Explicit Pathnames in the RM/COBOL Program

For filenames that include directory paths and that do not already point to a server directory, you must change the pathname in the SELECT clause of the RM/COBOL program. For example:

```
SELECT DATA-FILE ASSIGN TO RANDOM,  
      "//UNIX_SERVER/usr/infox/data.fil"
```

This type of pathname specification makes the program less portable, however, because whenever the location of the file **data.fil** changes (from one server to another), you must recompile the source program.

Specifying Complete Pathnames Using RM/COBOL Data-Names

Some RM/COBOL programs use data-names to change pathnames dynamically. For example, the SELECT statement:

```
SELECT INX-FILE ASSIGN TO <RANDOM> DATA-FIL
```

In this example, DATA-FIL is the data-name defined in the DATA DIVISION, and it contains the complete pathname of the file at the time the file was opened. These data-names must include the name of a UNIX machine or the Windows server on which an RM/InfoExpress server is running. For example, DATA-FIL could contain the following:

```
//UNIX_SERVER/usr/infox/data.fil
```

Executing RM/COBOL Programs

Execute your RM/COBOL program by entering the following command line on the terminal of your UNIX client machine:

```
librminfox name [option]
```

where:

name points to RM/COBOL object files.

option is any valid RM/COBOL Runtime Command option.

Before executing the **librminfox** command, set up the environment to create and access files on the server machine.

Execute the RM/COBOL verification suite for UNIX, as described in Chapter 5: *System Verification*, of the *RM/COBOL User's Guide*.

Chapter 5: RM/InfoExpress Server Operations

The RM/InfoExpress user interface is implemented for UNIX character-based terminals and the Windows console interface. The RM/InfoExpress Server Display (screen handler) program examines information and data from the server and client, and updates the screen once every second.

CAUTION Multiple RM/InfoExpress Server Display programs, with screens other than the main screen displayed, may affect server performance. As long as a Server Display program is running with its main menu selected, it does not noticeably affect server performance.

Keyboard Functions

The following list describes the keys used in the RM/InfoExpress Server Display program.


Keyboard Functions	
Key	Action
<i>n N</i>	Any command or response may be selected by pressing the first character of the command. Case is not important. For example: S for Select file, t for Terminate, or a number, if appropriate.
Escape (Esc)	Selects No in response to a query from the command line. Also backtracks through a menu path.
Home	Returns to the RM/InfoExpress Server Display main screen.
Up Arrow	Moves the cursor up during client or file selection.
Down Arrow	Moves the cursor down during client or file selection.
Left Arrow	Moves the cursor left during the selection of menu commands and responses.
Right Arrow	Moves the cursor right during the selection of menu commands and responses.
Page Up (PgUp) or Ctrl+B	Scrolls the screen up to examine and review client and file information.
Page Down (PgDn) or Ctrl+F	Scrolls the screen down to examine and review client and file information.

Keyboard Functions	
Key	Action
Enter	Chooses the currently highlighted item for command and response selection, and for individual client or file selection.

Server Display Screen Format

Except for the main screen (illustrated on the following page), each RM/InfoExpress Server Display program screen has the same basic format, as illustrated in [Figure 2](#).

Figure 2: Server Display Screen Format



The elements of the RM/InfoExpress Server Display screen are described as follows:

- **Activity area.** The activity area contains information related to the current activity or Server Display screen.
- **Command line.** The command line, located at the bottom of the screen, shows command names, user prompts, or user queries.
- **Date.** The date area displays the current system date.
- **Product name.** The product name displays the product name and version information.
- **Time.** The time area displays the current system time.
- **Title line.** The title line displays the name of the Server Display screen.

Server Display Commands

The first screen you see when you start the RM/InfoExpress Server Display program is the RM/InfoExpress main screen, as illustrated in [Figure 3](#).

Figure 3: Server Display Main Screen

LIANT SOFTWARE CORPORATION			
RM/InfoExpress Version nn.nn			
Copyright 1986-2nnn All Rights Reserved			
Liant Software Corporation			
Registration Number: 9D-0090-10016-0016			
2:53 pm		Sunday, July 31, 2nnnn	
			Up 10 days
Active clients	4		
Open files (unique, all, max)	4	6	100
Dynamic load	0.0 %		
Messages processed	1,296		
Machine ID: MyCOMPUTER			
Command:	Clients	Files	Log
		Log	Terminate

The RM/InfoExpress Server Display main screen lists the current time, date, the uptime (in days), and identifies the RM/InfoExpress server machine (in the Machine ID field). It also provides an overview of current network activity, including the following:

- The Active clients field indicates the total number of clients currently connected to this RM/InfoExpress server. Other programs using RM/COBOL are not shown.

Note that the active client count on the main screen of the Server Display program sometimes shows a value that is more than the number of clients actually connected. This behavior is most noticeable when sessions are established and released rapidly.

- The Open files field records a count of the number of files currently open. The first number indicates the number of unique files that are currently opened. The second number indicates the total number of all files currently opened by all clients. The third number is the maximum number of open files allowed (you may increase this number by using the [FileCount option](#), described on page 87, in the server configuration file, **rmixsrvr.ini**).
- The Dynamic load field shows the percentage of CPU utilization by the server.
- The Messages processed field indicates the number of client requests honored by the server.

The command line at the bottom of the Server Display main screen contains the following command options:

- **Clients.** This command lists all clients and reports on specific clients. Clients may be selected any time the Clients field appears in the command line. For more information, see [Client Information](#) (on page 40).
- **Files.** This command lists all currently open files and reports on specific files. Files may be selected any time the Files field appears in the command line. For more information, see [File Information](#) (on page 41).
- **Log.** This command provides access to two sub-screens: Open Log and Error Log. Select log information from a command line or by pressing the letter **L** at any time. For more information, see [Open Log Information](#) (on page 43) and [Error Log Information](#) (on page 44).

- **Terminate.** This command provides a number of termination modes. Terminate may be selected any time the Terminate field appears in the command line. For more information, see also [Termination of Communication Activity](#) (on page 45).

Each command and its associated screens, prompts, and queries are described in the following sections. To return to the Server Display main screen from any of the following screens, press the letter **M** or choose **Main** from the command line.

Client Information

The Client Information screen, illustrated in [Figure 4](#), is displayed when you choose the **Clients** command from the RM/InfoExpress Server Display main screen.

Figure 4: Client Information Screen

RM/InfoExpress Version nn.nn 3:21 pm Tuesday, September 25, 2nnn				
Client Information				
Files	Client name	User name	Messages	System type
1	scoware	porting	729	UNIX
1	vogon	qa	3	UNIX
0	rs6000	support	309	UNIX
0	WCUBED	Michael	208	MS_WINDOWS

Command: **Select Client** Files Main Terminate

The Client Information screen lists all active clients by name, the number of files each client has open, the total number of messages processed for each client, and the type of operating system on which the client is running. Whenever there are more clients or files than can be displayed on a single screen, a message is displayed on the screen advising that Page Up or Page Down may be used to request the previous or next screen.

Use the command **Select Client** to select a particular client in order to see information that is more detailed. Press Enter or the letter **S** to choose the **Select Client** command. The following prompt is displayed on the command line:

```
Select Client to display (using PgUp, PgDn, or Arrow keys)
```

Use Page Up, Page Down, or the arrow keys to select a client and press Enter. The Client Files screen is displayed, as illustrated in [Figure 5](#).

Figure 5: Client Files Screen

```
RM/InfoExpress Version nn.nn          3:22 pm          Tuesday, September 25, 2nnn
-----
Client Files
-----
ga@vogon has      1 files open:          3 messages
-----
ORG  OPEN  ACCESS  FILENAME
-----
INX  I-O   Dynamic  c:\rminfo\x\rmqa\INXFA
-----
Command:  Clients      Files      Main      Terminate
```

The Client Files screen shows the total number of files currently opened by the client, and the total number of messages passed between the client and the server. For each open file, the Client Files screen also shows the following information.

- The ORG column indicates the file organization:
 - INX (Indexed)
 - SEQ (Sequential)
 - REL (Relative)
- The OPEN column indicates the type of open mode:
 - I-O (Input/Output)
 - Input
 - Output
 - Extend
- The ACCESS column indicates the type of access:
 - Dynamic
 - Sequent(ial)
 - Random
- The FILENAME column indicates the absolute pathname.

File Information

The File Information screen, illustrated in [Figure 6](#), is displayed when you choose the **Files** command from the RM/InfoExpress Server Display main screen.

Figure 6: File Information Screen

```
RM/InfoExpress Version nn.nn          3:23 pm          Tuesday, September 25, 2nnn
-----
File Information
-----
Open count   File name
-----
           1   c:\rminfox\rmqa\INXFA
           1   d:\rminfox\PINKFL
-----
Command:      Clients      Select File      Main      Terminate
```

The File Information screen lists the absolute pathname for each file and the number of times each file has been opened. Whenever there are more clients or files than can be displayed on a single screen, a message is displayed on the screen advising that Page Up or Page Down may be used to request the previous or next screen.

Use the command **Select File** to select a particular file in order to see information that is more detailed. Press Enter or type the letter **S** to choose the **Select File** command. The following prompt is displayed on the command line:

```
Select file to display (using PgUp, PgDn or Arrow keys)
```

Use Page Up, Page Down, or the arrow keys to select a file and press Enter. The File Clients screen is displayed, as illustrated in [Figure 7](#).

Figure 7: File Clients Screen

```
RM/InfoExpress Version nn.nn          3:24 pm          Tuesday, September 25, 2nnn
-----
File Clients
-----
c:\rminfox\rmqa\INXFA open           1 times
-----
ORG  OPEN  ACCESS  USERNAME
-----
INX  Input  Sequent  qa@vogon
-----
Command:      Clients      Files      Main      Terminate
```

The File Clients screen shows the number of clients that have opened this file since the server was initiated and lists the clients that currently have the file open. In addition to the user name of the client (USERNAME), this screen indicates the file organization (ORG), the type of open mode (OPEN), and the type of access (ACCESS) of the client. (For more explanation of [these columns](#), see page 41.)

Open Log Information

The Open Log screen, illustrated in [Figure 8](#), is displayed when you choose the **Log** command from the RM/InfoExpress Server Display main screen, and then choose the **Open Log** command or press the letter **O**. The Open Log screen displays information about a maximum of 24 previous opens by the server, beginning with the latest open.

Figure 8: Open Log Screen

RM/InfoExpress Version nn.nn		3:25 pm	Tuesday, September 25, 2nnn		
Open Log					
Client/User	File name	Error	Exist?	Org	Time
scoware porting	d:\rminfox\PINXFL		Yes	INX	15:15:51
WCUBED michael	c:\rminfox\seqfl		Yes	SEQ	15:15:15
WCUBED michael	c:\rminfox\seqfl		Yes	SEQ	15:15:15
WCUBED michael	c:\rminfox\seqfl		Yes/No	SEQ	15:15:15
WCUBED Michael	c:\rminfox\seqfl	35,01	Yes	SEQ	15:15:15
HEADY	d:\rminfox\inxfl	35,01	Yes	INX	15:12:33
Rs6000 support	c:\rminfox\relfl		Yes	REL	15:10:19
Rs6000 support	c:\rminfox\relfl		Yes	REL	15:10:16
PgDn (Ctrl-F) for more					
Command:	Main	Freeze	Unfreeze	Toggle	

Note On the Open Log screen and the [Error Log screen](#) (on page 44), filenames up to 32 characters long and client names up to 12 characters long can be displayed without loss of information. If necessary, use the DotsBias option, described in [Common Server-Specific Configuration Options](#) (on page 86), to control which part of longer filenames is lost. To navigate to the Error Log screen from this location, press the Esc key (to go back to the previous screen), followed by the letter **E**.

The command line provides three commands: **Freeze**, **Unfreeze**, and **Toggle**. To choose a command, use the arrow keys or press the first letter of the desired command.

- The **Freeze** command temporarily suspends the updating of the Open Log screen for that particular Server Display application. However, it does not affect the logging of the new opens into the data structures by the server.
- The **Unfreeze** command causes the Server Display program to update the Open Log screen with the information from the server data structures.
- The **Toggle** command causes the information on the Open Log screen to be displayed in a different form, illustrated in [Figure 9](#), which is useful for Micro Focus Customer Care.

Figure 9: Open Log Screen (Toggled)

RM/InfoExpress Version nn.nn		3:25 pm	Tuesday, September 25, 2nnn	
Open Log				
Client/User	File name	Error	Flags	Org Time
scoware	d:\rminfox\PINXFL		00,C9,28 INX	15:15:51
porting				
WCUBED	c:\rminfox\seqfl		80,59,0C SEQ	15:15:15
michael				
WCUBED	c:\rminfox\seqfl		80,49,08 SEQ	15:15:15
michael				
WCUBED	c:\rminfox\seqfl		80,60,09 SEQ	15:15:15
michael				
WCUBED	c:\rminfox\seqfl	35,01	80,61,09 SEQ	15:15:15
michael				
HEADY	d:\rminfox\inxfl	35,01	80,E1,09 INX	15:12:33
rs6000				
support	c:\rminfox\relfl		80,FD,0C REL	15:10:19
rs6000				
support	c:\rminfox\relfl		80,C9,08 REL	15:10:16
PgDn (Ctrl-F) for more				
Command:	Main	Freeze	Unfreeze	Toggle

Error Log Information

The Error Log screen, illustrated in [Figure 10](#), is displayed when you choose the **Log** command from the RM/InfoExpress Server Display main screen, and then choose the **Error Log** command or press the letter **E**. The Error Log screen displays a maximum of 24 errors, beginning with the most recent error. It also lists the name of the client for which the error was issued, the error code detected by the server, the time the error occurred, the location within the RM/InfoExpress server code at which the error occurred, and an explanation (or status) of the error.

Figure 10: Error Log Screen

RM/InfoExpress Version nn.nn		3:28 pm	Tuesday, September 25, 2nnn	
Error Log				
Client/User	Error	Time	Loc	Command/Filename
scoware	10	15:26:34	17	Read Next Record
porting				d:\rminfox\PINXFL
vogon	10	15:26:13	17	Read Next Record
qa				c:\rminfox\rmqa\INXFA
WCUBED	35,01	15:15:15	17	Open Output, File must exist
michael				c:\rminfox\seqfl
HEADY	35,01	15:12:33	17	Open Output, File must exist
				d:\rminfox\inxfl
rs6000	35,01	15:10:16	17	Open Output, File must exist
support				c:\rminfox\relfl
rs6000	30,12,3	15:09:45	17	Open Output, File may/may not exist
support				C:\Program Fil...s\cdrvie\relfl
rs6000	35,01	15:09:45	17	Open Output, File must exist
support				C:\Program Fil...s\cdrvie\relfl
PgDn (Ctrl-F) for more				
Command:	Main	Freeze	Unfreeze	Toggle

Note On the Error Log screen and the [Open Log screen](#) (on page 43), filenames up to 32 characters long and client names up to 12 characters long can be displayed without loss of information. If necessary, use the DotsBias option, described in [Common Server-Specific Configuration Options](#) (on page 86), to control which part of longer filenames is lost. To navigate to the Open Log screen from this location, press the Esc key (to go back to the previous screen), followed by the letter **O**.

The command line provides three commands: **Freeze**, **Unfreeze**, and **Toggle**. To choose a command, use the arrow keys or press the first letter of the desired command.

- The **Freeze** command temporarily suspends the updating of the Error Log screen for that particular Server Display application. However, it does not affect the logging of the new errors into the data structures by the server.
- The **Unfreeze** command causes the Server Display program to update the Error Log screen with the information from the server data structures.
- The **Toggle** command causes the information on the Error Log screen to be displayed in a different form, illustrated in [Figure 11](#), which is useful for Micro Focus Customer Care.

Figure 11: Error Log Screen (Toggled)

RM/InfoExpress Version nn.nn		3:28 pm		Tuesday, September 25, 2nnn	
Error Log					
Client/User	Error	Time	Loc	FAP	Message
scoaware	10	15:26:34	17	01 FF 12 00 00	01 0A 03 01 06 19 01 82 1E
porting				01 19 05 04 BC	0F 6B 00 07 10 53 68 61 72
vogon	10	15:26:13	17	01 FF 12 00 00	01 0A 03 01 06 19 01 82 1E
qa				01 28 05 04 CC	0F 6B 00 0F 6B 00 24 06 00
WCUBED	35,01	15:15:15	17	01 FF 24 00 00	01 01 03 01 02 0A 01 1E 0D
Michael				01 08 0E 01 08	16 04 80 61 09 00 06 0D 5C
HEADY	35,01	15:12:33	17	01 FF 34 00 00	01 01 03 01 06 0A 01 1E 0D
rs6000				01 08 0E 01 08	12 08 03 00 00 00 03 00 09
support	35,01	15:10:16	17	01 FF 24 00 00	01 01 03 01 04 0A 01 1E 0D
rs6000				01 08 0E 01 08	16 04 80 E1 09 00 06 0D 2F
support	30,12,3	15:09:45	17	01 FF 24 00 00	01 01 03 01 04 16 04 80 E0
rs6000				09 00 0A 01 1E	0D 01 08 0E 01 08 06 0D 2F
support	35,01	15:90:45	17	01 FF 24 00 00	01 01 03 01 04 0A 01 1E 0D
rs6000				01 08 0E 01 08	16 04 80 E1 09 00 06 0D 2F

PgDn (Ctrl-F) for more

Command:	Main	Freeze	Unfreeze	Toggle
----------	------	--------	----------	--------

Termination of Communication Activity

The **Terminate** command provides access to a variety of termination nodes.

When you select the **Terminate** command from anywhere within the RM/InfoExpress server program, the Terminate command line is displayed, as illustrated in [Figure 12](#).

Figure 12: Terminate Command Line

Terminate:	Display	Client	Server
------------	---------	--------	--------

The **Terminate** commands are described in the next sections.

Note To avoid terminating the RM/InfoExpress server program accidentally, the default behavior of the RM/InfoExpress Server Display program has changed. When you start the screen display program, you can terminate only the screen display program itself, not the server program or communication to a particular client. The Terminate command line on the Server Display main screen will show only the Display command. However, if the **-t** option is specified on the command line for the Server Display program, then you may also terminate the server or communication to a particular client. The illustration in [Figure 12](#) and the following discussion assume that the **-t** option is specified for the screen display program. For more information, see [UNIX Server Display Command Line Option](#) (on page 25) and [Windows Server Display Command Line Option](#) (on page 28).

Termination of Server Display

It is possible to temporarily terminate the screen interface (Server Display program) in order to increase the processing power of the server. Press the letter **D** to choose the **Display** command from the Terminate command line. The Server Display program will be terminated without affecting the server or any clients.

Termination of Client Communications

Termination of communications between the client and server should be requested only if the particular client is interfering with other clients on the network (for instance, a runaway program has left a record locked). Keep in mind that any access to open files will result in I/O errors on shared files on the terminated client. This action does not remove the client program.

Press the letter **C** to choose the **Client** command from the Terminate command line. The Client Information screen (see [Figure 4](#) on page 40) is displayed with the following prompt at the command line:

```
Select Client to terminate (using PgUp, PgDn or Arrow Keys)
```

Use Page Up, Page Down, or the arrow keys to select a client and press Enter. The Client Files screen is displayed (see [Figure 5](#) on page 41) with the following prompt at the command line:

```
Terminate selected Client? No Yes
```

Press the letter **Y** to terminate communication. Press Enter or Escape or the letter **N** to cancel the command.

Note The use of the Server Display (screen handler) program is for administrative purposes only. When invoked multiple times, only one administrator should perform operations such as terminating clients.

Termination of the Server

To terminate the server, press the letter **S** from the Terminate command line. The following command line is displayed, as illustrated in [Figure 13](#).

Figure 13: Quit Command Line



```
Quit:  When Idle  In a while  Now
```

The **Quit** commands are described in the following sections.

Quit When Idle

Press the letter **W** to choose the **When Idle** command. The following prompt is displayed:

```
Quit when idle?
```

Press the letter **N** or press **Escape** to cancel the command. Otherwise, when all clients are idle, the following prompt is displayed:


```
Terminate Server Now? No Yes
```

Press the letter **Y** to terminate the server immediately. Press the letter **N**, **Escape**, or **Home** to cancel the command.

Quit in a While

Press the letter **I** to choose the **In A While** command. The following command line is displayed, as illustrated in [Figure 14](#).

Figure 14: Quit in a While Command Line



```
Quit in: 3 minutes 5 minutes 10 minutes 20 minutes
```

When you choose one of the time options, the number of minutes will decrement as the specified time elapses. You can cancel the termination at any time by pressing the letter **N** or **Escape**. Otherwise, when all clients are idle, the following prompt is displayed:

```
Terminate Server Now? No Yes
```

Press the letter **Y** to terminate the server immediately. Press the letter **N**, **Escape**, or **Home** to cancel the command.

Quit Now

Press the letter **N** to choose the **Now** command. The following prompt is displayed:

```
Terminate Server Now? No Yes
```

Press the letter **Y** to terminate the server immediately. Press the letter **N**, **Escape**, or **Home** to cancel the command.

The recommended way to terminate the server is by using the command sequence (Terminate, Server, Now, Yes) of the screen display (screen handler) program when no active client is connected.

WARNING Never attempt to terminate one or more RM/InfoExpress UNIX server processes using the **kill** command. This may cause the server to terminate without cleaning up resources and closing open files. For example, using the **kill** command causes the server to exit without removing the IPC (Inter Process Communications) objects, such as shared memory segments and semaphores. As a result, when the server is started next time, it fails with server error code 1 (RMIX_API_ERR_SERVER_ALREADY_EXISTS). For more information, see [Removing IPC Objects After Server Failure](#) (on page 78) in Appendix C: *Troubleshooting*.

Chapter 6: File Security on the RM/InfoExpress UNIX Server

An important consideration in RM/InfoExpress is protecting the system and its data from unauthorized access. This chapter describes the implementation of file security on the RM/InfoExpress UNIX server and the authentication procedures performed by the server on various clients to grant access to the files on the server.

UNIX System Security

The basic security features of UNIX operating systems allow a user of a UNIX server to belong to one of three categories of file access: Owner, Group, and Others. Each category of users can have different access permissions to files. The possible file access permissions are read, write, and execute. For example, if only the Owner of the file has write permission, the UNIX operating system will prevent any other user from writing to the file.

On a standalone UNIX server, the operating system validates the authenticity of the user at login time using information stored in the system password file and other security files. In a networked, client/server environment, however, users may log in to the UNIX server from remote, non-UNIX clients. To validate users on these clients, UNIX uses other security database files such as `.rhosts` or `hosts.equiv`. For more information, see [rhosts File Entry](#) (on page 52).

Note The RM/InfoExpress UNIX server software does not look at `hosts.equiv`, nor does it use the `ruserok` function.

When a user on a remote client logs in to the UNIX server, the networking software on the client passes information to the server about that user, including the server user name, password, and client machine name. After the user has been authenticated, the user on the remote client is allowed to access the files on the server as one of the local users of that server. For more information on file security provided by the UNIX operating system, refer to your UNIX system documentation.

RM/InfoExpress File Security

The implementation of file security in RM/InfoExpress uses the UNIX system security philosophy to protect the files on the RM/InfoExpress UNIX server from unauthorized access

by users on client machines. To be able to use the file security features of RM/InfoExpress, a security parameter file, **ixpwwfile**, must be created on each client machine and each UNIX server using the utility program, **ixsecure.cob**. For more information on this utility, see [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 93).

On a client machine, **ixpwwfile** contains information needed to connect the RM/InfoExpress client to different RM/InfoExpress UNIX servers. Similarly, on the server, **ixpwwfile** is created by the server administrator and contains information that permits different clients to be connected to this server. Only the server administrator should have read and write permissions to the server security parameter file.

The client passes information obtained from **ixpwwfile** to the server when a session is established. The server validates this information against the server's version of **ixpwwfile**.

RM/InfoExpress UNIX Server Security Levels

The RM/InfoExpress UNIX server can be invoked at one of six security levels using the configuration option, `ServerSecurityLevel=number`, where *number* has a value in the range of 0 through 5. These six security levels are described in [Table 1](#). Refer also to [Appendix D: Configuring RM/InfoExpress](#) (on page 79), for more information about server configuration.

If the `ServerSecurityLevel` option is absent in the configuration file, the server runs in “compatibility mode”; that is, the server behaves like a version 2.0 RM/InfoExpress UNIX server. See [Server Compatibility with Older and Newer Clients](#) (on page 53).

Note Older RM/InfoExpress clients can only connect to RM/InfoExpress servers running at security levels “compatible”, 0, or 1.

At other security levels, the server performs various tests on the client to validate its authenticity to access files on the server. These tests become more stringent as the security levels increase, which means that starting the server at level 5 provides the highest level of security to files on the server.

When the RM/InfoExpress UNIX server is run with security enabled, the server-user-name passed from the client is used, if possible, as the User ID while accessing files. If the server-user-name is not present (as is the case for older versions of the RM/InfoExpress client) or invalid, the server will either run the process with the default server user or disallow the client connection to the server. Only servers running at security level 0 or 1 will use the default server user. A server running at security level 0 or 1 will terminate with an error if the default server user is invalid. Servers running at security level 2 or higher will disallow the client connection unless the server-user-name is present and valid. See [Setting Up the Network to Run RM/InfoExpress with Security Enabled](#) (on page 54) for more information.

The RM/InfoExpress UNIX server security levels are summarized in [Table 1](#). Terminology used in the table is defined following the table.

Table 1: RM/InfoExpress UNIX Server Security Levels

RM/InfoExpress UNIX Server Security Levels		
Server Security Level	Requires	To
0	A valid server-user-name.	Verify that server-user-name is valid. If validation fails, server runs the process as the default server user.

RM/InfoExpress UNIX Server Security Levels		
Server Security Level	Requires	To
1	A valid server-user-name. An appropriate entry in the .rhosts file	Verify that server-user-name and .rhosts entry are valid. If validation fails, server runs the process as the default server user.
2	A valid server-user-name. An appropriate entry in the .rhosts file.	Verify that server-user-name and .rhosts entry are valid. If validation fails, client connection is disallowed.
3	A valid server-user-name. An appropriate entry in the ixpwwfile file. The correct user password. The password is normally obtained from ixpwwfile on the client.	Verify that server-user-name and password are valid. If validation fails, client connection is disallowed.
4	A valid server-user-name. An appropriate entry in the .rhosts file. An appropriate entry in the ixpwwfile file. The correct user password. The password is normally obtained from ixpwwfile on the client.	Verify that server-user-name, .rhosts entry, ixpwwfile entry, and password are valid. If validation fails, client connection is disallowed.
5	A valid server-user-name. An appropriate entry in the .rhosts file. An appropriate entry in the ixpwwfile file. The correct user password. The user must enter the password on the client.	Verifies that server-user-name, .rhosts entry, ixpwwfile entry, and password entered by the user are valid. If validation fails, client connection is disallowed.

Server-User-Name

In [Table 1](#), a “valid server-user-name” means that the **ixpwwfile** file on the client contains an entry specifying the name of the server machine, the name of the client machine, and a valid user-name to be used on the server. For more information, see [ixpwwfile File Entry](#) (on page 52).

Default Server User

At security level 0 or 1, the server allows the client to run as a default user on the server when the client fails to meet the security requirements of the server. Normally, the default server user will be allowed to access files that do not require high levels of security. The

default server user, which must be a valid user on the server, is specified using the configuration parameter, `DefaultServerUser`. For more information about this parameter, refer to [UNIX Server-Specific Configuration Options](#) (on page 89). See also the discussion of compatibility of older clients with the new server in [Server Compatibility with Older and Newer Clients](#) (on page 53).

.rhosts File Entry

The **.rhosts** file, present in each user's home directory on the server, is used by the UNIX operating system to validate the permissions of clients who try to access the files on the server owned by the local user. This ASCII file contains information about the client machine and one of its users. The following is a template for an entry line in the **.rhosts** file:

```
machine-name      [user-name]
```

where *machine-name* is the node name of a client machine, and *user-name* is the name of the user on that machine who, when connected to the server, will obtain the owner's permissions on files owned by the local user. If *user-name* is not found on the entry, all the users on the client machine have permission to access files.

Note *user-name* refers to the name used on the client machine, not on the server machine. The *user-name* may match the name used on the server machine, or it may be different.

An "appropriate entry in the **.rhosts** file" in [Table 1](#) (on page 50) means that the **.rhosts** file exists in server-user-name's home directory, the **.rhosts** file owner is server-user-name, only the owner has write permissions (that is, the file permissions must be "rw-r--r--"), and a line exists in the **.rhosts** file specifying client machine-name and, optionally, the client user-name.

ixpwwfile File Entry

To successfully establish a session with the server running at one of the six security levels, clients must pass certain information to the server at the time the session is established. This information is created and stored in an **ixpwwfile** security parameter file for each client and each server system.

Each record in the **ixpwwfile** security parameter file consists of four fields:

```
{server-machine-name, client-machine-name, server-user-name, password}
```

where *server-machine-name* is the name of the machine running the RM/InfoExpress UNIX server with which the client (*client-machine-name*) will establish the session. *server-user-name* is the name of the user on the server by which the client is known. *password* is the password string of the user (*server-user-name*) on the server.

For information about how to run the utility program to create and update **ixpwwfile**, refer to [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 93).

An "appropriate entry in the **ixpwwfile** file" in [Table 1](#) (on page 50) means that the **ixpwwfile** file on the server (pointed to in the **rmixsrvr.ini** configuration file) contains an entry specifying the *server-machine-name*, *client-machine-name*, and *server-user-name*. Note that the *password* should not be present in the entry on the RM/InfoExpress server. The *password* is ignored.

User Password

In [Table 1](#), “correct user password” means that the password sent by the client matches the UNIX system password for *server-user-name* on the server.

Additional Parameters Needed for Non-UNIX Clients

Every UNIX and Windows machine on the network is recognized by its node name. There is, however, no concept of a node name on a machine running the Windows 3.1 operating system. For proper recognition, workstations running Windows 3.1 must define the *client-machine-name* using the ClientName configuration parameter.

Note This discussion of the ClientName configuration parameter is for backward-compatibility issues only as this option was provided for 16-bit Windows clients. RM/InfoExpress no longer supports this option.

Client Validation by the Server at Different Security Levels

At the time the connection between the client and the server is established, each client passes information obtained from the **ixpfile** security parameter file and the configuration file to the RM/InfoExpress UNIX server. The server then validates this information using the UNIX security database files such as **etc/passwd**, **\$HOME/.rhosts**, and so forth, and the **ixpfile** security parameter file on the server.

Server Compatibility with Older and Newer Clients

The following server and client compatibility issues are discussed below.

Older Clients with the New Server

Earlier versions of RM/InfoExpress clients can communicate with the new server running in “compatibility mode” (that is, no security level specified or at security levels 0 or 1). These clients run as the default server user. When the server security level is 2 or greater, however, the server rejects the client connections. One of the following error messages is displayed:

```
RMIX_ERR_SERVER_USERNAME_PARAM_NOT_FOUND
```

- or -

```
RMIX_ERR_USER_PASSWORD_NOT_FOUND
```

New Clients with an Older Server

New versions of RM/InfoExpress clients can communicate with older (pre-2.1) versions of the RM/InfoExpress UNIX server without any problem. At the time the session is established, the information passed by the new client will be ignored by the older server.

Setting Up the Network to Run RM/InfoExpress with Security Enabled

The following sections provide instructions for setting up each of the six levels of file security on the RM/InfoExpress UNIX server. (The setup differences between server security levels are summarized in [Table 2](#) on page 60.) In these procedures, two UNIX machines are connected to a network and are known on that network as *serverU* and *clientU*. A third machine running Windows, known on the network as *clientW*, is also connected on the same network.

A UNIX user running RM/COBOL with the RM/InfoExpress client on machine *clientU* wants to access data files on the RM/InfoExpress server running on machine *serverU*. On the client machine, the user logs in as *clientUser1*, but on the server machine, the user logs in as *serverUser1* with password *pass1*. (Note that *serverUser1* may be the same as or different from *clientUser1*.)

Similarly, a Windows user running RM/COBOL with the RM/InfoExpress client on machine *clientW* wants to access data files on the RM/InfoExpress server running on machine *serverU*. On the client machine, the user is known as *clientUser2*, but on the server machine the user is known as *serverUser2* with password *pass2*. (Note that *serverUser2* may be the same as or different from *clientUser2*.)

It is assumed that the following software is installed and available:

- RM/COBOL with the RM/InfoExpress client on the UNIX client machine (in directory **/usr/rmcobol**) and on the Windows client machine (in directory **c:\rmcobol**)
- RM/COBOL on the UNIX server machine (in directory **/usr/rmcobol**)
- RM/InfoExpress server on the UNIX server machine (in directory **/usr/rminfo**)

The following notes apply to the procedures for setting up RM/InfoExpress to run at each of the six security levels:

Note 1 “create an **ixpwwfile**” means to run **runcobol ixsecure.cob** with your current directory set to where you want the **ixpwwfile** security parameter file to reside or with the IXPWFILE environment variable pointing to the path.

Normally, **ixpwwfile** on the UNIX server is maintained by the RM/InfoExpress server administrator, and only such file is present on the UNIX server machine, generally in the **/usr/rminfo** directory. The **ixpwwfile** file on a Windows client machine is normally maintained by the owner of the Windows machine and resides in the RM/COBOL install directory, **c:\rmcobol**. On a UNIX client machine, each RM/InfoExpress client has his own copy of **ixpwwfile**. The client or server configuration file (either **rmixclnt.ini** or **rmixsrvr.ini**) can be used to configure other locations for **ixpwwfile**. The environment variable IXCONFIG may be used to specify the location and name of the configuration (*.ini) file.

RM/COBOL with the RM/InfoExpress client will look for **ixpwwfile** in the location specified by the IxPwFile option in the Security section of the client configuration file. If the IxPwFile option is not present in the configuration file, then RM/COBOL with the RM/InfoExpress client will attempt to open file **ixpwwfile** in the current working directory.

If the server security level is 3 or 4, passwords may be stored in the client **ixpwwfile**; therefore, it should reside in a secure place (with appropriate owner and restrictive permissions on UNIX).

Note 2 “create a *filename.ini* file” means to use a text editor of your choice to create the appropriate configuration file. Template files are provided as part of the installation:

- **/usr/rminfo/rmixsrvr.ini** for a UNIX server.

- **%ALLUSERSPROFILE%\Micro Focus\RM\RMInfoExpressv12[-64]\rmixsrvr.ini** for a Windows server.
- **/usr/rmcobol/rmixclnt.ini** for a UNIX client, if only a single client configuration file is to be used when no user passwords are required in the security parameter file. If multiple configuration files are required so that each UNIX user can be responsible for the UNIX system password stored in a tradition **ixpwfile** file, then the configuration file should be placed in the current working directory or located using the IXCONFIG environment variable.
- **%ALLUSERSPROFILE%\Micro Focus\RM\RMInfoExpressv12[-64]\rmixclnt.ini** for a Windows client.

Note 3 “create a **.rhosts** file” means to use a text editor of your choice to create a file named **.rhosts** in the home directory of *serverUser*. The owner of the file must be *serverUser* and only the owner can have write permission. The **.rhosts** file entry is the following:

```
clientU clientUser
```

clientUser is optional; if not present, any client user-name on machine *clientU* is allowed. *clientUser* is a client user-name, not a server-user-name such as *serverUser*. Although *clientUser* and *serverUser* are often the same user-name, this is not required.

Note 4 Notation of the form:

```
serverU/clientU/serverUser1/pass1
```

will be used to indicate an **ixpwfile** entry with *serverU* as the server-machine-name, *clientU* as the client-machine-name, *serverUser1* as the server-user-name, and *pass1* as the UNIX system password for the UNIX user ID *serverUser1*. The password will only be present for security levels 3 and 4.

Setup for Running RM/InfoExpress at Server Security Level 0

1. Create an **ixpwfile** file (see [Appendix E](#) on page 93) on each of the two client machines, *clientU* and *clientW*.

- a. On machine *clientU*, create an **ixpwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwfile** file and enter:

```
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 79) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]
ServerSecurityLevel=0
DefaultServerUser=<server-user-name>
```

3. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23).
4. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 1

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 93) on each of the two client machines, *clientU* and *clientW*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 79) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]
ServerSecurityLevel=1
DefaultServerUser=<server-user-name>
```

3. Create two [.rhosts files](#) (see page 52) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```


4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23).
5. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 2

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 93) on each of the two client machines, *clientU* and *clientW*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 79) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ServerSecurityLevel=2
```

3. Create two [.rhosts files](#) (see page 52) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23).

5. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 3

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 93) on each of three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1 / pass1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2 / pass2
```

- c. On machine *serverU*, create an **ixpwwfile** and enter:

```
serverU / clientU / serverUser1  
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 79) on each of the three machines, *clientU*, *clientW* and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]  
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]  
ixpwwfile=<path>  
ServerSecurityLevel=3
```

3. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23).

4. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 4

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 93) on each of three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1 / pass1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2 / pass2
```

- c. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1  
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 79) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]
ixpwwfile=<path>
ServerSecurityLevel=4
```

3. Create two [.rhosts files](#) (see page 52) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23).

5. Run the application on machines *clientU* and *clientW*.

Setup for Running RM/InfoExpress at Server Security Level 5

1. Create an **ixpwwfile** file (see [Appendix E](#) on page 93) on each of three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
```

- b. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientW / serverUser2
```

- c. On machine *clientW*, create an **ixpwwfile** file and enter:

```
serverU / clientU / serverUser1
serverU / clientW / serverUser2
```

2. Create a configuration (.INI) file (see [Appendix D](#) on page 79) on each of the three machines, *clientU*, *clientW*, and *serverU*.

- a. On machine *clientU*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- b. On machine *clientW*, create **rmixclnt.ini** and enter:

```
[Security]
ixpwwfile=<path>
```

- c. On machine *serverU*, create **rmixsrvr.ini** and enter:

```
[Security]
ixpwwfile=<path>
ServerSecurityLevel=5
```

3. Create two [.rhosts files](#) (see page 52) on machine *serverU*.

- a. Log in as *serverUser1*, create **\$HOME/.rhosts** and enter:

```
clientU clientUser1
```

- b. Log in as *serverUser2*, create **\$HOME/.rhosts** and enter:

```
clientW clientUser2
```

4. Start the RM/InfoExpress server on machine *serverU*, as described in [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23).

5. Run the application on machines *clientU* and *clientW*. The appropriate password entry dialog box is displayed.

Setup Differences Between Server Security Levels

[Table 2](#) summarizes the differences between the setup procedures for each server security level and the setup for the next higher level.

Note The entry in `ServerSecurityLevel=number` in step 2c of each setup procedure is incremented by one, beginning with level 1.

Table 2: Summary of Setup Differences Between Server Security Levels

Summary of Setup Differences Between Server Security Levels	
Server Security Levels	Setup Differences
0 and 1	Setup for level 1 adds step 3, which is the requirement for .rhosts files on the server machine.
1 and 2	Setup for level 2 does not support older clients (such as 16-bit Windows clients). The <code>DefaultServerUser=<server-user-name></code> entry in level 1 step 2c is not needed because the server at level 2 refuses the connection rather than running as <code><server-user-name></code> .

Summary of Setup Differences Between Server Security Levels	
Server Security Levels	Setup Differences
2 and 3	Setup for level 3 uses passwords rather than .rhosts files. Steps 1a and 1b requires the entry of passwords in the client ixpwwfile entries, and level 3 step 1c is added because the server requires ixpwwfile entries (passwords are not needed here) for the clients that will connect to it. Level 3 step 2c adds the ixpwwfile=<path> entry so that the server can access the ixpwwfile file created by level 3 step 1c. Level 2 step 3, which is the .rhosts file requirement, is not needed at level 3.
3 and 4	Setup for level 4 adds step 3, which is the requirement for .rhosts files on the server machine.
4 and 5	Setup for level 5 does not require passwords in steps 1a and 1b for the client ixpwwfile entries because the server forces clients to make the user enter the password via a dialog box on the client machine.

Appendix A: Messages

This appendix lists the error messages that can occur while RM/InfoExpress is being used.

Error Message Types

Errors that can occur when using RM/InfoExpress fall into two categories:

- **COBOL errors**, which do not start with the value 30. These errors are described in the appropriate RM/COBOL user's guide.
- **Non-COBOL permanent errors**, which have the following format:

30, error type, error code

where,

error type is used to identify the software that generates the error.

error code is the number returned by that software.

[Table 3](#) lists each error type, the error codes that can occur with each type, and the possible source of the error code for errors generated by RM/InfoExpress. Other error codes associated with error types such as UNIX and Windows can be found in the appropriate vendor documentation.

A complete description of each error type can be found in [Permanent Error Types](#) (on page 64). A complete [description of possible error codes](#) begins on page 65.

Notes

- For more information on error messages, refer to “Error Message Types” and “Error Message Formats” in Appendix A: *Runtime Messages*, in the *RM/COBOL User's Guide*.
- Earlier versions of RM/InfoExpress usually returned two errors: 255 for network-specific errors and 254 for errors detected by RM/InfoExpress. In this version of RM/InfoExpress, errors are returned as they occur, along with the appropriate error code.

Table 3: Error Types and Associated Error Codes

Error Types and Associated Error Codes		
Permanent Error Type (Number and Description)	Possible Error Code (Number/Description)	Possible Error Code (Source)
15 - RM/InfoExpress Server Error	1 - 13	RM/InfoExpress API
	21 - 59	RM/InfoExpress
	12xxx	RM/InfoExpress Windows Sockets Interface
	4xx - 5xx	RM/InfoExpress BSD Sockets Interface
16 - RM/InfoExpress Client Error	21 - 59	RM/InfoExpress
	12xxx	RM/InfoExpress Windows Sockets Interface
	4xx - 5xx	RM/InfoExpress BSD Sockets Interface
21 - RM/InfoExpress WinSock Error	10xxx - 11xxx	Windows Sockets

Permanent Error Types

Error type 15: RM/InfoExpress Server Error

The RM/InfoExpress server generates this type of error when it encounters an error within its code. Errors such as incorrect File Access Protocol (FAP) message received from the client, out-of-memory, and so forth, fall into this category.

Possible error codes for error type 15 are described in the following topics:

- [RM/InfoExpress API-Generated Error Codes](#) (on page 65)
- [RM/InfoExpress-Generated Error Codes](#) (on page 67)
- [RM/InfoExpress Windows Sockets Interface Error Codes](#) (on page 73)
- [RM/InfoExpress BSD Sockets Interface Error Codes](#) (on page 74)

Error type 16: RM/InfoExpress Client Error

The RM/InfoExpress client generates this type of error when it encounters an error within its code. Errors such as incorrect File Access Protocol (FAP) message received from the RM/COBOL program (**runcobol**), incorrect FAP response from the server, out-of-memory, and so forth, fall into this category.

Possible error codes for error type 16 are described in the following topics:

- [RM/InfoExpress-Generated Error Codes](#) (on page 67)
- [RM/InfoExpress Windows Sockets Interface Error Codes](#) (on page 73)

- [RM/InfoExpress BSD Sockets Interface Error Codes](#) (on page 74)

Error type 21: RM/InfoExpress WinSock Error

RM/InfoExpress generates this type of error when either the Windows client program or the Windows server program receives an error from the underlying Windows Sockets software. Possible error codes are described in [RM/InfoExpress WinSock Error Codes](#) (on page 71).

RM/InfoExpress API-Generated Error Codes

Error codes 1 through 13 are common to the server program, the Server Display (screen handler) program, and the API application.

Error code 1: RMIX_API_ERR_SERVER_ALREADY_EXISTS

Failure Definition: Indicates that the server being started encounters a server already running in the system, or at least one of its components is present in the system.

Action: For RM/InfoExpress running on UNIX, this error occurs if the server invoked previously is not terminated, or it is terminated improperly. If the server has been terminated improperly, remove the related IPC (Inter Process Communications) objects (shared memory, key starting with 0x49584D and semaphore, key starting with 0x495853, displayed using the `ipcs` command) using the UNIX command `ipcrm`.

Error code 2: RMIX_API_ERR_OUT_OF_MEMORY

Failure Definition: Indicates that there is not enough memory available in the system for RM/InfoExpress (server or Server Display programs) to continue.

Action: Bring down all the connected clients, bring down the server, and make more memory available before starting the server again.

Error code 3: RMIX_API_ERR_TOO_MANY_USERS

Failure Definition: Indicates that too many Server Display programs are being invoked. The limit is nine for UNIX and Windows.

Action: Close any unnecessary Server Display applications.

Error code 4: RMIX_API_ERR_NOT_AUTHORIZED

Failure Definition: Indicates that the application using the server API attempted either to open the server database with a mode other than `O_RDONLY`, or it used an unauthorized API. This message may also indicate that the Server Display executable is corrupted.

Action: In case of a corrupted Server Display executable, install RM/InfoExpress again.

Error code 5: RMIX_API_ERR_SERVER_NOT_PRESENT

Failure Definition: Indicates that either the application using the server API or the Server Display application is being started without the server having been started.

Action: Start the server and then start the application.

Error code 6: RMIX_API_ERR_CLIENT_ID_NOT_FOUND

Failure Definition: Indicates a malfunction of either the server or the Server Display program.

Action: Bring down all the connected clients, terminate the server, and restart.

Error code 7: RMIX_API_ERR_TOO_MANY_CLIENTS

Failure Definition: Indicates that the server has run out of free slots for remote clients.

Action: Bring down unused client connections to release some slots on the server. Alternatively, you can also perform one of the following:

- Edit the server configuration file, **rmixsrvr.ini**, to include the UseCount option. For more information, see [Common Server-Specific Configuration Options](#) (on page 86).
- Bring down all the connected clients, terminate the server, and restart with the -k command line option. For more information, see [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 23).

Error code 8: RMIX_API_ERR_TOO_MANY_FILES

Failure Definition: Indicates that the server has run out of the free slots for open files.

Action: Close inactive open files from the client applications. Alternatively, edit the server configuration file, **rmixsrvr.ini**, to include the FileCount option. For more information, see [Common Server-Specific Configuration Options](#) (on page 86).

Error code 9: RMIX_API_ERR_CLIENT_NOT_FOUND

Failure Definition: Indicates a server malfunction.

Action: Bring down all the connected clients, terminate the server, and restart.

Error code 11: RMIX_API_ERR_FILE_NOT_FOUND

Failure Definition: Indicates a malfunction of either the server or the Server Display program.

Action: Bring down all the connected clients, terminate the server, and restart.

Error code 12: RMIX_API_ERR_SERVER_APPLICATION_MISMATCH

Failure Definition: Indicates that either the Server Display or the server API application that is being started does not match the server running in the system.

Action: Use a matching Server Display. Also, make sure that the Server Display and the server belong to same release, even though they support the same protocol.

Error code 13: RMX_API_ERR_SERVER_DATABASE_NOT_OPEN

Failure Definition: Indicates a malfunction of either the server or the Server Display program.

Action: Bring down all the connected clients, terminate the server, and restart.

RM/InfoExpress-Generated Error Codes

Error codes 21 through 59 are common to the client, the server, and the Server Display.

Error code 21: RMX_ERR_INVALID_FAP_MESSAGE

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Micro Focus Customer Care for assistance.

Error code 22: RMX_ERR_FILE_HANDLE_NOT_FOUND

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Micro Focus Customer Care for assistance.

Error code 23: RMX_ERR_OUT_OF_MEMORY

Failure Definition: Indicates that there is not enough memory available in the system for RM/InfoExpress (client or server) to continue.

Action: If the associated error type is 15 (RM/InfoExpress Server Error), bring down all the connected clients, bring the server down, and make more memory available before starting the server again. If the associated error type is 16 (RM/InfoExpress Client Error), terminate the client application and restart it after making more memory available on the client system.

Error code 24: RMX_ERR_SESSION_REJECTED

Failure Definition: This error is reported by either the Windows client or the server. When returned by the server, it indicates a problem with the network interface. When returned by the Windows client, it indicates that the RM/COBOL runtime does not match the client.

Action: If returned by the server, contact Micro Focus Customer Care for assistance. If returned by the client, use the version of the runtime that matches the Windows client.

Error code 26: RMX_ERR_SIGNAL_CAUGHT

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Micro Focus Customer Care for assistance.

Error code 27: RMX_ERR_FAP_MANIPULATION

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Micro Focus Customer Care for assistance.

Error code 28 RMIX_ERR_IPC_OBJECTS_REMOVED

Failure Definition: Indicates that the server or the Server Display discovered Inter Process Communications (IPC) objects missing in the system. This error is specific to the server and the Server Display for UNIX.

Action: It may be that the IPC objects have been removed accidentally. Remove the other IPC objects and start the server and/or the Server Display again.

Error code 30 RMIX_ERR_INVALID_COMMAND

Failure Definition: Indicates an RM/InfoExpress system error.

Action: Contact Micro Focus Customer Care for assistance.

Error code 32 RMIX_ERR_TOO_MANY_CLIENTS

Failure Definition: The server reports this error when the number of clients exceeds the value specified on the -k option (or the UseCount configuration file option) or the number of licensed use counts, whichever is less.

Action: Restart the server with a larger value on the UseCount configuration file option, as described in [Common Server-Specific Configuration Options](#) (on page 86), or use a server licensed for more users.

Error code 33 RMIX_ERR_DEF_USER_NAME_NOT_FOUND

Failure Definition: The server, running at a security level of 0 to 2, reports this error when it detects that the name specified on the DefaultServerUser configuration file option or the user name **rmserver** is not a valid user on the server machine. This error may also occur if root is specified as the default user name.

Action: Using system administration tools, add a new user with the name specified. If that user already exists, check the **/etc/passwd** file.

Error code 34 RMIX_ERR_SECURITY_INFO_NOT_FOUND

Failure Definition: The RM/InfoExpress server reports this error when it cannot find a match for the *server-user-name*, *client-machine-name*, and *server-machine-name* triple passed by the client in the server's security parameter file, **ixpwwfile**.

Action: Update **ixpwwfile** by using the utility program **ixsecure.cob** on both the client and the server machines to add an entry for the *client-machine-name* and the *server-user-name* pair. For more information, see [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 49) and [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 93). For a Windows client, the client name is the Windows computer name. For a UNIX client, this is the node name and is given by the **uname** command.

Error code 35 RMIX_ERR_USER_PASSWORD_PARAM_NOT_FOUND

Failure Definition: This error is normally reported by the RM/InfoExpress server running at a security level of 3 or higher.

Action: Contact Micro Focus Customer Care for assistance.

Error code 36 RMIX_ERR_SYSTEM_PASSWORD_MISMATCH

Failure Definition: The server, running at a security level of 3 or higher, reports this error when it detects that the *password* string stored in the **ixpwfile** security parameter file on the client machine and on the server machine, and the password stored in the UNIX system, do not match.

Action: See that the *password* string entered interactively at the client terminal or stored in **ixpwfile** on the client machine matches the *password* string stored in **ixpwfile** on the server machine and the one stored in the UNIX system. To update the password entry in **ixpwfile**, use the utility program **ixsecure.cob**. See [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 93).

Error code 37 RMIX_ERR_SYSTEM_PASSWORD_NOT_FOUND

Failure Definition: The server, running at a security level of 3 or higher, reports this error when it cannot locate the user password in the UNIX system security database.

Action: This error normally occurs on UNIX systems that maintain the security database in a file different from the **/etc/passwd** file. This indicates that one or both of these files have been corrupted. Contact your system administrator.

Error code 38 RMIX_ERR_RHOSTS_FILE_OPEN_ERROR

Failure Definition: The server reports this error when it cannot open the **.rhosts** file in the user's home directory.

Action: Seek your server administrator's help in creating the **.rhosts** file with appropriate entries in the user's home directory on the server machine.

Error code 39 RMIX_ERR_RHOSTS_FILE_PERMISSIONS_INVALID

Failure Definition: The server reports this error when it finds the permissions of the **.rhosts** file in the user's home directory to be invalid.

Action: Set the permissions of the **.rhosts** file in the user's home directory on the server machine to be "**-rw-r--r--**" and make certain that the user is the owner of this file.

Error code 40 RMIX_ERR_ENTRY_NOT_FOUND_IN_RHOSTS_FILE

Failure Definition: The server reports this error when it fails to find a matching client name entry (with the *client-machine-name* parameter passed by the client machine) in the **.rhosts** file on the server machine.

Action: With the help of your server administrator, edit the **.rhosts** file in the user's home directory on the server machine and add a new entry containing the *client-machine-name* and an optional *server-user-name*.

Error code 41 RMIX_ERR_NO_SESSION

Failure Definition: Both the server and the client may report this error. Although not fatal, this error is still considered an RM/InfoExpress system error.

Action: Contact Micro Focus Customer Care for assistance.

Error code 42 RMIX_ERR_SERVER_USER_NAME_PARAM_NOT_FOUND

Failure Definition: The server, running at a security level of 0 to 5, reports this error when it detects that the *server-user-name* parameter is absent in the information passed by the client when connections are established.

Action: This error may occur when an old client tries to establish a connection with the new server running at security level 2 or higher. This error may also occur when the new client cannot provide the required information to the server due to some problem in processing the security parameter file, **ixpwfile** (for example, the file is not present on the client machine). Upgrade to a new version of the RM/InfoExpress client in order to use security features on the server.

Error code 43 RMIX_ERR_CLIENT_MACH_NAME_PARAM_NOT_FOUND

Failure Definition: The server, running at a security level of 0 to 5, reports this error when it detects that the *client-machine-name* parameter is absent in the information passed by the client when connections are established.

Action: This error may occur when an old client tries to establish a connection with the new server running at security level 2 or higher. This error may also occur when the new client cannot provide the required information to the server due to some problem in processing the security parameter file, **ixpwfile** (for example, the file is not present on the client machine). Upgrade to a new version of the RM/InfoExpress client in order to use security features on the server.

Error code 44 RMIX_ERR_SERVER_SECURITY_INFO_FILE_ERROR

Failure Definition: This error occurs when the server fails to open the security parameter file, **ixpwfile**, on the server machine.

Action: Make sure that a valid security parameter file, **ixpwfile**, is present on the server machine. If this file does not exist, create it using the **ixsecure.cob** utility program (see Appendix E).

Error code 45 RMIX_ERR_MALFORMED_MESSAGE

Failure Definition: Indicates an RM/InfoExpress system error. This error occurs when either the client or the server fails to decompress the message received from the session partner.

Action: Contact Micro Focus Customer Care for assistance.

Error code 46 RMIX_ERR_NO_MEMORY_FOR_COMPRESSION

Failure Definition: There was insufficient memory to compress or decompress the data.

Action: Set the IxCompress configuration file option to No to disable message compression, as described in [Common Configuration Options](#) (on page 81). Message compression should not be used for records of more than 64000 bytes.

Error code 47 RMIX_ERR_TOO_MANY_FILES

Failure Definition: The client(s) have exceeded the total number of open files supported by the server.

Action: Increase the value of the FileCount configuration file option and restart the server, as discussed in [Common Server-Specific Configuration Options](#) (on page 86).

Error code 48 RMIX_ERR_SYSTEM_PASSWORD_FILE_OPEN_ERROR

Failure Definition: This error occurs when an invalid `/etc/passwd` file (which may be missing) or the `server-user-name` with which the client is trying to run is not present on the server machine.

Action: Contact your system administrator.

Error code 49 RMIX_ERR_CLIENT_SECURITY_INFO_FILE_ERROR

Failure Definition: This error occurs when the client fails to open the security parameter file, `ixpwwfile`, on the client machine.

Action: Make sure that a valid security parameter file, `ixpwwfile`, is present on the client machine. If this file does not exist, create it using the `ixsecure.cob` utility program. See [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 93).

Error codes 50 — 59

Failure Definition: Error codes 50 through 59 represent internal errors in the RM/InfoExpress server program. Error code 54 may indicate an attempt to use an old client with a new server in a mode other than compatibility mode.

Action: Contact Micro Focus Customer Care for assistance.

RM/InfoExpress WinSock Error Codes

[Table 4](#) lists the possible error codes for permanent error type 21, which is described on page 65. Codes in the 10000 range represent network or system errors. Codes in the 11000 range represent database errors.

Table 4: Error Codes Generated by Windows Sockets

Error Codes Generated by Windows Sockets			
Error Code	Description	Windows Sockets Error Equivalent	UNIX Error Equivalent
10004	Interrupted system call	WSAEINTR	EINTR
10009	Bad file number	WSAEBADF	EBADF
10013	Permission denied	WSAEACCES	EACCES
10014	Bad address	WSAEFAULT	EFAULT
10022	Invalid argument	WSAEINVAL	ENOTSOCK

Error Codes Generated by Windows Sockets			
Error Code	Description	Windows Sockets Error Equivalent	UNIX Error Equivalent
10024	Too many open files	WSAEMFILE	EMFILE
10035	Operation would block	WSAEWOULDBLOCK	EWOLDBLOCK
10036	Blocking operation in progress	WSAEINPROGRESS	EINPROGRESS
10037	Operation already in progress	WSAEALREADY	EALREADY
10038	Operation on non-socket	WSAENOTSOCK	ENOTSOCK
10039	Destination address required	WSAEDESTADDRREQ	EDESTADDRREQ
10040	Message too long	WSAEMSGSIZE	EMSGSIZE
10041	Wrong protocol type	WSAEPROTOTYPE	EPROTOTYPE
10044	Socket type not supported	WSAESOCKTNOSUPPORT	ESOCKTNOSUPPORT
10045	Operation not supported	WSAEOPNOTSUPP	EOPNOTSUPP
10046	Protocol family not supported	WSAEPFNOSUPPORT	EPFNOSUPPORT
10047	Address family not supported	WSAEAFNOSUPPORT	EAFNOSUPPORT
10048	Address already in use	WSAEADDRINUSE	EADDRINUSE
10049	Cannot assign address	WSAEADDRNOTAVAIL	EADDRNOTAVAIL
10050	Network is down	WSAENETDOWN	ENETDOWN
10051	Network is unreachable	WSAENETUNREACH	ENETUNREACH
10052	Network reset connection	WSAENETRESET	ENETRESET
10053	Connection was aborted	WSAECONNABORTED	ECONNABORTED
10054	Peer reset connection	WSAECONNRESET	ECONNRESET
10055	No available buffer space	WSAENOBUFS	ENOBUFS
10056	Socket already connected	WSAEISCONN	EISCONN
10057	Socket not connected	WSAENOTCONN	ENOTCONN
10058	Socket was shut down	WSAESHUTDOWN	ESHUTDOWN
10059	Too many references	WSAETOOMANYREFS	ETOOMANYREFS
10060	Connection timed out	WSAETIMEDOUT	ETIMEDOUT
10061	Connection refused	WSAECONNREFUSED	ECONNREFUSED
10062	Symbolic link loop	WSAELOOP	ELOOP
10063	Pathname too long	WSAENAMETOOLONG	ENAMETOOLONG
10064	Host is down	WSAEHOSTDOWN	EHOSTDOWN
10065	Host is unreachable	WSAEHOSTUNREACH	EHOSTUNREACH
10066	Directory not empty	WSAENOTEMPTY	
10067	Process limit	WSAEPROCLIM	
10091	Network is unusable	WSASYSNOTREADY	
10092	Version not supported	WSAVERNOTSUPPORTED	

Error Codes Generated by Windows Sockets			
Error Code	Description	Windows Sockets Error Equivalent	UNIX Error Equivalent
10093	Startup not done	WSANOTINITIALISED	
11001	Host not found	WSAHOST_NOT_FOUND	HOST_NOT_FOUND
11002	Try again	WSATRY_AGAIN	TRY_AGAIN
11003	No recovery	WSANO_RECOVERY	NO_RECOVERY
11004	No data	WSANO_DATA	NO_DATA

RM/InfoExpress Windows Sockets Interface Error Codes

Codes in the 12000 range, shown in [Table 5](#), are generated by the Windows Sockets interface portion of the RM/InfoExpress Windows client program or the Windows server program and represent memory allocation failures or unexpected conditions.

These errors are considered RM/InfoExpress system errors. When these errors are detected, contact Micro Focus Customer Care for assistance.

Table 5: Error Codes Generated by the RM/InfoExpress Windows Sockets Interface

Error Codes Generated by the RM/InfoExpress Windows Sockets Interface	
Error Code	Description
12001	Insufficient memory for connect.
12002	Internal socket number already in use.
12003	Unexpected event occurred during connect.
12004	Unexpected error condition from connect.
12005	Unexpected event occurred during initial receive.
12006	Received data length error (client/server not synchronized).
12007	Received data length error (client/server not synchronized).
12008	Received data length error (client/server not synchronized).
12009	Received data length inconsistent with FAP message length.
12010	Unexpected event occurred during secondary receive.
12011	Unexpected event occurred during send.
12012	Internal buffer length too small for status.
12013	Insufficient memory for status.
12014	Unknown error during asynchronous wait.
12015	Unknown error during event wait.
12016	Received data length error.
12017	Unknown error during asynchronous-wait.

Error Codes Generated by the RM/InfoExpress Windows Sockets Interface	
Error Code	Description
12018	Unknown error during event wait.
12019	Unknown error during event wait.

Appendix B: Limits and Ranges

This appendix describes RM/InfoExpress limits and ranges.

Limits and Ranges

The following limitations apply to RM/InfoExpress:

1. It is not possible to run more than one RM/InfoExpress server program at a time on a given machine.
2. No more than nine RM/InfoExpress UNIX and Windows Server Display (screen handler) programs may be run at one time on a given machine.

Appendix C: Troubleshooting RM/InfoExpress

This appendix is designed to help if you run into any problems when using RM/InfoExpress. Each section offers steps you can take to solve the problem.

Failure to Locate File or Path

Error messages that occur while accessing the file on the server machine, for example, “File not found” or “Path not found”, generally indicate one of the following conditions:

1. The RM/InfoExpress UNIX server program is not running on a UNIX server machine. In this case, load **rmservtcp**.
2. The complete filename (defined using the synonym or other means) does not correctly point to the location on the server. Check your environment variables and synonyms.
3. In the case of a Windows client, the **rmtcp32** and **winsock** DLLs are not in the execution path.
4. For a Windows client, the **runcobol** configuration file contains an incorrect DLL name or the DLL specified on the NAME option of the EXTERNAL-ACCESS-METHOD record cannot be located.
5. Invoke the RM/InfoExpress server with the **-c I** option so that pathnames from Windows clients will be converted to lowercase by the server.
6. While accessing files from a UNIX client, make certain that the machine name specified in the pathname is the same as the one in the **/etc/hosts** file on the client machine. For example, the machine name “HAL9000” in the pathname defined by **INXFL=//HAL9000/rminfo/inxfl** matches the name “HAL9000” in the **/etc/hosts** file entry 111.22.333.44 hal9000 HAL9000.

RM/InfoExpress Client Entries Not Terminating

Certain situations on some versions of UNIX, when running RM/InfoExpress using the TCP/IP protocol, can cause the server not to notice that a client has been terminated. This occurs only if the client is terminated in a non-standard method, such as turning off the client workstation or experiencing a system failure on the client workstation. In such instances, the

RM/InfoExpress client is unable to inform the server that the client is terminating. Although the operating system eventually notifies the RM/InfoExpress server that the connection has been broken, it could take several hours on some implementations of UNIX before the notification occurs.

One version of UNIX that exhibits this behavior is AIX running on the RS/6000. To reduce the amount of time before the inactivity on a TCP/IP connection is interpreted as a lost connection under AIX, use the following **no** command:

```
no -o tcp_keepidle=200 -o tcp_keepintvl=60
```

where,

-o is a network option.

Note On AIX 5.2, there is a defect that prevents a single **no** command from having two **-o** options. In this case, you must use two **no** commands.

tcp_keepidle determines the number of half-seconds to wait after the last successful I/O operation before attempting to determine whether a connection has been lost.

tcp_keepintvl determines the number of half-seconds to wait between requests for a response from the possibly lost connection.

After ten requests with no response, the operating system reports a lost connection to the server. The settings shown in this example will report a broken connection after 400 seconds (100+30*10).

Note You must run the **no** commands each time the network is started since it does not permanently change the default configuration values.

Removing IPC Objects After Server Failure

The recommended way to terminate the server is by using the command sequence (Terminate, Server, Now, Yes) of the screen display (screen handler) program when no active client is connected.

Using the **kill** command causes the RM/InfoExpress UNIX server to exit without removing the IPC (Inter Process Communications) objects, such as shared memory segments and semaphores. Consequently, when the server is started next time, it fails with server error code 1 (RMIX_API_ERR_SERVER_ALREADY_EXISTS).

In this situation, remove the IPC objects using the following UNIX commands:

```
ipcrm -m <shm_id> -s <sem_id>
```

where the **<shm_id>** and **<sem_id>** objects are obtained by using the UNIX command:

```
ipcs
```

Note that the key values for RM/InfoExpress IPC objects start with the value 0x49584D for shared memory and 0x495853 for semaphores.

Appendix D: Configuring RM/InfoExpress

RM/InfoExpress can be uniformly configured across all implementations of clients and servers. To maintain compatibility with previous versions of RM/InfoExpress, environment variables supported by previous versions can be used to override the settings of the configuration file. On the server, all the command line options can be specified in the configuration file.

This appendix describes the configuration files and their options.

Configuration Files and Options

Even though the names of the configuration files used by different implementations of RM/InfoExpress are different, the format of all these files is identical. The configuration files are as follows:

<u>Use</u>	<u>To set configuration parameters for</u>
rmixclnt.ini	RM/InfoExpress Windows and UNIX client programs.
rmixsrvr.ini	Either the RM/InfoExpress UNIX or the Windows server program.

IXCONFIG – optional environment variable on Windows and UNIX that specifies the path or path and filename of the ini configuration file.

- On Windows: If *just* the path is specified, it must end with a “\” and the appropriate file name will be appended. If the value ends with any other character, the value is assumed to be the path and file name of the configuration file. If the file does not exist, the other default locations are searched for the configuration file.
- On UNIX: The search starts with the current directory. If the expected configuration file is not found, then the IXCONFIG value is checked. If used, it should be set to the full path and file name of the configuration file.

For Windows clients and Windows servers, the configuration file is located with this priority:

1. The value of IXCONFIG environment variable.
2. PROGRAMDATA\Micro Focus\RM\RMInfoExpressv12(-64)
3. The directory where runcobol.exe is located.
4. The directory where rmtcp32.dll is located.

5. The Windows directory (usually C:\WINDOWS).

For UNIX clients and UNIX servers, the configuration file must be present in the current directory or the directory pointed to by the environment variable, IXCONFIG.

In a configuration file, any line beginning with a semi-colon (;) is treated as a comment and is not processed.

The client and server configuration files are divided into sections, each of which consists of a group of related options that you can use to customize your implementation of RM/InfoExpress. Some configuration options are used only by the client, while others are used only by the server. Some options are specific to the type of server. Still others are common to both client and server. All configuration options are shown in the sample configuration file that follows. See the more [detailed descriptions of the configuration options](#) on page 81.

Note Option names are not case-sensitive.

Sample Configuration File

```
[Debug]
;###Common###
InfoxDebug=debug filename

[Options]
;###Common###
IxCompress=Yes|No
ReconnectEnable=Yes|No

;###Client-Specific###
KeepSession=Yes|No
PathPrefixExcluded=list
PathPrefixIncluded=list
ReconnectDelay=number
StartupLogPath=directory-path

;###Server-Specific, All Servers###
DotsBias=number
FileBufferPool=number
FileCount=number
FileProcessCount=number
MinimumBlockSize=number
RoundToNiceBlockSize=Yes|No
UseCount=number
ReconnectTimeout=number
LargeFileLockLimit=number
InxUseLargeLimit=Yes|No
RelUseLargeLimit=Yes|No
SeqUseLargeLimit=Yes|No

;###Server-Specific, UNIX Server Only###
ConvertFileName=NoConvert|UpperCase|LowerCase
```



```
###Server-Specific, Window Server Only###
UseCurrentDirectory=Yes|No
UseSystemShares=Yes|No

[Security]
###Common###
EncodeData=Yes|No
IxFwFile=pathname

###Client-Specific###
AcceptPassword=Yes|No

###Server-Specific, UNIX Server Only###
DefaultServerUser=server-user-name
ServerSecurityLevel=number

[Sharing]
###Server-Specific, Windows Server Only###
share-name=share-path

[Tcp]
###Common###
MaxSendSize=number

[Winsock]
###Common###
IgnoreHangupError=Yes|No (Windows only)

###Client-Specific###
UseBlockingIO=Yes|No
```

Common Configuration Options

The following configuration options, listed alphabetically, are *common* to both the client and server components of RM/InfoExpress:

- **EncodeData.** The EncodeData option in the [Security] section is used to encode messages to provide more security to the data transmitted on the network. EncodeData=No is the default. When the value is set to Yes, the RM/InfoExpress component (either the client or the server) negotiates the encoding algorithm of the messages exchanged with its session counterpart. If both the session partners have the value set to Yes, the messages are encoded before they are sent and decoded immediately after they are received. However, if any of the session partners have the value set to No, the message encoding does not take place. Message encoding will not take place if either of the session partners is using a release of RM/InfoExpress earlier than version 2.1.
- **IgnoreHangupError.** The IgnoreHangupError option in the [Winsock] section is used only by RM/InfoExpress on Windows. If the value is IgnoreHangupError=Yes, any error returned by Windows Sockets functions, called while the Windows client is trying to disconnect the session with the server, are ignored. Do not specify this option unless instructed to do so by Micro Focus Customer Care.

IgnoreHangupError=No is the default value. If the value is set to No, a possibly serious error, should one occur while disconnecting the session with the server, is returned to the Close operation. This is normal behavior for any I/O operation.

- **InfoxDebug.** The InfoxDebug option in the [Debug] section causes the file whose pathname is given by *debug filename* to be created and trace information written into it. After the client RM/COBOL application is terminated, send this file to Micro Focus Customer Care for further investigation. Use this option only when you are investigating a problem with the assistance of Micro Focus Customer Care. Using this option under normal conditions affects client operations negatively.

On the server, the InfoxDebug configuration option is equivalent to the -d command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 25). Note that the command line option overrides the configuration option.

- **IxCompress.** The IxCompress option in the [Options] section is used to compress messages transmitted on the network. Depending on the compressibility of the messages, which may contain COBOL data records, this option may improve the performance on the network. IxCompress=Yes is the default. When the value is set to Yes, the RM/InfoExpress component (either the client or the server) negotiates the compressibility of the messages exchanged with its session counterpart. If both the session partners have the value set to Yes, the messages are compressed before they are sent and decompressed immediately after they are received. However, if any of the session partners have the value set to No, the message compression does not take place. Message compression will not take place if either of the session partners is using a release of RM/InfoExpress earlier than version 2.1.
- **IxPwFile.** The value of *pathname* specified on the IxPwFile option in the [Security] section is used to locate the file containing the security parameters. If this option is absent, RM/InfoExpress looks for the security parameter file, **ixpwfile**, in the current directory. See [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 49).
- **MaxSendSize.** The MaxSendSize option in the [Tcp] section may be specified for those TCP/IP implementations that have a limitation. We recommend that you leave this value unspecified unless you know that the TCP/IP in use has a limitation. Some UNIX systems have a limit of 4096 bytes. Note that this value is *not* the same value as the size of the maximum packet allowed on the network

The value specified by the MaxSendSize option is used to determine whether the RM/InfoExpress client or server code must perform multiple send operations on a given message. The underlying TCP stack implementation determines the maximum allowable value for a single send operation. Multiple send operations may be required for some large messages. The TCP stack will transmit the data in as many network packets as required by the underlying network. Again, for large messages, multiple network packets may be required.

If I/O errors occur on a file with a record size larger than about 4000 bytes while files with smaller record sizes perform normally, try specifying MaxSendSize=4096. The default value is system-dependent, but is currently 4096 or larger. The value cannot be less than 512.

On the server, the MaxSendSize configuration option is equivalent to the -z command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 25). Note that the command line option overrides the configuration option.

- **ReconnectEnable.** The ReconnectEnable option in the [Options] section determines whether reconnection logic in the client or server is enabled or disabled. For the client, the option determines whether the client will attempt to reconnect the session with the server if the connection is broken. For the server, this option determines whether the server will keep the file manager process and the current state of its open files intact waiting for the client to reconnect and continue from where it left off when the connection was broken.

Both the client and server sides of a connection must have reconnection enabled for the attempt to succeed. If the value is set to No for the client and the server, then they both behave identically to previous RM/InfoExpress releases; that is, the client reports an error to the COBOL program and the server closes files and terminates the file manager process running on behalf of the client. The default value is Yes for the client and No for the server. These defaults allow reconnection to any given server to be enabled simply by changing the **rmixsrvr.ini** file for that server and starting the server again.

Beginning with version 8, a limited reconnection capability, which allows a connection that becomes broken to be reconnected automatically, has been added to the RM/InfoExpress client and server logic. The client and server continue normal operation without the client run unit (COBOL program) ever being aware of the disconnection. The server writes a log file, named RMRECONN.LOG, which is created in the directory specified in the environment variable RM_RECONN_LOG_PATH, if defined. If this environment variable is not defined, the log file is created in the TEMP directory on Windows or in the current directory on UNIX. Although it is not recommended, you can disable the log file by setting the RM_RECONN_LOG_PATH environment variable to a non-existent directory name.

TCP/IP provides a capability, known as “keepalive” support, to determine automatically whether an idle connection is still intact. When a connection has been idle for a certain period of time, TCP/IP transmits keepalive packets to see whether they are acknowledged, thus indicating an intact connection. After several retries—with each attempt receiving no acknowledgement—TCP/IP informs RM/InfoExpress that the connection is broken.

Having keepalive support enabled and keepalive packets being sent every short interval helps the reconnection logic work in a reasonable manner. Unfortunately, systems typically have keepalive support disabled or set to occur only after two hours of inactivity. Micro Focus recommends enabling keepalive support, if necessary, and setting the keepalive delay time to a cycle of two minutes or less. Since the method of setting these system TCP/IP variables varies from system to system, consult your system administration documentation. On UNIX, these TCP/IP parameters are normally part of the kernel parameters that UNIX system administrators can set. On all versions of Windows, these TCP/IP parameters are set in the Windows registry under the following key:

```
HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\Tcpip\Parameter
```

In particular, it is the value name KeepAliveTime, the REG_DWORD value that defaults to 7,200,000 milliseconds (two hours), which is the value that Micro Focus recommends changing to 120,000 milliseconds (two minutes) or less. More information is available by searching the Microsoft Support Knowledge Base for “keepalive configuration.” RM/InfoExpress calls the **setsockopt** function to enable the SO_KEEPALIVE socket option.

Client-Specific Configuration Options

The following configuration options, listed alphabetically, are *specific* to RM/InfoExpress clients:

- **AcceptPassword.** The AcceptPassword option in the [Security] section specifies whether the client should always accept passwords interactively. The default value is No. The server requires a password from the client when the server is running at security level 3, 4, or 5. At level 5, the server forces the client to always accept the password interactively, ignoring any password stored in the **ixpwfile** file on the client machine.

When AcceptPassword=No is set and the server is running at level 3 or 4, the client obtains the password from the **ixpwfile** on the client machine and sends it to the server.

When AcceptPassword=Yes is set and the server is running at level 3 or 4, the client accepts the password interactively (as it does for level 5).

The server administrator may wish to set AcceptPassword=Yes on unsecured client machines where it is undesirable to store any passwords (even though they are encoded) in the **ixpwfile** on that client machine.

- **KeepSession.** Located in the [Options] section. KeepSession=Yes is the default. If the value is set to Yes, the client keeps the session with the server until the run unit terminates, even if all files on that server are closed before that time. This option is sometimes necessary when the client application opens and closes files rapidly, causing sessions to be established and released in rapid succession. Some network implementations cannot handle such frequent session creation, which can lead to errors and program hangs. This option may also improve performance slightly by eliminating the overhead of releasing and re-establishing a session between the Close of one remote file and the Open of another remote file on the same server. The drawback of specifying this option is that sessions may be kept with several servers for long periods of time when they will never be used again, thereby consuming network resources. Errors may occur if some network resources are exhausted.

If the value is KeepSession=No, the client releases the session with the server when the last open file is closed. In addition, the UNIX client supports this option as an environment variable (also called KEEPSSESSION), which when set, overrides the current setting.

- **PathPrefixExcluded** and **PathPrefixIncluded.** These two configuration options are both used to allow an RM/InfoExpress client to exclude selected UNC-style pathnames (beginning with \\ or //) from access via RM/InfoExpress. (Prior to version 8, RM/InfoExpress always attempted access to all UNC-style pathnames.) The PathPrefixExcluded option in the [Options] section determines which pathname prefixes are not to be accessed via RM/InfoExpress. The PathPrefixIncluded option in the [Options] section determines which pathname prefixes can be accessed via RM/InfoExpress.

In each option, the *list* is a comma-separated list of pathname prefix strings. Embedded spaces within each string are kept while leading and trailing spaces are ignored. Matching is case-insensitive and slash (/) matches backslash (\). Thus, \\SRV1\TMP is equivalent to //srv1/tmp. Only whole edgenames are matched, where edgename means the text between two slashes or backslashes or end of string. Consequently, //srv matches //srv/tmp/file.ext but does not match //srv1/tmp/file.ext. No wildcard characters are allowed.

Consider the following to determine when and how to use these closely related options:

- If only PathPrefixExcluded is specified, matching pathnames are excluded and all other pathnames are included.
- If only PathPrefixIncluded is specified, matching pathnames are included and all other pathnames are excluded.
- If both PathPrefixExcluded and PathPrefixIncluded are specified, the longest matching prefix string determines exclusion or inclusion, and pathnames matching none of the prefix strings are included by default.
- If neither PathPrefixExcluded nor PathPrefixIncluded is specified, all pathnames are included (which is the same behavior as prior versions of RM/InfoExpress).

Typically, you would specify either PathPrefixExcluded or PathPrefixIncluded based upon which pathname prefix list is the shortest or most well defined to enumerate. However, both options can be specified for more complicated exclusion and inclusion schemes.

For example, specifying:

```
PathPrefixExcluded=//srv1, //srv2
PathPrefixIncluded=//srv2/data, //srv2/tmp
```

means that an RM/InfoExpress client will not attempt to access any files on server **srv1** and will attempt to access only files whose pathnames begin with //srv2/data or //srv2/tmp on server **srv2**. You might want this in a situation in which **srv2** is a Windows server where all RM/InfoExpress data files reside in directories **data** and **tmp**, but there are also Windows printers that you want to access via pathnames //srv2/printer1, //srv2/printer2, and so forth. Note, however, that if printer1 and printer2 are the only two pathnames that you do not want to access via RM/InfoExpress on **srv2**, then specifying only the following would achieve the same result:

```
PathPrefixExcluded=//srv1, //srv2/printer1, //srv2/printer2
```

Any other pathname on **srv2**, such as //srv2/data/file, would be included by default since that pathname does not match any excluded path prefix.

- **ReconnectDelay.** The ReconnectDelay option in the [Options] section determines the number of milliseconds the client will delay before attempting to reconnect to the server after the client becomes aware that the connection has been broken. The default value is 100 (one tenth of a second).
- **StartupLogPath.** The StartupLogPath option in the [Options] section creates a file whose directory and pathname are given by *directory-path*, and writes logging information into the file. This client-side log file can be used to diagnose and troubleshoot problems when initially starting up the connection of the RM/InfoExpress client to the RM/InfoExpress server. This log file indicates errors that are encountered in the pre-connection, connect, and first message sent and received operations during the initial connection to the server. The log file also contains the client-side host name, the client-side IP address (from gethostbyname), the server-side host name, the server side IP address, and the result of the connect request.

To configure the location of this log file, RMCLIENT.LOG, specify the following configuration parameter in the [Options] section of the **rmixclnt.ini** file:

```
StartupLogPath=c:\Micro Focus\Logs
```

Note The environment variable, RM_CLIENT_LOG_PATH, may also be used to configure and specify the location of the RMCLIENT.LOG file. Setting the environment

variable takes precedence over setting the configuration parameter in the **rmixclnt.ini** file (as described above).

- **UseBlockingIO.** The UseBlockingIO option in the [Winsock] section is provided to improve the performance of the RM/InfoExpress Windows client. If the value is UseBlockingIO=Yes, Windows Sockets functions are called in blocking mode; that is, every function call will block until the request is complete. Using this value also ensures that Windows Sockets Asynchronous functions and the **PeekMessage** function are never called. Substantial performance improvements may occur, depending upon the type of Windows Sockets implementation used. However, the operator will not be able to cancel a Read operation waiting on a locked record. We suggest users experiment using their own benchmark programs to determine whether specifying the value Yes results in better performance for the specific TCP/IP implementation in use.

If the value is UseBlockingIO=No (the default value), Windows Sockets Asynchronous functions and the **PeekMessage** function are used; that is, functions are called in non-blocking mode. If any COBOL program using the Windows client executes a Read operation that waits on a locked record and the operator requires the ability to cancel that operation, the UseBlockingIO option must be set to No.

Sample RM/InfoExpress Windows Client Configuration File

The following is a sample Windows client configuration file (**rmixclnt.ini**).

```
[Debug]
;;;InfoxDebug=DBGFILE

[Security]
IxPwFile=d:\tmp\IXPWFIL

[Winsock]
UseBlockingIO=Yes
```

Common Server-Specific Configuration Options

CAUTION It is imperative that on every RM/InfoExpress server and RM/COBOL runtime system accessing any particular file from any machine, the values specified for the FileProcessCount, LargeFileLockLimit, RelUseLargeLimit, and SeqUseLargeLimit keywords in the RM/InfoExpress server configuration file must match the values specified in the corresponding configuration option in the RM/COBOL runtime system.

The following configuration options, listed alphabetically, are *common* to both the RM/InfoExpress UNIX server and the Windows server programs:

- **DotsBias.** The DotsBias option in the [Options] section is used to specify where an ellipsis (...) appears in filenames that are too long to fit in the display field of the Server Display program. The leftmost part of the filename appears to the left of the dots and the rightmost part of the filename appears to the right of the dots (the middle of the filename is replaced by the ellipsis.) The default value is zero, which causes the ellipsis to appear in the middle of the field. Negative values move the ellipsis to the left and positive values move the ellipsis to the right. Special value +9999 moves the ellipsis completely

out of the right side of the field, thus displaying the leftmost part of the filename (truncated). This is equivalent to RM/InfoExpress version 2.0 behavior. Special value -9999 moves the ellipsis completely out of the left side so that the rightmost part of the filename is displayed (with no ellipsis). This option is cosmetic and has no effect on server operation other than the display.

- **FileBufferPool.** The FileBufferPool option in the [Options] section is used to specify the common buffer pool size on the server machine. The default value is zero, which causes the default size for the common buffer pool. Normally, you should not need to specify a value. This option corresponds to the BUFFER-POOL-SIZE keyword in the RUN-FILES-ATTR configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.

The FileBufferPool configuration option is equivalent to the -p command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 25). Note that the command line option overrides the configuration option.

- **FileCount.** The FileCount option in the [Options] section may be used to specify the number of files the server can have open simultaneously. The default value is ten times the UseCount. FileCount may need to be increased when every client application has more than ten files on the server open simultaneously. Reducing FileCount will reduce the server's shared and local memory requirements.
- **FileProcessCount.** The FileProcessCount option in the [Options] section determines the maximum number of run units that can have a file open at the same time. It applies to all file organizations. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same file process count. The maximum value for this keyword is 16384; the minimum value is 8. The default value is 1024. This option corresponds to the FILE-PROCESS-COUNT keyword in the RUN-FILES-ATTR configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **InxUseLargeLimit.** The InxUseLargeLimit option in the [Options] section determines which value to use for the lock limit when creating a version 4 indexed file. If the value is set to No (the default), the lock limit placed into the KIB is 2 GB for indexed files created by the RM/InfoExpress server. If the value is set to Yes, the lock limit placed into the KIB is the value of the LargeFileLockLimit option for indexed files created by the RM/InfoExpress server. Note that existing version 4 indexed files always use the lock limit stored in their KIB. This option corresponds to the USE-LARGE-FILE-LOCK-LIMIT keyword in the RUN-INDEX-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **LargeFileLockLimit.** The LargeFileLockLimit option in the [Options] section determines the limit for the location to apply locks to a file that will be accessed as a large file. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a particular file must use the same lock limit for that file. The lock limit also limits the actual amount of data that can be stored in a file. This limit will be used when a new indexed file is created provided the file version of the file is 3 or greater. Otherwise, this limit has no effect on indexed files. The value assigned to this keyword is specified in gigabytes (GB). The maximum value is 1048576, which equates to 1 petabyte (2^{50}). The minimum value is 1. The default value is 64. The lock limit for a normal file is 2 GB. This option corresponds to the LARGE-FILE-LOCK-LIMIT keyword in the RUN-FILES-ATTR configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.

- **MinimumBlockSize.** The MinimumBlockSize option in the [Options] section determines the minimum disk block size for the indexed files created by the RM/InfoExpress server, represented as a decimal number. The maximum value for this keyword is 4096; the minimum value is 256. The default value is 1024. This option corresponds to the MINIMUM-BLOCK-SIZE keyword in the RUN-INDEX-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **ReconnectTimeout.** The ReconnectTimeout option in the [Options] section determines the number of minutes the server will keep the file manager process serving the client intact waiting for the client to reconnect to it. In particular, all file and record locks remain in place while the client is disconnected and will prevent access by other run units. The default value is 180 (three hours).
- **RelUseLargeLimit.** The RelUseLargeLimit option in the [Options] section determines which value to use for the limit when applying locks to a relative file. If the value is set to No (the default), the lock limit for relative files is 2 GB. If the value is set to Yes, the value of the LargeFileLockLimit option is used. For record and file locks to perform correctly, all run units RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same lock limit for that file. This option corresponds to the USE-LARGE-FILE-LOCK-LIMIT keyword in the RUN-REL-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **RoundToNiceBlockSize.** The RoundToNiceBlockSize option in the [Options] section determines whether the block size computed for the indexed files created by the RM/InfoExpress server is forced to be a multiple of 512 (under Windows) or the value of BUFSIZ, taken from the C include file <stdio.h> (under UNIX). The default value for this keyword is Yes. This option corresponds to the ROUND-TO-NICE-BLOCK-SIZE keyword in the RUN-INDEX-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **SeqUseLargeLimit.** The SeqUseLargeLimit option in the [Options] section determines which value to use for the limit when applying locks to a sequential file. If the value is set to No (the default), the lock limit for sequential files is 2 GB. If the value is set to Yes, the value of the LargeFileLockLimit option is used. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same lock limit for that file. This option corresponds to the USE-LARGE-FILE-LOCK-LIMIT keyword in the RUN-SEQ-FILES configuration record specified for **runcobol**, as described in Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*.
- **UseCount.** The UseCount option in the [Options] section may be used to specify the number of clients that the server can serve simultaneously. This number must not be greater than the server's licensed client count. A reduced value on the UseCount option will reduce the server's shared and local memory requirements. The number of clients will default to the server's licensed client count unless the client count is "unlimited." In that case, it will default to 50.

The UseCount configuration option is equivalent to the -k command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 25). Note that the command line option overrides the configuration option.

UNIX Server-Specific Configuration Options

The following configuration options, listed alphabetically, are *specific* to the RM/InfoExpress UNIX server:

- **ConvertFileName.** The ConvertFileName option, which is located in the [Options] section and can have three values, is used to process the filename before the file is opened on the server's native operating system. When ConvertFileName=NoConvert (the default value), no filename mapping is performed. ConvertFileName=UpperCase indicates that the entire filename is mapped to uppercase before the Open request is attempted. ConvertFileName=LowerCase indicates that the entire filename is mapped to lowercase before the Open request is attempted.

The ConvertFileName configuration option is equivalent to the -c command line option, as described in the appropriate sections of [Starting the RM/InfoExpress UNIX Server Program](#) (on page 23) and [Starting and Stopping the RM/InfoExpress Windows Server Program](#) (on page 25). Note that the command line option overrides the configuration option.

- **DefaultServerUser.** The DefaultServerUser option in the [Security] section specifies the user name (at security levels 0 or 1) to run on the server when the security validation fails. Normally, the default server user will be allowed to access files that do not require high levels of security. The default server user must be a valid user on the server. The default is DefaultServerUser=rmsrver.
- **ServerSecurityLevel.** The ServerSecurityLevel option in the [Security] section specifies the security level number at which the UNIX server is to run (for more information, see [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) on page 49). Valid values range from 0 through 5. If this option is not specified, the server runs in compatibility mode, that is, the behavior is equivalent to an RM/InfoExpress version 2.0 server.

Sample RM/InfoExpress UNIX Server Configuration File

The following is a sample UNIX server configuration file (**rmixsrvr.ini**).

```
[Debug]
;;; InfoXDebug=DBGFILE

[Security]
IxPwFile=/usr/foo/ixpwfile
ServerSecurityLevel=5
DefaultServerUser=foo
```

Windows Server-Specific Configuration Options

The following configuration options are specific to the RM/InfoExpress Windows server:

- *share-name.* The *share-name* option in the [Sharing] section defines a share name and equates it with a pathname (*share-path*). On Windows, the edgename following the server machine name is a share name; for example, `\\server-name\share-name\rest-of-path-to-file`. All share names and paths are case-insensitive.

The server generates pathnames as follows:

1. Searches for the specified share name.
2. If found, substitutes the *share-path* for the name; if not found, searches for a null share name.
3. If found, prepends the *share-path* to the filename; if not found, checks the UseCurrentDirectory configuration flag.
4. If “Yes”, prepends the current working directory path to the filename; if “No”, returns a “35” error.

The generated pathname is then given to the RM/COBOL File Manager.

For example, if the [Sharing] section on host *serverW* contains

```
[Sharing]
cdrive=c:\tmp
AcctPayable=d:\acctpayable\data
=e:\guest\data
```

then the client path `\\serverW\cdrive\file.dat` causes the server to access

```
c:\tmp\file.dat
```

Similarly,

<code>\\serverW\cdrive\red\white\blue</code>	<code>c:\tmp\red\white\blue</code>
<code>\\serverW\acctpayable\master.inx</code>	<code>d:\acctpayable\data\master.inx</code>
<code>\\serverW\file1</code>	<code>e:\guest\data\file1</code>
<code>\\serverW\xyzy\tmp\junk.x</code>	<code>e:\guest\data\xyzy\tmp\junk.x</code>
<code>\\serverW\cdrive</code>	<code>e:\guest\data\cdrive</code>

If the null share name line `(=e:\guest\data)` did not exist and the server was started in `c:\bin`, then:

<code>\\serverW\file1</code>	<code>c:\bin\file1</code>
<code>\\serverW\xyzy\tmp\junk.x</code>	<code>c:\bin\xyzy\tmp\junk.x</code>
<code>\\serverW\cdrive</code>	<code>c:\bin\cdrive</code>

The server’s current working directory is the default path for the null share name provided the UseCurrentDirectory option is set to Yes.

If there is no [Sharing] section and if UseCurrentDirectory=No and UseSystemShares=No are both set, then every open returns a 35 error.

The path associated with a share name is intended to start with a drive letter and to specify a valid directory so that the resulting final pathname is an absolute pathname on the server machine.

- **UseCurrentDirectory.** The UseCurrentDirectory option in the [Options] section determines whether or not the server’s current directory pathname is prepended to the

filename when the edgename following the server name does not match any valid share name. UseCurrentDirectory=Yes is the default.

- **UseSystemShares.** The UseSystemShares option in the [Options] section determines whether or not the Windows server system share names are used. UseSystemShares=Yes is the default. A Windows server system share name is defined in the Shared As portion of the Sharing tab of the disk or directory folder Properties. Note that RM/InfoExpress server ignores the Access Type and Passwords portions of the Sharing tab. If UseSystemShares=No is specified, only the share names defined in the **rmixsrvr.ini** file [Sharing] section are used.

Sample RM/InfoExpress Windows Server Configuration File

The following is a sample Windows server configuration file (**rmixsrvr.ini**).

```
[Debug]
;;; InfoxDebug=DBGFILE

[Sharing]
cdrive=c:\
ShareTemp=d:\tmp\shared\files

[Options]
UseCurrentDirectory=Yes
UseSystemShares=Yes
```


Appendix E: RM/InfoExpress Security Parameter File Update Utility

This appendix describes how to use the **ixsecure.cob** program to update the **ixpwwfile** parameter file with security-related information that is used by the server to authenticate the clients. Note that **ixpwwfile** must exist when the RM/InfoExpress server is run at security levels greater than level 2. The implementation of file security in RM/InfoExpress is detailed in [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 49).

The RM/COBOL object program, **ixsecure.cob**, is included with the RM/InfoExpress media to enable users to build the security parameter file, **ixpwwfile**. The RM/COBOL runtime system (**runcobol**) is needed to run this object program.

A separate parameter file (**ixpwwfile**) is required for each of the client machines and one for the server machine. The parameter file for the client machine may have several entries, each giving information about this client and one of the servers with which this client communicates. Similarly, the parameter file for the server machine may have several entries, each giving information about this server and one of the clients that may connect to the server.

Using the Utility

To run the security parameter file update utility, use the following command:

```
runcobol ixsecure
```

If the security parameter file, **ixpwwfile**, is not in the current directory or has a different name, set the IXPWWFILE environment variable to the current pathname of the file.

The RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#), is displayed.

Figure 15: Security Parameter File Update Utility Main Screen

```
RM/InfoExpress Security Parameter File Update Utility

1. Add an entry
2. Modify an entry
3. Delete an entry
4. List all entries
5. Exit/Quit to system

Select option using arrow keys, number, or letter:
```

To choose an option on this screen, move the cursor with the arrow keys to a particular option and press Enter. Alternatively, you can type the option number or the first letter of the option description (it is not necessary to press Enter afterwards). To exit the utility program, choose option 5.

Note If RM/COBOL finds an error while performing the requested operation, a message with the appropriate RM/COBOL runtime error is displayed on the last line of the screen, and the utility waits for acknowledgment.

When the **ixpwfile** is empty (such as the first time this utility is run on a machine), a warning message is displayed and the file is created.

Adding a New Entry

To add a new entry, choose option 1 on the Main screen. The RM/InfoExpress Security Parameter File Update utility Add Entry screen, illustrated in [Figure 16](#), is displayed.

Figure 16: Add Entry Screen

```
RM/InfoExpress Security Parameter File Update Utility
ADD ENTRY

SERVER MACHINE NAME:.....
CLIENT MACHINE NAME:
SERVER USER NAME:
PASSWORD:
```

Type the requested information and press Enter on the last line to complete the entry. If you want to cancel the input at any time, press Esc. The utility displays the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 94. Otherwise, the entry will be added to the file.

The SERVER USER NAME is case-sensitive.

The SERVER MACHINE NAME and CLIENT MACHINE NAME are not case-sensitive; that is, they will be displayed as entered but will be mapped to uppercase for use by RM/InfoExpress.

Note If you are creating a security parameter file for an RM/InfoExpress server, the password field on the Add Entry screen should be left blank (simply press Enter in this field). The password in an entry for the server security parameter file is always ignored.

Modifying an Existing Entry

To modify an existing entry, choose option 2 on the Main screen. The RM/InfoExpress Security Parameter File Update utility Modify Entry screen, illustrated in [Figure 17](#), is displayed.

Figure 17: Modify Entry Screen

```
RM/InfoExpress Security Parameter File Update Utility
                          MODIFY ENTRY

SERVER MACHINE NAME:  unixserver.....
CLIENT MACHINE NAME:  mypc
SERVER USER NAME:    user1
PASSWORD:

Select using DOWN-ARROW/UP-ARROW/ENTER/ESC:
```

Using the arrow keys, choose the entry you wish to modify. Update the information on the screen and press Enter on the last line to complete the entry. If you want to cancel the input at any time, press Esc. The utility displays the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 94. Otherwise, the current entry in the file will be replaced by this information.

Deleting an Existing Entry

To delete an existing entry, choose option 3 on the Main screen. The RM/InfoExpress Security Parameter File Update utility Delete Entry screen, illustrated in [Figure 18](#), is displayed.

Figure 18: Delete Entry Screen

```
RM/InfoExpress Security Parameter File Update Utility
                        DELETE ENTRY

SERVER MACHINE NAME:  unixserver.....
CLIENT MACHINE NAME:  mypc
SERVER USER NAME:    user1
PASSWORD:

Select using DOWN-ARROW/UP-ARROW/ENTER/ESC:
```

Using the arrow keys, choose the entry you wish to delete and press Enter. If you want to cancel the input at any time, press Esc. The utility displays the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 94. Otherwise, the current entry in the file will be deleted.

After successful deletion, the following message is displayed for confirmation:

```
Confirm deletion (Y/N)
```

Type Y to confirm deletion. (To abandon the deletion, type N.) The following message is displayed to confirm the successful deletion of the entry from the file:

```
Record deleted successfully. Press any key...
```

Listing All Entries

To list all entries in the file, choose option 4 on the Main screen. The RM/InfoExpress Security Parameter File Update utility List Entries screen, illustrated in [Figure 19](#), is displayed showing the following information.

Figure 19: List Entries Screen

```
RM/InfoExpress Security Parameter File Update Utility
                        LIST ENTRIES

Server Machine Name  Client Machine Name  Server User Name
unixserver1          mypc                  user1
unixserver2          mypc                  user2

Press any key. . .
```

Press any key to return to the RM/InfoExpress Security Parameter File Update utility Main screen, illustrated in [Figure 15](#) on page 94. If the file contains more entries than can be

displayed on one screen, additional screens will be displayed when a key is pressed. When all entries have been displayed, pressing a key will return to the Main screen.

Note The password information is not displayed.

Appendix F: Using RM/InfoExpress with Relativity

RM/InfoExpress can be used with Relativity for RM/COBOL to access the catalog and/or files stored on a server running the RM/InfoExpress server program. This appendix provides instructions for RM/InfoExpress Windows clients.

Note Some earlier versions of Relativity are called Relational DataBridge.

Changes to Relativity Configuration for 32-Bit Windows Clients

The 32-bit RM/InfoExpress Windows client software (**rmtcp32.dll**) is installed with Relativity. Note that the RM/InfoExpress Windows client software is not supplied with the RM/InfoExpress server software or versions of Relativity prior to 2.5. It is distributed with the RM/COBOL for Windows runtime or development system or, alternatively, it can be downloaded from the Micro Focus web site (supportline.microfocus.com). Contact Micro Focus Customer Care for more information.

The configuration procedures begin in the section [Configure Relativity to Use RM/InfoExpress](#) (on page 100). These instructions assume the following:

- You have the RM/InfoExpress server main program and Server Display program installed and running on your server machine. For more information, see the installation instructions in [Chapter 1: Installation and Verification](#) (on page 7).
- You have the complete Microsoft TCP/IP software package installed and configured in the Networking option on the Control Panel. (See also Chapter 1 of this manual.)
- You are running Windows clients.

Create a Configuration File

Create a file, called **rmixclnt.ini**, in the %ALLUSERSPROFILE% directory (usually c:\ProgramData) at the path `Micro Focus\RM\RMInfoExpressv12 [-64]` to set configuration parameters for RM/InfoExpress client programs. Include the following entry:

```
[Winsock]  
UseBlockingIO=Yes
```

This entry prevents a 10055 system error: “No available buffer space”. This configuration parameter is discussed in [Client-Specific Configuration Options](#) (on page 84).

Configure Relativity to Use RM/InfoExpress

There are two aspects to configuring the Relativity ODBC data source setup: configuring Relativity to use RM/InfoExpress and specifying the location of the Relativity catalog on the server.

Note All setup options can be configured from the Windows client workstation using the ODBC Data Source Administrator that is distributed with Relativity.

To configure Relativity to use RM/InfoExpress:

1. On the Windows client workstation, open the **Control Panel**.
2. To access the ODBC Data Source Administrator from the Control Panel, double-click **Administrative Tools**.
3. On the Administrative Tools page, double-click **Data Sources (ODBC)**.
4. In the ODBC Data Source Administrator dialog box, select the **User DSN** tab and then click **Add**.
5. In the Create Data Source dialog box, double-click **Relativity (*.rcg)** as the driver type.
6. In the Relativity dialog box, select the **RM/COBOL** option in the File Manager tab and then select the **RM/InfoExpress** tab to display the RM/InfoExpress page.
7. In the RM File Manager options area, select the **Enable RM/InfoExpress** check box, which enables access to RM/InfoExpress.

The option for “Allow File Creation” is selected by default.

8. Next, click the **Display Initial Message Box** option to verify correct operation.

This action is useful when first configuring Relativity to use RM/InfoExpress. A message box will be displayed when RM/InfoExpress is first called. If the message box is not displayed, it indicates that any problems are not network related, but are caused by the software installation. Similarly, if there is a problem but the message box is displayed, the problem is related to the network.

Note After installation is verified, you may return to the RM/InfoExpress tab using the 32-bit ODBC Administrator, as described in Step 3, and clear the Display Initial Message Box option.

9. In the Relativity dialog box, select the **DSN** tab.

This tab has entries for the data source name and description, as well as buttons to select or create a Relativity catalog.

Continue by specifying the location of the Relativity catalog on the server:

1. In the **Data Source Name** box on the DSN tab, enter the name needed for the data source (what users will see from their ODBC-enabled application, such as Microsoft Access or Excel).
2. Click the **Select Catalog** button. The Select Catalog for Data Source dialog box is displayed.

3. In the Select Catalog for Data Source dialog box, select the **Use RM/InfoExpress only** check box.
4. In the **File name** box, enter the complete pathname.

You must specify the name in the following format:

```
\\RMInfoExpressServer\PathToFile
```

where *RMInfoExpressServer* must match the TCP/IP host name for the server machine on this client (for example, \\HOSTNAME\test.rcg). The following example specifies a Relativity catalog called **shirt3.rcg** in the directory **/usr/relsamples** on the server **unixware21**:

```
\\unixware21\usr\relsamples\shirt3.rcg
```

5. After you enter a valid RM/InfoExpress server and filename, click **Open**. The Relativity catalog name will be validated and returned to the Relativity dialog box as the name of the Relativity catalog for the data source. This information is displayed in the Catalog Name area.
6. In the Relativity dialog box, click **OK** to complete creation of the Relativity data source.

Appendix G: Summary of Enhancements

This appendix provides a summary of the new features and changes in the various releases of RM/InfoExpress. It also tells you where to look for more information about them.

The enhancements and changes for the most recent release described by this document are listed first. The information in this appendix is historical and was accurate at the time written for the specific version being described. Various features may have changed in later releases, and, possibly, some features may have been removed.

Note The RM/InfoExpress version number refers to the RM/InfoExpress server; RM/InfoExpress client(s) do not have version numbers.

Version 12 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 12:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 12 compatibility.
- Client-side logging is a new capability to diagnose initial connection problems from the RM/InfoExpress client to the RM/InfoExpress server. The RMCLIENT.LOG file logs errors that are encountered in the pre-connection, connect, and the first message sent and received operations. In addition, this new log file contains the following information for each connection:
 - the client-side host name
 - the client-side IP address (from gethostbyname)
 - the server-side host name
 - the server-side IP address
 - the result of the connect request

For more information, see the StartupLogPath configuration parameter in [Client-Specific Configuration Options](#) (on page 84) of Appendix D: *Configuring RM/InfoExpress*.

Version 11 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 11:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 11 compatibility.
- Support for Microsoft Windows Vista was added.

Version 10 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 10:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 10 compatibility.

Version 9 Enhancements

The following summarizes the major new enhancements in RM/InfoExpress version 9:

- The RM/InfoExpress server File Manager has been updated to RM/COBOL version 9 compatibility. (For further information, see “Version 9 Enhancements” in Appendix L: *Summary of Enhancements*, of the *RM/COBOL User’s Guide*.)
- The RM/InfoExpress Server Display main screen now shows the server uptime (in days) at the end of the date and time line. It can also now display 999,999,999,999 (one trillion—U.S.—minus one) total messages after which the count wraps back to zero. See [Server Display Commands](#) (on page 38).
- The Windows server (**rmsrvtcp.exe**) now uses WinSock 2. In particular, this allows a much larger connection queue (WinSock 1 had a maximum backlog of 5), which should avoid error 10061.
- The Windows server installation creates a Windows Firewall Exception, if applicable, for the RM/InfoExpress TCP port number 21069. If you change the port number (which is *not* recommended), you must change both the **services** file and the Windows Firewall configuration.

Version 8 Enhancements

This section summarizes the major enhancements available in version 8 of RM/InfoExpress.

Support for Large Files

Because the RM/InfoExpress server contains the RM/COBOL file management system, the RM/InfoExpress server includes the same support for large files as that offered by the RM/COBOL runtime system (**runcobol**).

When running under operating systems that support files larger than 2 GB (gigabytes), the RM/COBOL runtime system allows RM/COBOL files to grow past limits imposed in previous versions. This support is provided by the LARGE-FILE-LOCK-LIMIT keyword of the RUN-FILES-ATTR configuration record. In order to use this new limit on relative or sequential files, you must use the USE-LARGE-FILE-LOCK-LIMIT keyword in a RUN-REL-FILES or RUN-SEQ-FILES configuration record. In RM/InfoExpress, the server configuration file (**rmixsrvr.ini**) contains keywords that correspond to those in the RM/COBOL runtime system and that provide the same support. For record and file locks to perform correctly, all RM/InfoExpress servers and RM/COBOL runtime systems opening a file must use the same lock limit for that file.

On the Windows 9x class of operating systems, files up to 4 gigabytes (GB) are supported. The Windows NT class of operating systems supports multiple terabyte files on the NT file system. Only files on FAT32 (file system format supported for Windows 9x-class operating systems) or NTFS (file system format supported on Windows NT-class operating systems) may be larger than 2 GB.

For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 79) of this manual and Chapter 10: *Configuration*, of the *RM/COBOL User's Guide*. In order to use this new limit on indexed files, you must use an indexed file version level of 3 (see the "Very Large File Support" topic in Chapter 8: *RM/COBOL Features*, of the *RM/COBOL User's Guide* for more information). Additional information about UNIX and Windows systems that support large files also can be found in the "Using Large Files" topic in Chapter 2: *Installation and System Considerations for UNIX* and in Chapter 3: *Installation and System Considerations for Microsoft Windows*, respectively, of the *RM/COBOL User's Guide*.

Atomic I/O Support for File Version Level 4

In RM/InfoExpress, as in RM/COBOL, file version level 4 indexed files optionally support the new "atomic I/O" capability, which provides a means for users to avoid almost all 98 errors caused by failures that occur while a file is open. Files created with atomic I/O will almost never need recovery. If a crash occurs during a COBOL I/O operation, the file will be automatically and quickly recovered the next time the file is opened or a write operation is performed. The ENABLE-ATOMIC-IO keyword has been added to the RUN-INDEX-FILES configuration record to determine whether indexed files created by the runtime system use atomic I/O.

The default indexed file version for new files has been changed from 2 to 4 to automatically provide the higher level of reliability to new files. The DEFAULT-FILE-VERSION-NUMBER keyword of the RUN-INDEX-FILES configuration record may be used to specify a different value.

Version 4 indexed files may, like version 3 files, grow to a larger size than version 0 or 2 files. However, unlike version 3 files, version 4 files may be either large or regular sized files, depending on the new USE-LARGE-FILE-LOCK-LIMIT keyword of the RUN-INDEX-FILE configuration record. This new keyword determines whether the LARGE-FILE-LOCK-LIMIT or the FILE-LOCK-LIMIT keyword of the RUN-FILES-ATTR configuration record is used to determine the largest address that can be locked in the file. This, in turn, determines how large the file can be.

Limited Automatic Session Reconnection

Beginning with version 8, a limited reconnection capability, which allows a connection that becomes broken to be reconnected automatically, has been added to the RM/InfoExpress client and server logic. The client and server continue normal operation without the client run

unit (COBOL program) ever being aware of the disconnection. To enable this capability, you must set `ReconnectEnable=Yes` in the [Options] section of the `rmixsrvr.ini` server configuration file, as explained in [Appendix D: Configuring RM/InfoExpress](#) (on page 79).

Client Path Prefix Inclusion and Exclusion

A new feature has been added in version 8 to allow the RM/InfoExpress client to exclude selected UNC-style pathnames (beginning with `\\` or `//`) from access via RM/InfoExpress. Prior versions of RM/InfoExpress always attempted access to all UNC-style pathnames. In the `rmixclnt.ini` configuration file in the [Options] section, you can specify `PathPrefixIncluded=list` and `PathPrefixExcluded=list`. For more information, see [Appendix D](#) (on page 79).

Version 2.1 Enhancements

This section summarizes the major enhancements available in version 2.1 of RM/InfoExpress.

RM/InfoExpress Server Now Supported on Windows NT Version 4.0

A version of the RM/InfoExpress server software now runs on the Windows NT Server (version 4.0).

File Security on the RM/InfoExpress UNIX Server

The RM/InfoExpress UNIX server now provides enhanced file security. The level of security is specified at the time the server is invoked. The server performs various validations on the authenticity of the client(s) before granting access to a file. For more information, see [Chapter 6: File Security on the RM/InfoExpress UNIX Server](#) (on page 49).

New Utility to Update RM/InfoExpress Parameter File

To make the RM/InfoExpress server screens display similar information about all types of clients, all new clients now provide client-specific information (such as *client-machine-name* and *user-name* of the client on the server, as described in Chapter 6) to the server from a security parameter file. This parameter file, default name `ixpwwfile`, is created using a utility program, `ixsecure.cob`. For more information about how to use this utility, refer to [Appendix E: RM/InfoExpress Security Parameter File Update Utility](#) (on page 93).

Improved Server Screens

Additional information has been added to the server screens to identify the clients. For example, the Error Log screen now displays the name of the file on which the error occurred.

Optional Message Compression

This version of RM/InfoExpress optionally compresses messages before transmitting them on the network. Depending on the compressibility of the messages, which include the records from RM/COBOL data files, compression may improve the performance of RM/InfoExpress over WANs and heavily loaded LANs.

Optional Message Encoding

This version of RM/InfoExpress optionally encodes messages before transmitting them on the network to provide more security for the COBOL data.

Initialization File Support

All implementations of RM/InfoExpress now allow configuration information to be stored in a file that is in an .INI format. For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 79).

-m Server Option Obsolete

The RM/InfoExpress server now automatically expands the message buffer size (previously set using the -m option on the server command line) as required by each session. The user should no longer receive the error RMIX_ERR_OUT_OF_MEMORY when transmitting records larger than 5000 bytes.

Use Count Check by the Server

The RM/InfoExpress server now limits the number of client connections to the value specified by the UseCount configuration option or the licensed use count, whichever is less. For more information, see the [UseCount configuration option](#) (on page 88).

New File Count Option

The RM/InfoExpress server can now be configured for any number of simultaneously open files, independent of the licensed use count. For more information, see the [FileCount configuration option](#) (on page 87).

New Option to Handle the Display of Long Filenames

The RM/InfoExpress screen handler (Server Display) program can now be configured to display more reasonably a filename that is too long to fit in the display field of the screen handler. For more information, see the DotsBias configuration option as described in [Appendix D](#) (on page 79).

Version 2.0.2 Enhancements

This section summarizes the major enhancements available in version 2.0.2 of RM/InfoExpress.

New Server Option Enables the RM/plusDB Interface

The `-b` option has been added in order to enable RM/InfoExpress to communicate with RM/plusDB. Use the `-b` option when invoking the RM/InfoExpress server with the RM/plusDB product if every filename is to be checked for an RM/plusDB table name by the server before opening the RM/COBOL data file.

Note Beginning with version 8 of RM/InfoExpress, Micro Focus no longer develops or supports RM/plusDB. This option is maintained for backward compatibility only and should be ignored. Do not specify this option unless you have used RM/plusDB in your application.

Version 2.0 Enhancements

This section summarizes the major enhancements available in version 2.0 of RM/InfoExpress.

RM/InfoExpress UNIX Server Filename Case-Sensitivity

For the RM/InfoExpress UNIX server, the `-c` option allows you to specify whether to map the filename on an Open request to uppercase, lowercase, or leave it unaltered (the default). For more information, see [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) (on page 23).

RM/InfoExpress UNIX Server Configuration Option

For the RM/InfoExpress UNIX server, the `-c 1` configuration option must be specified if the pathnames are to be converted to lowercase (as in the previous version). The default is no conversion. For more information, see [Chapter 2](#) (on page 23).

RM/InfoExpress UNIX Server Runs as a Daemon

This version of the RM/InfoExpress UNIX server runs unattended in the background and no longer requires an additional terminal. The server uses data structures built-in shared memory. The server modifies the data structures using a well-defined administrative API (Application Programming Interface) to preserve the integrity of the server data structures.

RM/InfoExpress Screen Handler Program

The screen handler (Server Display) portion of RM/InfoExpress has been removed from the server program and is now a separate application. The screen handler application shares the

data structures present in shared memory along with the server daemon. The screen handler accesses the data structures using a well-defined administrative API.

The screen handler program is improved to read an entire screen of information in a single operation, thus providing more consistency to the data it displays.

Under UNIX, the screen handler can be invoked more than once on the system, making it possible for multiple users to view the server statistics simultaneously. The screen handler application can be run from any terminal on the UNIX system.

The command sequence, Terminate Display, now terminates the screen handler program without affecting the server or any clients.

The following sections describe two additional modifications to the screen handler program.

Changes in the Default Behavior

The default behavior of the screen handler (Server Display) program allows only the termination of the screen handler program itself. This prevents you from accidentally stopping the server or a specific client. To terminate the server or a particular client, you must specify the `-t` option (as described in [Chapter 2: Configuring and Running the RM/InfoExpress Server](#) on page 23) when you start the screen handler program.

New Screens

The Error Information screen has been replaced by two new screens.

The Open Log screen displays information about the most recent 24 open operations performed by the server. The Error Log screen displays information about the most recent 24 errors, including the complete error code and location of the error. For more information, see [Chapter 5: RM/InfoExpress Server Operations](#) (on page 37).

More COBOL Information Added to Existing Screens

More COBOL-related information has been added to existing screens. The Client Files Information screen now displays the organization, open mode, and the access mode of each file currently opened by the client. A new field, System name, has been added to the Client Information screen. This field displays the type of operating system on which the client is running. See [Chapter 5](#) (on page 37) for further details.

Improved Error Handling

Error handling has been improved in this version of RM/InfoExpress. Additional information, such as the location of the occurrence, is also now maintained.

KEEPSESSION Configuration Option

The default value for the KEEPSESSION configuration option has changed from NO to YES. For more information, see [Appendix D: Configuring RM/InfoExpress](#) (on page 79).

Index

A

AcceptPassword configuration option 84

B

Block size 88

Bold type, use of as a document convention 3

Browsers 9–14

BSD Sockets software, error messages 64

Buffer pool size 24, 27, 87

BUFFER-POOL-SIZE keyword, RUN-FILES-ATTR configuration record 87

C

-c command line option, server 24, 89

Case-sensitivity, configuration options 24, 80, 108

Character-based terminals 37

Client program 8

accessing 29, 33

configuration file options 79, 81, 84

executing RM/COBOL programs with 32, 35

installation 14

pointing to network data files 29–32, 33–35

setting up TCP/IP package 14

system requirements 7–8

terminating communication to 25, 28, 45, 77

verification, installation 15–22, 15–22

Clients, validating 49

Command line options, server 23, 24, 27

buffer pool size (-p) 24, 27, 87

debug (-d) 24, 27, 82

display program (-t) 25, 26, 28, 45

mapping filenames (-c) 24, 89

maximum amount of data handled by TCP send function (-z) 25, 27, 82

maximum number of clients open (-k) 24, 27, 88

Communication, client and server machines 18, 21

Compatibility mode 50, 53, 89

Compiler options (RM/COBOL), hyphens, used with 3

Configuration 79, *See also* Configuration file options;

Command line options, server

client 79, 81, 84

files, samples of 80, 86, 89, 91

server 79, 81, 86, 89

with RM/COBOL 79, 104

Configuration file options 79

client 84

AcceptPassword 84

KeepSession 84

PathPrefixExcluded 84

PathPrefixIncluded 84

ReconnectDelay 85

StartLogPath 85

UseBlockingIO 86

client and server 81

EncodeData 81

IgnoreHangupError 81

InfoxDebug 24, 27, 82

IxCompress 82

IxPwFile 54, 82

MaxSendSize 25, 27, 82

ReconnectEnable 83

server 23, 86, 89

ConvertFileName 24, 89

DefaultServerUser 51, 53, 60, 89

DotsBias 43, 44, 86

FileBufferPool 25, 27, 87

FileCount 87

FileProcessCount 87

InxUseLargeLimit 87

LargeFileLockLimit 87

MinimumBlockSize 88

ReconnectTimeout 88

RelUseLargeLimit 88

RoundToNiceBlockSize 88

SeqUseLargeLimit 88

ServerSecurityLevel 50, 53, 60, 89

share-name 89

UseCount 24, 27, 88

UseCurrentDirectory 90

UseSystemShares 91

Configuration files

client (rmixclnt.ini) 54–60, 79

server (rmixsrvr.ini) 54–60, 79

Configuration records, RM/COBOL

EXTERNAL-ACCESS-METHOD 29, 33

RUN-FILES-ATTR 87, 105

RUN-REL-FILES 105

RUN-SEQ-FILES 105

Console interface 37

Conventions and symbols used in this manual 3

ConvertFileName configuration option 24, 89

Customer Care 4

D

- d command line option, server 24, 27, 82
- Data-names, RM/COBOL programs 31, 35
- Debugging 24, 27, 82
- DefaultServerUser configuration option 51, 53, 60, 89
- Directory search sequence, synonyms 30, 34
- DNS *See* Domain Name Service
- Documentation overview 1
- Domain Name Service 9, 14
- DOS environment variables 30
- DotsBias configuration option 43, 44, 86
- Downloading, from Web 9–14

E

- Ellipsis in filenames 86
- EncodeData configuration option 81
- Encoding messages 81
- Enhancements to RM/InfoExpress
 - version 10 104
 - version 11 104
 - version 12 103
 - version 2.0 108
 - version 2.0.2 108
 - version 2.1 106
 - version 8 104
 - version 9 104
- Environment variables
 - DOS 30
 - IXCONFIG 54, 80
 - IXPWFIL 54
 - IXPWFIL 93
 - KEEPSESSION 84
 - PATH 21
 - RM_CLIENT_LOG_PATH 85
 - RM_RECONN_LOG_PATH 83
 - RUNPATH 21, 31, 34
 - troubleshooting 77
- Error messages 63–74
- Explicit pathnames 31, 34
- EXTERNAL-ACCESS-METHOD configuration
 - record 29, 33

F

- Failure to locate file or path 77
- File access, network 29, 33
- File lock limit 87, 88, 105
- File security 8, 49, 93, *See also* Security, on UNIX server
- File security parameter file update utility
 - (ixsecure.cob) 8, 50, 93
- File version level, in indexed files 87, 105
- FileBufferPool configuration option 25, 27, 87

- FileCount configuration option 87
- FileProcessCount configuration option 87
- FILE-PROCESS-COUNT keyword, RUN-FILES-ATTR configuration record 87
- Files
 - client program
 - librminfo.so, UNIX 8, 14, 20, 33
 - rmtcp32.dll, Windows 8, 14, 29
 - configuration
 - rmixclnt.ini 79, 86
 - rmixsrvr.ini 23, 79, 89, 91
 - sample of 80
 - hosts 9, 14, 20
 - rhosts 49, 52, 55
 - server display program
 - rmdisptcp, UNIX 8, 23
 - rmdistcp.exe, Windows 8
 - server program
 - rmservertcp, UNIX 8, 23
 - rmsrvtcp.exe, Windows 8
 - services 9, 14, 20

H

- hosts file 9, 14, 20
- Hyphen (-), using with optional, RM/COBOL compilation and runtime options 3

I

- IgnoreHangupError configuration option 81
- Indexed files 87, 105
- InfoDebug configuration option 24, 27, 82
- infxdmo, verification program 21
- Installation
 - client program 8, 14
 - server display program 8, 9, 12
 - server program 8, 9, 12
 - setting up TCP/IP package for
 - RM/InfoExpress clients 14
 - RM/InfoExpress servers 9
 - system considerations 13, *See also* Configuration records
 - system requirements 7–8
 - verification 15–22
- InxUseLargeLimit configuration option 87
- IPC objects, removing after server failure 47, 78
- Italic type, use of as a document convention 3
- IxCompress configuration option 82
- IXCONFIG environment variable 54, 80
- ixpwfile (security parameter file) 50, 52, 54, 93
- IxPwFile configuration option 54, 82
- IXPWFIL environment variable 54, 93
- ixsecure.cob, file security parameter file update utility 8, 50, 93
- ixverify, Windows client verification program 17

K

- k command line option, server 24, 27, 88
- Keepalive support, TCP 83
- KeepSession configuration option 84
- KEEPSESSION environment variable 84
- Key combinations, document convention for 3
- Keyboard interface, server display program 37
- kill command, UNIX 47, 78

L

- Large file support 87, 88, 104
- LargeFileLockLimit configuration option 87
- LARGE-FILE-LOCK-LIMIT keyword, RUN-FILES-ATTR configuration record 87, 105
- liant.lic (license certificate file) *See* License file
- librminfo.so, client program, UNIX 8, 14, 20, 33
- License file 10, 12, 13
 - use count 88
- Limits and ranges 75
- Local area networks (LANs) 1
- Log file, initial client connection to server 85

M

- MaxSendSize configuration option 25, 27, 82
- Messages
 - compression 82
 - encoding 81
 - error 63–74
 - large 82
- MinimumBlockSize configuration option 88

N

- Network
 - accessing clients 29, 33
 - compressing messages 82
 - data files, pointing to 29–32, 33–35
 - security 54, *See also* Security, on UNIX server

O

- Organization of this manual 1

P

- p command line option, server 24, 27, 87
- Passwords, client 84
- PATH environment variable 21
- Pathnames 77
 - case-sensitivity 24
 - explicit 31, 34
 - specifying 29–32, 33–35
 - UNC-style 84, 106
- PathPrefixExcluded configuration option 84

- PathPrefixIncluded configuration option 84
- PDF format 1
- Performance, network 82
- Ports, user 9, 14

R

- ReconnectDelay configuration option 85
- ReconnectEnable configuration option 83
- Reconnecting server and client 83, 85
- ReconnectTimeout configuration option 88
- Related publications 2
- Relativity, using with 99
- RelUseLargeLimit configuration option 88
- rhosts file 49, 52, 55
- RM/COBOL
 - client program 8, 14
 - compilation options, hyphens, used with 3
 - configuration file options 79, 104
 - list support modules loaded by the RM/COBOL runtime option (V) 20
 - runtime options, hyphens, used with 3
 - using with RM/InfoExpress 29, 33
- RM/InfoExpress
 - client program 8
 - accessing 29, 33
 - configuration file options 79, 81, 84
 - executing RM/COBOL programs with 32, 35
 - installation 14
 - pointing to network data files 29–32, 33–35
 - setting up TCP/IP package 14
 - system requirements 7–8
 - terminating communication to 25, 28, 45, 77
 - verification, installation 15–22
 - configuring with RM/COBOL 79, 104
 - enhancements, summary of 103
 - error messages 63–74
 - installation 9, 12, 14
 - limits and ranges 75
 - messages 63–74
 - Relativity, using with 99
 - RM/COBOL, using with 29, 33
 - security, on UNIX server 49, 82, 89, 93, *See also* Security, on UNIX server
 - server display program 8, 9, 12
 - command line option 25, 26, 28, 45
 - commands
 - Clients 40
 - Error Log 44
 - Files 41
 - Main 40
 - Open Log 43
 - Terminate 45
 - Client 46
 - Display 46
 - Server 46
 - keyboard functions 37

- main screen 38
 - screen format, illustrated 38
 - starting 23, 25
 - terminating 25, 28, 45
 - server program 8
 - command line options 23, 24, 27
 - configuration 23
 - configuration file options 79, 81, 86, 89
 - default server user 51, 53
 - installation 9
 - security, on UNIX 49, 82, 89, 93, *See also*
 - Security, on UNIX server
 - setting up TCP/IP package 9
 - starting 23, 25
 - automatically 26
 - System account 16, 26
 - system requirements 7–8
 - terminating 25, 28, 45
 - verification, installation 15–22
 - version number, significance of 103
 - system requirements, installation 7–8
 - terminating 45
 - troubleshooting 77
 - verification, installation 15
 - RM_CLIENT_LOG_PATH environment variable 85
 - RM_RECONN_LOG_PATH environment variable 83
 - RMCLIENT.LOG 85
 - rmdisptcp, server display program, UNIX 8
 - rmdistcp.exe, server display program, Windows 8
 - rmixclnt.ini, client configuration file 54–60, 79, 86,
 - See also* Configuration file options
 - rmixsrvr.ini, server configuration file 23, 54–60, 79,
 - 89, 91, *See also* Configuration file options
 - rmservrtecp, server program, UNIX 8
 - rmsrvtcp.exe, server program, Windows 8
 - rmtcp32.dll, client program, Windows 8, 14, 29
 - RoundToNiceBlockSize configuration option 88
 - RUN-FILES-ATTR configuration record 105
 - BUFFER-POOL-SIZE keyword 87
 - FILE-PROCESS-COUNT keyword 87
 - LARGE-FILE-LOCK-LIMIT keyword 87, 105
 - RUNPATH environment variable 21, 31, 34
 - RUN-REL-FILES configuration record, USE-
 - LARGE-FILE-LOCK-LIMIT keyword 88, 105
 - RUN-SEQ-FILES configuration record, USE-
 - LARGE-FILE-LOCK-LIMIT keyword 88, 105
 - Runtime options (RM/COBOL), hyphens, used with 3
- S**
- Screen handler program *See* Server display program
 - Security, on UNIX server 49
 - .rhosts file 49, 52, 55
 - client validation 53
 - clients, non-UNIX 53
 - compatibility mode 50, 53, 89
 - configuration file options 50, 51, 53, 54, 60
 - default server user 51, 53, 60, 89
 - file security 49, 93
 - security levels 50, 53, 54, 60, 89
 - security parameter file (ixpwfile) 50, 52, 54, 82, 93
 - setting up network 54
 - Send operations, maximum allowed 25, 27, 82
 - SeqUseLargeLimit configuration option 88
 - Server configuration file (rmixsrvr.ini) 23
 - Server display program 8, 9, 12
 - command line option 25, 26, 28
 - commands
 - Clients 40
 - Error Log 44
 - Files 41
 - Main 40
 - Open Log 43
 - Terminate 45
 - Client 46
 - Display 46
 - Server 46
 - keyboard functions 37
 - main screen 38
 - screen format, illustrated 38
 - starting 23, 25
 - terminating 25, 28, 45, 46
 - Server program 8
 - command line options 23, 24, 27
 - configuration file options 79, 81, 86, 89
 - installation 9, 12
 - security, on UNIX 49, 82, 89, 93
 - .rhosts file 49, 52, 55
 - client validation 53
 - clients, non-UNIX 53
 - compatibility mode 50, 53
 - configuration file options 50, 51, 53, 54, 60
 - default server user 51, 53, 60
 - file security 49
 - security levels 50, 53, 54, 60
 - security parameter file (ixpwfile) 50, 52, 54
 - server display program 9, 12
 - setting up TCP/IP package 9
 - starting 15, 16, 17, 23, 25
 - automatically 26
 - System account 16, 26
 - system requirements 7–8
 - terminating 25, 28, 45
 - verification, installation 15–22
 - version number, significance of 103
 - ServerSecurityLevel configuration option 50, 53, 60, 89
 - services file 9, 14, 20
 - share-name configuration option 89
 - Starting

- server display program 23, 25
- server program 23, 25
 - automatically 26
 - on a specific account 27
- StartupLogPath configuration option 85
- Support services, technical 4
- Symbols and conventions used in this manual 3
- Synonyms, directory search sequence 30, 34
- System account 16, 26
- System requirements, installation 7–8

T

- t command line option, server display 25, 26, 28, 45
- TCP/IP communication protocol 7, 9, 14, 15
 - keepalive support 83
 - send function 25, 27, 82
- TCP/IP package, setting up for
 - RM/InfoExpress clients 14
 - RM/InfoExpress servers 9
- Terminating 25, 28
 - client communications 45, 46
 - client entries, troubleshooting 77
 - server 45, 46
 - server display 45, 46
- Transmission Control Protocol/Internet Protocol *See* TCP/IP communication protocol
- Troubleshooting
 - client entries not terminating 77
 - failure to locate file or path 77
 - removing IPC objects after server failure 47, 78

U

- UNC-style pathnames 84, 106
- UNIX client 8, *See also* Client program; RM/InfoExpress
 - accessing 33
 - configuration file options 79, 81, 84
 - installation 14
 - system requirements 7–8
 - verification, installation 15–22
- UNIX server 8, *See also* Server program; RM/InfoExpress
 - command line options 24, 25
 - configuration file options 79, 81, 86, 89
 - file security parameter file update utility (ixsecure.cob) 8, 50, 93
 - installation 12
 - security 49
 - server display program 37
 - starting 23
 - verification, installation 15–22
- UseBlockingIO configuration option 86
- UseCount configuration option 24, 27, 88
- UseCurrentDirectory configuration option 90

- USE-LARGE-FILE-LOCK-LIMIT keyword
 - RUN-REL-FILES configuration record 88, 105
 - RUN-SEQ-FILES configuration record 88, 105
- UseSystemShares configuration option 91

V

- V Runtime Command option, RM/COBOL 20
- Validating clients 49
- Verification
 - UNIX client 20
 - UNIX client and server communication 21
 - UNIX server 16, 17
 - Windows client 17
 - Windows client and server communication 18
 - Windows server 15
- Version number, RM/InfoExpress client 103
- Version number, RM/InfoExpress server 103

W

- Web browser 9–14
- Wide area networks (WANs) 1
- Windows client 8, *See also* Client program; RM/InfoExpress
 - accessing 29
 - configuration file options 79, 81, 84
 - installation 14
 - system requirements 7–8
 - verification, installation 15–22
- Windows console 37
- Windows operating systems 8
- Windows server 8, *See also* Server program; RM/InfoExpress
 - command line options 27, 28
 - configuration file options 79, 81, 86, 89
 - installation 9
 - server display program 9, 37
 - starting 25
 - automatically 26
 - System account 16, 26
 - verification, installation 15–22
- Windows service *See* Windows Service Control Manager (SCM)
- Windows Service Control Manager (SCM) 11, 12, 15
- Windows Sockets software 17
 - blocking mode 86
 - error messages 64, 71, 73
 - IgnoreHangupError configuration option 81

Z

- z command line option, server 25, 27, 82

