

PROGRESS[®] ORBIX[®]

Orbix Programmer's Reference Java Edition

Version 3.3, SP11 March 2012

Progress Orbix v3.3.11

© 2012 Progress Software Corporation and/or its subsidiaries or affiliates. All rights reserved.

These materials and all Progress® software products are copyrighted and all rights are reserved by Progress Software Corporation. The information in these materials is subject to change without notice, and Progress Software Corporation assumes no responsibility for any errors that may appear therein. The references in these materials to specific platforms supported are subject to change.

Actional, Apama, Artix, Business Empowerment, Business Making Progress, Corticon, Corticon (and design), DataDirect (and design), DataDirect Connect, DataDirect Connect64, DataDirect Technologies, DataDirect XML Converters, DataDirect XQuery, DataXtend, Dynamic Routing Architecture, Empowerment Center, Fathom, Fuse Mediation Router, Fuse Message Broker, Fuse Services Framework, IONA, Making Software Work Together, Mindreef, ObjectStore, OpenEdge, Orbix, PeerDirect, Powered by Progress, PowerTier, Progress, Progress DataXtend, Progress Dynamics, Progress Business Empowerment, Progress Empowerment Center, Progress Empowerment Program, Progress OpenEdge, Progress Profiles, Progress Results, Progress Software Business Making Progress, Progress Software Developers Network, Progress Sonic, ProVision, PS Select, RulesCloud, RulesWorld, Savvion, SequeLink, Shadow, SOAPscope, SOAPStation, Sonic, Sonic ESB, SonicMQ, Sonic Orchestration Server, SpeedScript, Stylus Studio, Technical Empowerment, WebSpeed, Xcalia (and design), and Your Software, Our Technology-Experience the Connection are registered trademarks of Progress Software Corporation or one of its affiliates or subsidiaries in the U.S. and/or other countries. AccelEvent, Apama Dashboard Studio, Apama Event Manager, Apama Event Modeler, Apama Event Store, Apama Risk Firewall, AppsAlive, AppServer, ASPen, ASP-in-a-Box, BusinessEdge, Cache-Forward, CloudEdge, DataDirect Spy, DataDirect SupportLink, Fuse, FuseSource, Future Proof, GVAC, High Performance Integration, ObjectStore Inspector, ObjectStore Performance Expert, OpenAccess, Orbacus, Pantero, POSSE, ProDataSet, Progress Arcade, Progress CloudEdge, Progress Cloudware, Progress Control Tower, Progress ESP Event Manager, Progress ESP Event Modeler, Progress Event Engine, Progress RFID, Progress RPM, Progress Responsive Cloud, Progress Responsive Process Management, Progress Software, PSE Pro, SectorAlliance, SeeThinkAct, Shadow z/Services, Shadow z/Direct, Shadow z/Events, Shadow z/Presentation, Shadow Studio, SmartBrowser, SmartComponent, SmartDataBrowser, SmartDataObjects, SmartDataView, SmartDialog, SmartFolder, SmartFrame, SmartObjects, SmartPanel, SmartQuery, SmartViewer, SmartWindow, Sonic Business Integration Suite, Sonic Process Manager, Sonic Collaboration Server, Sonic Continuous Availability Architecture, Sonic Database Service, Sonic Workbench, Sonic XML Server, The Brains Behind BAM, WebClient, and Who Makes Progress are trademarks or service marks of Progress Software Corporation and/or its subsidiaries or affiliates in the U.S. and other countries. Java is a registered trademark of Oracle and/or its affiliates. Any other marks contained herein may be trademarks of their respective owners.

Third Party Acknowledgements: One or more products in the Progress Orbix v3.3.11 release includes third party components covered by licenses that require that the following documentation notices be provided:

Progress Orbix v3.3.11 incorporates OpenSSL/SSLey v0.9.8.i technology from OpenSSL.org. Such Technology is subject to the following terms and conditions: LICENSE ISSUES

The OpenSSL toolkit stays under a dual license, i.e. both the conditions of the OpenSSL License and the original SSLey license apply to the toolkit. See below for the actual license texts. Actually both licenses are BSD-style Open Source licenses. In case of any license issues related to OpenSSL please contact openssl-core@openssl.org.

OpenSSL License

Copyright (c) 1998-2008 The OpenSSL Project. All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgment:

"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>)"

4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact openssl-core@openssl.org.
5. Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project.
6. Redistributions of any form whatsoever must retain the following acknowledgment:

"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>)"

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com).
This product includes software written by Tim Hudson (tjh@cryptsoft.com).

Original SSLeay License

Copyright (C) 1995-1998 Eric Young (eay@cryptsoft.com) All rights reserved. This package is an SSL implementation written by Eric Young (eay@cryptsoft.com). The implementation was written so as to conform with Netscapes SSL. This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@cryptsoft.com).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed. If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used. This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:

"This product includes cryptographic software written by Eric Young (eay@cryptsoft.com)"
The word 'cryptographic' can be left out if the routines from the library being used are not cryptographic related :-).

4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement:

"This product includes software written by Tim Hudson (tjh@cryptsoft.com)"

THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The licence and distribution terms for any publically available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution licence [including the GNU Public Licence.]

Progress Orbix v3.3.11 incorporates mcpp v2.6.4 from SourceForge (<http://sourceforge.net/softwaremap/index.php>). Such technology is subject to the following terms and conditions: Copyright (c) 1998, 2002-2007 Kiyoshi Matsui kmatsui@t3.rim.or.jp All rights reserved. This software including the files in this directory is provided under the following license. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met: 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer. 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution. THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Progress Orbix v3.3.11 incorporates IDL Compiler Front End v1.0 from Sun Microsystems. Such technology is subject to the following terms and conditions: COPYRIGHT NOTICE on OMG IDL CFE: Copyright 1992 Sun Microsystems, Inc. Printed in the United States of America. All Rights Reserved. This product is protected by copyright and distributed under the following license restricting its use. The Interface Definition Language Compiler Front End (CFE) is made available for your use provided that you include this license and copyright notice on all media and documentation and the software program in which this product is incorporated in whole or part. You may copy and extend functionality (but may not remove functionality) of the Interface Definition Language CFE without charge, but you are not authorized to license or distribute it to anyone else except as part of a product or program developed by you or with the express written consent of Sun Microsystems, Inc. ("Sun"). The names of Sun Microsystems, Inc. and any of its subsidiaries or affiliates may not be used in advertising or publicity pertaining to distribution of Interface Definition Language CFE as permitted herein. This license is effective until terminated by Sun for failure to comply with this license. Upon termination, you shall destroy or return all code and documentation for the Interface Definition Language CFE. The Interface Definition Language CFE may not be exported outside the United States without first obtaining the appropriate government approvals. INTERFACE DEFINITION LANGUAGE CFE IS PROVIDED AS IS WITH NO WARRANTIES OF ANY KIND INCLUDING THE WARRANTIES OF DESIGN, MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, NONINFRINGEMENT, OR ARISING FROM A COURSE OF DEALING, USAGE OR TRADE PRACTICE. INTERFACE DEFINITION LANGUAGE CFE IS PROVIDED

WITH NO SUPPORT AND WITHOUT ANY OBLIGATION ON THE PART OF Sun OR ANY OF ITS SUBSIDIARIES OR AFFILIATES TO ASSIST IN ITS USE, CORRECTION, MODIFICATION OR ENHANCEMENT. SUN OR ANY OF ITS SUBSIDIARIES OR AFFILIATES SHALL HAVE NO LIABILITY WITH RESPECT TO THE INFRINGEMENT OF COPYRIGHTS, TRADE SECRETS OR ANY PATENTS BY INTERFACE DEFINITION LANGUAGE CFE OR ANY PART THEREOF. IN NO EVENT WILL SUN OR ANY OF ITS SUBSIDIARIES OR AFFILIATES BE LIABLE FOR ANY LOST REVENUE OR PROFITS OR OTHER SPECIAL, INDIRECT AND CONSEQUENTIAL DAMAGES, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013 and FAR 52.227-19. Sun, Sun Microsystems and the Sun logo are trademarks or registered trademarks of Sun Microsystems, Inc. SunSoft, Inc. 2550 Garcia Avenue Mountain View, California 94043

Updated: 07-Mar-2012

Contents

Preface	23
Audience	23
Organization of this Guide	23
Document Conventions	25

Part I

Package org.omg.CORBA

Class org.omg.CORBA.ARG_IN	29
Class org.omg.CORBA.ARG_INOUT	30
Class org.omg.CORBA.ARG_OUT	31
Class org.omg.CORBA.Bounds	32
Bounds()	32
Class org.omg.CORBA.CompletionStatus	33
value()	33
from_int()	34
Class org.omg.CORBA.Context	35
Class org.omg.CORBA.ContextList	37
Class org.omg.CORBA.CTX_RESTRICT_SCOPE	38
Class org.omg.CORBA.Current	39
Class org.omg.CORBA.DynamicImplementation	40
Class org.omg.CORBA.Environment	41
Class org.omg.CORBA.ExceptionList	42
Class org.omg.CORBA.NamedValue	43
Class org.omg.CORBA.NVList	44
Interface org.omg.CORBA.Object	45
Class org.omg.CORBA.ORB	46
init()	50
init()	50
init()	51
Class org.omg.CORBA.ORBPackage.InvalidName	52
InvalidName()	52

Class org.omg.CORBA.portable.InputStream	53
Class org.omg.CORBA.portable.OutputStream	55
Class org.omg.CORBA.portable.Streamable	57
Class org.omg.CORBA.Principal	58
Class org.omg.CORBA.Request	59
Class org.omg.CORBA.ServerRequest	61
op_name()	62
ctx()	62
params()	62
result()	65
except()	65
Class org.omg.CORBA.SystemException	66
Class org.omg.CORBA.TCKind	67
value()	69
from_int()	69
Class org.omg.CORBA.TypeCode	71
Class org.omg.CORBA.TypeCodePackage.BadKind	74
BadKind()	74
Class org.omg.CORBA.TypeCodePackage.Bounds	75
Bounds()	75
Class org.omg.CORBA.UnknownUserException	76
UnknownUserException()	76
Class org.omg.CORBA.UserException	77

Part II

Package

IE.Iona.OrbixWeb.CORBA

Class IE.Iona.OrbixWeb.CORBA.Any	81
Any()	84
Any()	86
Any()	86
Any()	87
clone()	88
containsType()	88
copy()	89
create_output_stream()	89
create_input_stream()	90

equal()	90
extract()	91
fromString()	92
insert()	93
read_value()	95
reset()	96
toString()	96
type()	97
write_value()	97
Interface IE.Iona.OrbixWeb.CORBA.BOA	98
anyClientsConnected()	103
change_implementation()	103
connect()	104
continueThreadDispatch()	106
create()	107
deactivate_impl()	108
deactivate_obj()	108
disconnect()	109
dispose()	110
enableLoaders()	110
enableProxyServer()	111
finalize()	111
get_current()	112
get_id()	112
get_principal()	113
get_principal_string()	113
impl_is_ready()	114
isEventPending()	117
myActivationMode()	117
myHost()	118
myHostIP()	119
myImplementationName()	119
myMarkerName()	120
myMarkerPattern()	120
myMethodName()	120
numClientsConnected()	121
obj_is_ready()	121
processEvents()	122
processNextEvent()	125
setNoHangup()	127
setProxyServer()	128
setServerName()	128

shutdown()	129
toString()	129
Class IE.Iona.OrbixWeb.CORBA.Context	130
Context()	132
Context()	132
Context()	133
Context()	133
_nil()	134
context_name()	134
create_child()	134
delete_values()	135
get_count()	135
get_count_all()	135
get_values()	136
IT_create()	137
parent()	137
set_one_value()	137
set_values()	138
Class IE.Iona.OrbixWeb.CORBA.ContextList	139
ContextList()	140
add()	140
count()	140
item()	141
remove()	141
Class IE.Iona.OrbixWeb.CORBA.ContextIterator	142
ContextIterator()	142
ContextIterator()	143
next()	143
setList()	143
Class IE.Iona.OrbixWeb.CORBA.Environment	145
exception()	145
exception()	146
clear()	146
Class IE.Iona.OrbixWeb.CORBA.ExceptionList	147
ExceptionList()	148
add()	148
count()	148
item()	149
remove()	149
Class IE.Iona.OrbixWeb.CORBA.InitService	150
InitService()	150
initialise()	151

Class IE.Iona.OrbixWeb.CORBA.NamedValue	152
NamedValue()	153
NamedValue()	153
NamedValue()	154
clone()	155
equals()	155
toString()	156
name()	156
value()	156
flags()	157
_nil()	157
Class IE.Iona.OrbixWeb.CORBA.NVList	158
NVList()	159
NVList()	160
NVList()	160
equals()	160
clone()	161
add()	161
add_item()	162
add_value()	162
count()	163
item()	163
_nil()	164
remove()	164
Class IE.Iona.OrbixWeb.CORBA.NVListIterator	165
NVListIterator()	165
NVListIterator()	166
next()	166
setList()	167
Interface IE.Iona.OrbixWeb.CORBA.ObjectRef	168
_create_request()	170
_create_request()	171
_deref()	172
_get_implementation();	173
_get_interface_def();	173
_hash()	174
_hasValidOpenChannel()	174
_host()	175
_id()	175
_implementation()	175
_interfaceHost()	176
_interfaceImplementation()	176

_interfaceMarker()	176
_is_a()	176
_is_equivalent()	177
_isRemote()	178
IT_PING()	178
_loader()	179
_marker()	179
_marker()	179
_name()	180
_non_existent()	180
_port()	180
_request()	180
_object_to_string()	181
_object_to_string()	182
_save()	182
Class IE.Iona.OrbixWeb.CORBA.ORB	184
baseInterfacesOf()	193
closeConnection()	194
collocated()	194
collocated()	195
config()	195
create_tc()	196
create_any()	198
create_context_list()	199
create_environment()	199
create_exception_list()	200
create_list()	200
create_named_value()	201
create_operation_list()	202
create_output_stream()	204
defaultTxTimeout()	205
finalize()	205
getConfigItem()	206
getConfiguration()	207
getDaemonConnections()	207
get_default_context()	208
getHostPort()	209
get_my_principal()	209
getMyReqTransformer()	210
get_next_response()	210
get_principal()	211
getTransformer()	211

get_principal_string()	212
hasValidOpenChannel()	213
init()	213
isBaseInterfaceOf()	217
list_initial_services()	217
locator()	218
makeIOR()	218
maxConnectRetries()	220
myHost()	221
_nil()	221
noReconnectOnFailure()	221
object_to_string()	222
pingDuringBind()	223
poll_next_response()	224
resizeConnectionTable()	224
registerIOCallback()	225
resolve_initial_references()	226
send_multiple_requests_deferred()	227
send_multiple_requests_oneway()	228
setConfigItem()	228
setConfiguration()	229
setDiagnostics()	229
setHostPort()	230
setMyReqTransformer()	231
set_parameters()	231
set_principal()	232
setReqTransformer()	232
string_to_object()	234
string_to_object()	234
toString()	235
unregisterIOCallback()	236
Class IE.Iona.OrbixWeb.CORBA.OrbCurrent	237
get_object()	240
get_principal()	240
get_principal_string()	241
get_protocol()	241
get_request()	242
get_server()	242
get_socket()	243
Class IE.Iona.OrbixWeb.CORBA.Principal	244
Principal()	245
Principal()	245

Principal()	245
access_name	246
name()	246
name()	246
toString()	247
Class IE.Iona.OrbixWeb.CORBA.Request	248
Request()	252
Request()	252
Request()	253
add_arg()	253
add_in_arg()	254
add_inout_arg()	254
add_named_in_arg()	254
add_named_inout_arg()	255
add_named_out_arg()	255
add_out_arg()	256
arguments()	256
contexts()	256
contexts()	257
create_input_stream()	257
create_output_stream()	257
ctx()	258
ctx()	258
env()	258
env()	259
exceptions()	259
exceptions()	259
getClientConnection()	260
_getException()	260
getMessageLength()	260
get_response()	261
invoke()	261
isDynamic()	262
isException()	262
_nil()	262
operation()	263
poll_response()	263
reset()	263
result()	264
return_value()	264
send_deferred()	265
send_oneway()	265

setOperation()	266
set_return_type()	266
setTarget()	267
target()	267
Class IE.Iona.OrbixWeb.CORBA.singletonORB	268
create_any()	271
create_context_list()	271
create_environment()	272
create_exception_list()	272
create_list()	273
create_named_value()	274
create_output_stream()	275
get_default_context()	275
create_tc()	276
Class IE.Iona.OrbixWeb.CORBA.TypeCode	279
TypeCode()	285
TypeCode()	286
kind()	286
equals()	287
equal()	287
compare()	288
id()	289
name()	289
member_count()	289
member_type()	290
member_name()	290
member_label()	291
discriminator_type()	291
default_index()	292
length()	292
content_type()	293
orbixTypeCode()	293
toString()	294

Part III

Package IE.Iona.OrbixWeb.Features

Class IE.Iona.OrbixWeb.Features.AuthenticationFilter	297
--	-----

AuthenticationFilter()	298
AuthenticationFilter()	298
Class IE.Iona.OrbixWeb.Features.Config	299
Config()	299
getConfigItem()	300
setConfigItem()	300
Class IE.Iona.OrbixWeb.Features.Filter	301
Filter()	302
Filter()	302
Filter()	303
_delete()	303
inReplyFailure()	304
inReplyPostMarshal()	304
inReplyPreMarshal()	305
inRequestPostMarshal()	306
inRequestPreMarshal()	307
outReplyFailure()	308
outReplyPostMarshal()	309
outReplyPreMarshal()	310
outRequestPostMarshal()	311
outRequestPreMarshal()	312
Interface IE.Iona.OrbixWeb.Features.ioCallback	313
CloseCallBack()	314
OpenCallBack()	315
Class IE.Iona.OrbixWeb.Features.IT_reqTransformer	316
transform()	317
transform_error()	318
Class IE.Iona.OrbixWeb.Features.LoaderClass	319
LoaderClass()	320
LoaderClass()	320
LoaderClass()	321
load()	321
record()	323
rename()	324
save()	325
Class IE.Iona.OrbixWeb.Features.locatorClass	327
locatorClass()	327
lookUp()	328
Class IE.Iona.OrbixWeb.Features.OrbConfig	330
OrbConfig()	331
defaultConfigFile()	331
getConfigFile()	331

getConfigItem()	332
getConfiguration()	332
setConfiguration()	332
setConfiguration()	333
setConfigItem()	333
zeroConfiguration()	333
Class IE.Iona.OrbixWeb.Features.ProxyFactory	334
ProxyFactory()	334
ProxyFactory()	335
New()	335
Class IE.Iona.OrbixWeb.Features.ThreadFilter	337
ThreadFilter()	338
ThreadFilter()	338
inRequestPreMarshal()	339

Part IV

Package IE.Iona.OrbixWeb

Class IE.Iona.OrbixWeb._CORBA	343
explicit_call	344
IT_INFINITE_TIMEOUT	345
IT_INTEROPERABLE_OR_KIND	345
IT_ORBIX_OR_KIND	345
_ORBIX_VERSION	345
_MAX_LOCATOR_HOPS	346
objectDeletion	346
Orbix	347
processTermination	348
Class IE.Iona.OrbixWeb._OrbixWeb	349
Any()	350
Context()	351
ContextList()	351
Current()	352
NamedValue()	353
NVList()	353
Object()	354
Principal()	354
Request()	355

ServerRequest()	355
TypeCode()	356

Part V

IDL Interface to the Interface Repository

Common CORBA Data Types	359
CORBA::DefinitionKind	359
CORBA::Identifier	359
CORBA::RepositoryId	360
CORBA::ScopedName	360
CORBA::AliasDef	361
AliasDef::describe()	361
AliasDef:original_type_def	362
CORBA::ArrayDef	363
ArrayDef::element_type	363
ArrayDef::element_type_def	364
ArrayDef::length	364
CORBA::AttributeDef	365
AttributeDef::describe()	365
AttributeDef::mode	366
AttributeDef::type	366
AttributeDef::type_def	366
CORBA::ConstantDef	367
ConstantDef::describe()	367
ConstantDef::type	368
ConstantDef::type_def	368
ConstantDef::value	369
CORBA::Contained	370
Contained::absolute_name()	371
Contained::containing_repository()	371
Contained::defined_in	371
Contained::describe()	372
Contained::id	373
Contained::move ()	373
Contained::name	374
Contained::version	374
CORBA::Container	375

Container::contents()	377
Container::create_alias()	378
Container::create_constant()	378
Container::create_enum()	379
Container::create_exception()	380
Container::create_interface()	380
Container::create_module()	381
Container::create_struct()	382
Container::create_union()	382
Container::describe_contents()	383
Container::lookup()	384
Container::lookup_name()	385
CORBA::EnumDef	386
EnumDef::describe()	386
EnumDef::members	387
CORBA::ExceptionDef	388
ExceptionDef::describe()	388
ExceptionDef::members	389
ExceptionDef::type	389
CORBA::IDLType	390
IDLType::type	391
CORBA::InterfaceDef	392
InterfaceDef::base_interfaces	393
InterfaceDef::create_attribute()	393
InterfaceDef::create_operation()	394
InterfaceDef::describe()	395
InterfaceDef::describe_interface ()	396
InterfaceDef::is_a ()	396
CORBA::IObject	397
IObject::def_kind	397
IObject::destroy()	397
CORBA::IT_InterfaceDef	398
IT_InterfaceDef::derived_interfaces()	398
CORBA::IT_Repository	399
IT_Repository::start()	399
IT_Repository::commit()	400
IT_Repository::rollBack()	400
IT_Repository::active_transactions()	400
CORBA::ModuleDef	401
ModuleDef::describe()	401
CORBA::OperationDef	402
OperationDef::contexts	403

OperationDef::exceptions	403
OperationDef::describe()	403
OperationDef::mode	404
OperationDef::params	404
OperationDef::result	405
OperationDef::result_def	405
CORBA::PrimitiveDef	406
PrimitiveDef::kind	406
CORBA::Repository	407
Repository::create_array()	408
Repository::create_sequence()	408
Repository::create_string()	409
Repository::get_primitive()	409
Repository::describe_contents()	409
Repository::lookup_id()	410
CORBA::SequenceDef	411
SequenceDef::bound	411
SequenceDef::element_type	411
SequenceDef::element_type_def	412
SequenceDef::type	412
CORBA::StructDef	413
StructDef::describe()	413
StructDef::members	414
CORBA::StringDef	415
StringDef::bound	415
CORBA::TypedefDef	416
TypedefDef::describe()	416
CORBA::UnionDef	418
UnionDef::describe()	419
UnionDef::discriminator_type	419
UnionDef::discriminator_type_def	420
UnionDef::members	420

Part VI

IDL Interface to the Orbix Java Daemon

IDL Interface to the Orbix Java Daemon	423
IT_daemon::addLaunchRightsDir()	427

IT_daemon::addInvokeRights()	427
IT_daemon::addInvokeRightsDir()	428
IT_daemon::addLaunchRights()	428
IT_daemon::addLaunchRightsDir()	428
IT_daemon::addMethod()	429
IT_daemon::addSharedMarker()	429
IT_daemon::addUnsharedMarker()	430
IT_daemon::changeOwnerServer()	430
IT_daemon::deleteDirectory()	431
IT_daemon::deleteServer()	431
IT_daemon::getServer()	431
IT_daemon::getServer2()	432
IT_daemon::getIIOPDetails	432
IT_daemon::getImplementationDetails	433
IT_daemon::killServer()	434
IT_daemon::LaunchStatus	434
IT_daemon::listActiveServers()	435
IT_daemon::listHostsInServer()	435
IT_daemon::listServers()	435
IT_daemon::lookUp()	436
IT_daemon::newDirectory()	436
IT_daemon::newPerMethodServer()	436
IT_daemon::newSharedServer()	437
IT_daemon::newSharedServer2()	438
IT_daemon::newUnSharedServer()	439
IT_daemon::registerPersistentServer()	439
IT_daemon::removeDirRights()	440
IT_daemon::removeInvokeRights()	441
IT_daemon::removeInvokeRightsDir()	441
IT_daemon::removeLaunchRights()	441
IT_daemon::removeLaunchRightsDir()	442
IT_daemon::removeMethod()	442
IT_daemon::removeSharedMarker()	442
IT_daemon::removeUnsharedMarker()	443
IT_daemon::serverDetails	443
IT_daemon::serverExists()	444

Part VII

Appendices

Appendix A	
IDL Reference	447
IDL Grammar	447
Appendix B	
Naming Service: IDL Definitions	453
Appendix C	
System Exceptions	455
System Exceptions Defined by CORBA	455
Index	459

Preface

The *Orbix Programmer's Reference Java Edition* expands on the information presented in the *Orbix Programmer's Guide Java Edition* and provides a reference for the application programming interface (API) to Orbix Java.

Orbix documentation is periodically updated. New versions between releases are available at this site:

<http://communities.progress.com/pcom/docs/DOC-105220>

If you need assistance with Orbix or any other PROGRESS products, contact PROGRESS at <http://www.progress.com/orbix/orbix-support.html>. Comments on PROGRESS documentation can be sent to <http://www.progress.com/en/about/contact.html>.

Audience

The *Orbix Programmer's Reference Java Edition* is designed as a reference for Orbix Java programmers. Before using this reference guide, read the *Orbix Java Edition Programmer's Guide* to learn about writing distributed applications using Orbix Java.

Organization of this Guide

This guide is divided into four parts as follows:

Parts I-IV API Reference

Parts I-IV provide a full reference listing for the following:

- The `org.omg.CORBA` classes and their methods.
- The `IE.IOna.OrbixWeb` classes and their methods.

Part V IDL Interface to the Interface Repository

The Interface Repository is the component of Orbix Java that provides runtime access to IDL definitions. The API to this component is defined in IDL. Part V provides an exhaustive reference for the IDL interface to the Interface Repository.

Part VI IDL Interface to the Orbix Java Daemon

The Orbix Java daemon, `orbixd`, manages several components of Orbix Java, including the Implementation Repository. Part VI provides a complete reference for the IDL interface to the Orbix Java daemon, which allows you to access the daemon functionality in your Orbix Java applications. The Orbix Java daemon acts as an Orbix Java server, with the server name `IT_daemon`.

The Orbix Java daemon `orbixdj` provides a subset of the functionality implemented for `orbixd`. Operations that are not supported by `orbixdj` are clearly indicated.

The IDL interfaces to both the Interface Repository and the Orbix Java daemon are compiled using the IDL to Java mapping defined in the *Orbix Java Edition Programmer's Guide*. The generated types for these interfaces are available in Orbix Java and are scoped by the package `IE.Iona.OrbixWeb.CORBA`.

Part VII Appendices

Appendix A, "IDL Reference", lists the full syntax of the IDL language.

Appendix B, "Naming Service: IDL definitions", lists the `CosNaming` module.

Appendix C, "System Exceptions", lists the Orbix Java system exceptions.

Note: In this guide, abstract methods are listed as throwing an `org.omg.CORBA.SystemException`. This is no longer necessary because `SystemExceptions` are now unchecked exceptions (extending `java.lang.RuntimeException`). These `SystemExceptions` are still listed however, to encourage programmers to enclose all statements in `try{}...catch{} blocks`.

Document Conventions

This guide uses the following typographical conventions:

`Constant width` Constant width (courier font) in normal text represents portions of code and literal names of items such as classes, functions, variables, and data structures. For example, text might refer to the `CORBA::Object` class.

Constant width paragraphs represent code examples or information a system displays on the screen. For example:

```
#include <stdio.h>
```

Italic Italic words in normal text represent *emphasis* and *new terms*.

Italic words or characters in code and commands represent variable values you must supply, such as arguments to commands or path names for your particular system. For example:

```
% cd /users/your_name
```

Note: some command examples may use angle brackets to represent variable values you must supply.

This guide may use the following keying conventions:

No prompt When a command's format is the same for multiple platforms, no prompt is used.

% A percent sign represents the UNIX command shell prompt for a command that does not require root privileges.

A number sign represents the UNIX command shell prompt for a command that requires root privileges.

> The notation > represents the DOS, Windows NT, or Windows 95 command prompt.

...
:
.
Horizontal or vertical ellipses in format and syntax descriptions indicate that material has been eliminated to simplify a discussion.

- [] Brackets enclose optional items in format and syntax descriptions.
- { } Braces enclose a list from which you must choose an item in format and syntax descriptions.
- | A vertical bar separates items in a list of choices enclosed in { } (braces) in format and syntax descriptions.

Part I

Package org.omg.CORBA

Class org.omg.CORBA.ARG_IN

- Synopsis** ARG_IN defines an integer constant for use with the DII when specifying an `in` parameter to a request.
- Refer to the *Orbix Programmer's Guide Java Edition* for details on using the DII.
- Java**

```
public interface ARG_IN
{
    public static final int value = 1;
}
```
- Notes** CORBA-defined.

Class `org.omg.CORBA.ARG_INOUT`

Synopsis `ARG_INOUT` defines an integer constant for use with the DII when specifying an `inout` parameter to a request.

Refer to the *Orbix Programmer's Guide Java Edition* for details on using the DII.

Java

```
public interface ARG_INOUT
{
    public static final int value = 3;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.ARG_OUT

Synopsis ARG_OUT defines an integer constant for use with the DII when specifying an out parameter to a request.

Refer to the *Orbix Programmer's Guide Java Edition* for details on using the DII.

Java

```
public interface ARG_OUT
{
    public static final int value = 2;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.Bounds

Synopsis Bounds is a CORBA-defined `UserException` that can be thrown to flag an out-of-bounds access on a data structure.

For examples of its use, refer to “Class org.omg.CORBA.ContextList” on page 37 and “Class org.omg.CORBA.ExceptionList” on page 42.

Java

```
final public class Bounds
extends org.omg.CORBA.UserException {
    public Bounds ();
}
```

Notes CORBA-defined.

Bounds()

Synopsis `public Bounds ();`

Description Default constructor.

Notes CORBA-defined.

Class org.omg.CORBA.CompletionStatus

Synopsis CompletionStatus contains an integer constant that enumerates the possible operation completion status at the time an Orbix Java system exception is raised.

Java

```
public final class CompletionStatus {

    // Completion Status constants
    public static final int _COMPLETED_YES = 0,
        _COMPLETED_NO = 1,
        _COMPLETED_MAYBE = 2;
    public static final CompletionStatus COMPLETED_YES =
        new CompletionStatus(_COMPLETED_YES);
    public static final CompletionStatus COMPLETED_NO =
        new CompletionStatus(_COMPLETED_NO);
    public static final CompletionStatus COMPLETED_MAYBE =
        new CompletionStatus(_COMPLETED_MAYBE);

    public int value()
        throws SystemException;
    public static final CompletionStatus from_int(int value)
        throws SystemException;
}
```

value()

Synopsis public int value();

Description Returns an integer constant representing the operation's completion status.

Notes CORBA-defined.

from_int()

Synopsis

```
public static final CompletionStatus from_int(int value);
```

Description

Creates and returns a `CompletionStatus` object with its constant value set to that of the integer parameter.

Parameters

value

An integer value of 0, 1 or 2 representing the operation completion status as defined above.

Notes

CORBA-defined.

Class org.omg.CORBA.Context

Synopsis For a description of Context and implementation details for abstract methods listed below refer to “Class IE.Iona.OrbixWeb.CORBA.Context” on page 130.

CORBA

```
pseudo interface Context{
    readonly attribute Identifier context_name;
    readonly attribute Context parent;
    Context create_child(in identifier child_ctx_name);
    void set_one_value(in Identifier propname,
                      in any propvalue);
    void set_values(in NVList values);
    void delete_values(in Identifier propname);
    NVList get_values(in Identifier start_scope,
                     in Flags op_flags,
                     in Identifier pattern);
};
```

Java

```
package org.omg.CORBA;

public abstract class Context {

    public abstract String context_name()
        throws SystemException;
    public abstract Context parent()
        throws SystemException;
    public abstract Context create_child(String child_ctx_name)
        throws SystemException;
    public abstract void set_one_value(String propname,
                                       Any propvalue)
        throws SystemException;
    public abstract void set_values(NVList values)
        throws SystemException;
    public abstract void delete_values(String propname)
        throws SystemException;
```

```
public abstract NVList get_values(String start_scpe,  
                                int op_flags,  
                                String pattern)  
    throws SystemException;  
};
```

Notes

CORBA-defined.

Class org.omg.CORBA.ContextList

Synopsis For a description of `ContextList` and implementation details for abstract methods listed here see “Class IE.Iona.OrbixWeb.CORBA.Context” on page 130.

See also “Class org.omg.CORBA.Context” on page 35.

CORBA

```
pseudo interface ContextList {
    readonly attribute unsigned long count;
    void add(in string ctx);
    string item(in unsigned long index) raises (CORBA::Bounds);
    void remove(in unsigned long index) raises (CORBA::Bounds);
};
```

Java

```
package org.omg.CORBA;

public abstract class ContextList {
    public abstract int count()
        throws SystemException;
    public abstract void add(String ctx)
        throws SystemException;
    public abstract String item(int index)
        throws org.omg.CORBA.Bounds, SystemException;
    public abstract void remove(int index)
        throws org.omg.CORBA.Bounds, SystemException;
}
```

Notes CORBA-defined.

Class `org.omg.CORBA.CTX_RESTRICT_SCOPE`

Synopsis Defines an integer constant used to specify that searching should be restricted to a specified scope when retrieving values from a `Context` object.

See also `get_values()` in “Class `org.omg.CORBA.Context`” on page 35.

Java

```
public interface CTX_RESTRICT_SCOPE
{
    public static final int value = 15;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.Current

Synopsis	For a description of Current, see “Class IE.Iona.OrbixWeb.CORBA.OrbCurrent” on page 237.
CORBA	pseudo interface Current { }
Java	public abstract class Current extends org.omg.CORBA.portable.ObjectImpl { }
Notes	CORBA-defined.

Class `org.omg.CORBA.DynamicImplementation`

Synopsis The `DynamicImplementation` class defines the interface that a dynamic server is expected to implement.

For further information see the `grid_dsi` demonstration.

Java

```
package org.omg.CORBA;

public abstract class DynamicImplementation
    extends org.omg.CORBA.portable.ObjectImpl {
    public abstract void invoke(org.omg.CORBA.ServerRequest
        request)
        throws SystemException;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.Environment

Synopsis For a description of `Environment` and the implementation of the methods listed below, see “Class `IE.Iona.OrbixWeb.CORBA.Environment`” on page 145.

Java

```
package org.omg.CORBA;

public abstract class Environment {
    void exception(java.lang.Exception except)
        throws SystemException;
    java.lang.Exception exception()
        throws SystemException;
    void clear()
        throws SystemException;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.ExceptionList

Synopsis For a description of `ExceptionList` and implementation of abstract methods listed below, see “Class `IE.Iona.OrbixWeb.CORBA.ExceptionList`” on page 147.

See also “Class `org.omg.CORBA.TypeCode`” on page 71.

CORBA

```
pseudo interface ExceptionList {
    readonly attribute unsigned long count;
    void add(in TypeCode exc);
    TypeCode item (in unsigned long index) raises (CORBA::Bounds);
    void remove (in unsigned long index) raises (CORBA::Bounds);
};
```

Java

```
package org.omg.CORBA;

public abstract class ExceptionList {
    public abstract int count()
        throws SystemException;
    public abstract void add(TypeCode exc)
        throws SystemException;
    public abstract TypeCode item(int index)
        throws org.omg.CORBA.Bounds, SystemException;
    public abstract void remove(int index)
        throws org.omg.CORBA.Bounds, SystemException;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.NamedValue

Synopsis For a description of `NamedValue` and implementation of abstract methods listed below, see “Class `IE.Iona.OrbixWeb.CORBA.NamedValue`” on page 152.

CORBA

```
pseudo interface NamedValue {
    readonly attribute Identifier name;
    readonly attribute Any value;
    readonly attribute Flags flags;
};
```

Java

```
package org.omg.CORBA;

public abstract class NamedValue
{
    public abstract String name()
        throws SystemException;
    public abstract Any value()
        throws SystemException;
    public abstract int flags()
        throws SystemException;
};
```

Notes CORBA-defined.

Class org.omg.CORBA.NVList

Synopsis For a description of `NVList` and implementation of abstract methods listed below, see “Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158.

See also “Class org.omg.CORBA.NamedValue” on page 43.

CORBA

```
pseudo interface NVList{
    readonly attribute unsigned long count;
    NamedValue add(in Flags flags);
    NamedValue add_item(in Identifier item_name, in Flags flags);
    NamedValue add_value(in Identifier item_name,
                        in any val,
                        in Flags flags);
    NamedValue item(in unsigned long index) raises (CORBA::Bounds);
    void remove(in unsigned long index) raises (CORBA::Bounds);
};
```

Java

```
package org.omg.CORBA;

public abstract class NVList
{
    public abstract int count()
        throws SystemException;
    public abstract NamedValue add(int flags)
        throws SystemException;
    public abstract NamedValue add_item(String item_name,
                                        int flags)
        throws SystemException;
    public abstract NamedValue add_value(String item_name,
                                        Any value,int item_flags)
        throws SystemException;
    public abstract NamedValue item(int index)
        throws Bounds, SystemException;
    public abstract void remove(int index)
        throws Bounds, SystemException;
};
```

Interface org.omg.CORBA.Object

Synopsis For the Orbix Java implementation of the Object interface, see “Interface IE.Iona.OrbixWeb.CORBA.ObjectRef” on page 168.

Java

```
package org.omg.CORBA;

public interface Object {
    boolean _is_a(String Identifier)
        throws SystemException;
    boolean _is_equivalent(Object that)
        throws SystemException;;
    boolean _non_existent()
        throws SystemException;;
    int _hash(int maximum)
        throws SystemException;;
    org.omg.CORBA.Object _duplicate()
        throws SystemException;;
    void _release()
        throws SystemException;;
    ImplementationDef _get_implementation()
        throws SystemException;;
    InterfaceDef _get_interface()
        throws SystemException;;
    Request _request(String s)
        throws SystemException;;
    Request _create_request(Context ctx,
        String operation, NVList arg_list,
        NamedValue result)
        throws SystemException;;
    Request _create_request(Context ctx,
        String operation, NVList arg_list,
        NamedValue result, ExceptionList exclist,
        ContextList ctxlist)
        throws SystemException;;
}
```

Notes CORBA-defined.

Class org.omg.CORBA.ORB

Synopsis For a description of ORB and implementation of abstract methods listed below, see “Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184.

CORBA

```
pseudo interface ORB {
    exception InvalidName {};
    typedef string ObjectId;
    typedef sequence<ObjectId> ObjectIdList;
    ObjectIdList list_initial_services();
    Object resolve_initial_references(in ObjectId object_name)
    raises(InvalidName);
    string object_to_string(in Object obj);
    Object string_to_object(in string str);
    NVList create_list(in long count);
    NVList create_operation_list(in OperationDef oper);
    NamedValue create_named_value(in String name, in Any value,
    in Flags flags);
    ExceptionList create_exception_list();
    ContextList create_context_list();
    Context get_default_context();
    Environment create_environment();
    void send_multiple_requests_oneway(in RequestSeq req);
    void send_multiple_requests_deferred(in RequestSeq req);
    boolean poll_next_response();
    Request get_next_response();

    // typecode creation
    TypeCode create_struct_tc ( in RepositoryId id,
        in Identifier name,
        in StructMemberSeq members);
    TypeCode create_union_tc ( in RepositoryId id,
        in Identifier name,
        in TypeCode discriminator_type,
        in UnionMemberSeq members);
    TypeCode create_enum_tc ( in RepositoryId id,
        in Identifier name,
        in EnumMemberSeq members);
    TypeCode create_alias_tc ( in RepositoryId id,
        in Identifier name,
```

```
        in TypeCode original_type);
TypeCode create_exception_tc ( in RepositoryId id,
    in Identifier name,
    in StructMemberSeq members);
TypeCode create_interface_tc ( in RepositoryId id,
    in Identifier name);
TypeCode create_string_tc ( in unsigned long bound);
TypeCode create_wstring_tc ( in unsigned long bound);
TypeCode create_sequence_tc ( in unsigned long bound,
    in TypeCode element_type);
TypeCode create_recursive_sequence_tc( in unsigned long bound,
    in unsigned long offset);
TypeCode create_array_tc ( in unsigned long length,
    in TypeCode element_type);
Current get_current();

// Additional operations for Java mapping
TypeCode get_primitive_tc(in TCKind tcKind);
Any create_any();
OutputStream create_output_stream();
void connect(Object obj);
void disconnect(Object obj);
}
```

Java

```
package org.omg.CORBA;

public abstract class ORB {
public abstract String[] list_initial_services()
    throws SystemException;
public abstract org.omg.CORBA.Object resolve_initial_references(
    String object_name)
    throws org.omg.CORBA.ORBPackage.InvalidName, SystemException;
public abstract String object_to_string(org.omg.CORBA.Object obj)
    throws SystemException;
public abstract org.omg.CORBA.Object string_to_object(String str)
    throws SystemException;
public abstract NVList create_list(int count)
    throws SystemException;
public abstract NVList create_operation_list(OperationDef oper)
    throws SystemException;
public abstract NamedValue create_named_value(String name,
    Any value, int flags)
    throws SystemException;
}
```

```
public abstract ExceptionList create_exception_list()
    throws SystemException;
public abstract ContextList create_context_list()
    throws SystemException;
public abstract Context get_default_context()
    throws SystemException;
public abstract Environment create_environment()
    throws SystemException;
public abstract void send_multiple_requests_oneway(Request[] req)
    throws SystemException;
public abstract void sent_multiple_requests_deferred(Request[]
req)
    throws SystemException;
public abstract boolean poll_next_response()
    throws SystemException;
public abstract Request get_next_response()
    throws SystemException;

// typecode creation
public abstract TypeCode create_struct_tc(String id,
    String name, StructMember[] members)
    throws SystemException;
public abstract TypeCode create_union_tc(String id,
    String name, TypeCode discriminator_type,
    UnionMember[] members)
    throws SystemException;
public abstract TypeCode create_enum_tc(String id,
    String name, EnumMember[] members)
    throws SystemException;
public abstract TypeCode create_alias_tc(String id,
    String name, TypeCode original_type)
    throws SystemException;
public abstract TypeCode create_exception_tc(String id,
    String name, StructMember[] members)
    throws SystemException;
public abstract TypeCode create_interface_tc(String id,
    String name)
    throws SystemException;
public abstract TypeCode create_string_tc(int bound)
    throws SystemException;
public abstract TypeCode create_wstring_tc(int bound)
    throws SystemException;
public abstract TypeCode create_sequence_tc(int bound,
```



```
TypeCode element_type)
    throws SystemException;
public abstract TypeCode create_recursive_sequence_tc(int bound,
    int offset)
    throws SystemException;
public abstract TypeCode create_array_tc(int length,
    TypeCode element_type)
    throws SystemException;
public abstract Current get_current()
    throws SystemException;

// additional methods for IDL/Java mapping
public abstract TypeCode get_primitive_tc(TCKind tcKind)
    throws SystemException;
public abstract Any create_any()
    throws SystemException;
public abstract org.omg.CORBA.portable.OutputStream
    create_output_stream()
    throws SystemException;
public abstract void connect( org.omg.CORBA.Object obj)
    throws SystemException;
public abstract void disconnect( org.omg.CORBA.Object obj)
    throws SystemException;

// additional static methods for ORB initialization
public static ORB init(Strings[] args, Properties props)
    throws SystemException;
public static ORB init(Applet app, Properties props)
    throws SystemException;
public static ORB init()
    throws SystemException;
}
```

Notes

CORBA-defined.

init()

- Synopsis** `public static ORB init ()`
- Description** The parameterless `ORB.init()` method returns a singleton ORB. A singleton ORB has restricted functionality. It is used to create `TypeCode` objects and Pseudo IDL objects. The parameterless `ORB.init()` method should only be called by all clients and servers that need to use an underlying singleton ORB. If called multiple times, this method always returns the same Java object.
- Return Value** A parameterless `ORB.init()` method returns a singleton ORB. This gives access to only a subset of the methods defined in class `org.omg.CORBA.ORB`. Refer to “Class `IE.Iona.OrbixWeb.CORBA.singletonORB`” on page 268 for more details.
- Notes** CORBA-defined.
- See Also** Other `init()` methods.
“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184
“Class `IE.Iona.OrbixWeb.CORBA.singletonORB`” on page 268

init()

- Synopsis** `public static ORB init(Strings[] args,
 java.util.Properties props);`
- Description** All client and server applications in a CORBA system must call this version of `ORB.init()` before they can make use of the underlying fully-functional ORB. Calling `ORB.init()` with parameters allows command-line arguments and properties to be passed to the ORB runtime. You can use properties supplied in the `props` parameter to customize the behaviour of the ORB. At initialization, the ORB reads whatever system properties it requires and then applies the `props` properties to its internal configuration settings. Both the argument array and properties can be null.
- Parameters**
- | | |
|--------------------|--|
| <code>args</code> | An array of <code>Strings</code> containing command-line arguments. |
| <code>props</code> | A <code>java.util.Properties</code> object containing property settings required for customizing of ORB behaviour. |

Return Value This version of `ORB.init()` returns a fully-functional `org.omg.CORBA.ORB` object, giving access to the various methods defined in this class.

Notes CORBA-defined.

See Also Other `init()` methods
“Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184

init()

Synopsis

```
public static ORB init(Applet app, java.util.Properties props);
```

Description All client and server applets in a CORBA system must call this version of `ORB.init()` before they can make use of the underlying fully-functional ORB. Here, an applet client can pass a reference to itself, allowing configuration from applet parameters. Properties supplied in the `props` parameter can be used to customize the ORB behaviour. At initialization, the ORB reads whatever system properties it requires and applies the `props` properties to its internal configuration settings. Both the applet and the properties can be null. If you wish to pass a null applet, you must cast it as follows:

```
(Applet)null
```

Parameters

<code>app</code>	The applet from which the call is made.
<code>props</code>	A <code>java.util.Properties</code> object, containing property settings.

Return Value This version of `ORB.init()` returns a fully-functional `org.omg.CORBA.ORB` object, giving access to the various methods defined in this class.

Notes CORBA-defined.

See Also Other `init()` methods.
“Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184

Class org.omg.CORBA.ORBPackage.InvalidName

Synopsis InvalidName is a CORBA-defined `UserException`. This can be thrown by the `resolve_initial_references` method of the ORB class to flag an invalid `object_name` parameter.

Java

```
package org.omg.CORBA.ORBPackage;  
  
public final class InvalidName extends org.omg.CORBA.UserException  
{  
    public InvalidName();  
}
```

Notes CORBA-defined.

InvalidName()

Synopsis `public InvalidName();`

Description Default constructor.

Notes CORBA-defined.

Class org.omg.CORBA.portable.InputStream

Java

```
package org.omg.CORBA.portable;
public abstract class InputStream extends java.io.InputStream
{
    public InputStream() {}
    public abstract boolean read_boolean();
    public abstract char read_char();
    public abstract char read_wchar();
    public abstract byte read_octet();
    public abstract short read_short();
    public abstract short read_ushort();
    public abstract int read_long();
    public abstract int read_ulong();
    public abstract long read_longlong();
    public abstract long read_ulonglong();
    public abstract float read_float();
    public abstract double read_double();
    public abstract String read_string();
    public abstract String read_wstring();
    public abstract void read_boolean_array(boolean[] value, int
        offset, int length);
    public abstract void read_char_array(char[] value, int offset,
        int length);
    public abstract void read_wchar_array(char[] value, int offset,
        int length);
    public abstract void read_octet_array(byte[] value, int offset,
        int length);
    public abstract void read_short_array(short[] value, int offset,
        int length);
    public abstract void read_ushort_array(short[] value, int
        offset, int length);
    public abstract void read_long_array(int[] value, int offset,
        int length);
    public abstract void read_ulong_array(int[] value, int offset,
        int length);
    public abstract void read_longlong_array(long[] value, int
        offset, int length);
    public abstract void read_ulonglong_array(long[] value, int
        offset, int length);
}
```

```
public abstract void read_float_array(float[] value, int offset,
    int length);
public abstract void read_double_array(double[] value, int
    offset, int length);
public abstract org.omg.CORBA.Object read_Object();
public abstract org.omg.CORBA.TypeCode read_TypeCode();
public abstract org.omg.CORBA.Any read_any();
public abstract org.omg.CORBA.Principal read_Principal();
}
```

Notes CORBA-defined.

Class org.omg.CORBA.portable.OutputStream

Synopsis See also “Class org.omg.CORBA.portable.InputStream” on page 53.

Java

```
package org.omg.CORBA.portable;
public abstract class OutputStream extends java.io.OutputStream
{
    public OutputStream() {}
    public abstract InputStream create_input_stream();
    public abstract void write_boolean (boolean value);
    public abstract void write_char (char value);
    public abstract void write_wchar (char value);
    public abstract void write_octet (byte value);
    public abstract void write_short (short value);
    public abstract void write_ushort (short value);
    public abstract void write_long (int value);
    public abstract void write_ulong (int value);
    public abstract void write_longlong (long value);
    public abstract void write_ulonglong (long value);
    public abstract void write_float (float value);
    public abstract void write_double (double value);
    public abstract void write_string (String value);
    public abstract void write_wstring (String value);
    public abstract void write_boolean_array(boolean[] value,
        int offset, int length);
    public abstract void write_char_array(char[] value, int offset,
        int length);
    public abstract void write_wchar_array(char[] value, int offset,
        int length);
    public abstract void write_octet_array(byte[] value, int offset,
        int length);
    public abstract void write_short_array(short[] value, int
        offset, int length);
    public abstract void write_ushort_array(short[] value, int
        offset, int length);
    public abstract void write_long_array(int[] value, int offset,
        int length);
    public abstract void write_ulong_array(int[] value, int offset,
        int length);
    public abstract void write_longlong_array(long[] value, int
```

```
    offset, int length);
public abstract void write_ulonglong_array(long[] value, int
    offset, int length);
public abstract void write_float_array(float[] value, int
    offset, int length);
public abstract void write_double_array(double[] value, int
    offset, int length);
public abstract void write_Object(org.omg.CORBA.Object value);
public abstract void write_TypeCode(org.omg.CORBA.TypeCode
    value);
public abstract void write_any (org.omg.CORBA.Any value);
public abstract void write_Principal(org.omg.CORBA.Principal
    value);
}
```

Notes

CORBA-defined.

Class `org.omg.CORBA.portable.Streamable`

Synopsis The `Streamable` interface specifies methods allowing you to read and write complex data types. The `Holder` classes for handling complex `out` and `inout` parameters provide an example of its use.

See also “Class `org.omg.CORBA.portable.InputStream`” on page 53, “Class `org.omg.CORBA.portable.OutputStream`” on page 55, and the discussion of holders in the chapter “IDL to Java Mapping” in the *Orbix Programmer’s Guide Java Edition* .

Java

```
package org.omg.CORBA.portable;

public interface Streamable {
    void _read(org.omg.CORBA.portable.InputStream istream)
        throws SystemException;
    void _write(org.omg.CORBA.portable.OutputStream ostream)
        throws SystemException;
    org.omg.CORBA.TypeCode _type()
        throws SystemException;
}
```

Notes `CORBA`-defined.

Class org.omg.CORBA.Principal

Synopsis	For a description of <code>Principal</code> and implementation of abstract methods defined below, see “Class <code>IE.Iona.OrbixWeb.CORBA.Principal</code> ” on page 244.
CORBA	<pre>pseudo interface Principal { attribute sequence<octet> name; }</pre>
Java	<pre>public abstract class Principal { public abstract byte[] name() throws SystemException; public abstract void name(byte[] name) throws SystemException;</pre>
Notes	CORBA-defined.

Class org.omg.CORBA.Request

Synopsis For a description of `Request` and implementation of abstract methods listed below, see “Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248.

See also “Dynamic Invocation Interface” and the demonstration in the `demos/dii_demo` directory of your Orbix Java installation.

CORBA

```
pseudo interface Request {
    readonly attribute Object target;
    readonly attribute Identifier operation;
    readonly attribute NVList arguments;
    readonly attribute NamedValue result;
    readonly attribute Environment env;
    readonly attribute ExceptionList exceptions;
    readonly attribute ContextList contexts;
    attribute Context ctx;
    any add_in_arg();
    any add_named_in_arg(in string name);
    any add_inout_arg();
    any add_named_inout_arg(in string name);
    any add_out_arg();
    any add_named_out_arg(in string name);
    void set_return_type(in TypeCode tc);
    any return_value();
    void invoke();
    void send_oneway();
    void send_deferred();
    void get_response();
    boolean poll_response();
};
```

Java

```
package org.omg.CORBA;

public abstract class Request {
    public abstract Object target()
        throws SystemException;
    public abstract String operation()
        throws SystemException;
```

```
public abstract NVList arguments()
    throws SystemException;
public abstract NamedValue result()
    throws SystemException;
public abstract Environment env()
    throws SystemException;
public abstract ExceptionList exceptions()
    throws SystemException;
public abstract ContextList contexts()
    throws SystemException;
public abstract Context ctx()
    throws SystemException;
public abstract void ctx(Context c)
    throws SystemException;
public abstract Any add_in_arg()
    throws SystemException;
public abstract Any add_named_in_arg(String name)
    throws SystemException;
public abstract Any add_inout_arg()
    throws SystemException;
public abstract Any add_named_inout_arg(String name)
    throws SystemException;
public abstract Any add_out_arg()
    throws SystemException;
public abstract Any add_named_out_arg(String name)
    throws SystemException;
public abstract void set_return_type(TypeCode tc)
    throws SystemException;
public abstract Any return_value()
    throws SystemException;
public abstract void invoke()
    throws SystemException;
public abstract void send_oneway()
    throws SystemException;
public abstract void send_deferred()
    throws SystemException;
public abstract void get_response()
    throws SystemException;
public abstract boolean poll_response()
    throws SystemException;
}
```

Notes

CORBA-defined.

Class `org.omg.CORBA.ServerRequest`

Synopsis An object adapter (for example, the BOA) dispatches an invocation to a DSI-based object implementation by calling the `invoke()` method on a `org.omg.CORBA.DynamicImplementation` object. The parameter passed to this method is a `ServerRequest` object. This `ServerRequest` object contains the state of an incoming invocation for the DSI. This can be compared to how the `org.omg.CORBA.Request` object is used in the DII approach for clients.

Refer to the demonstration in the `demos/grid_dsi` directory of your Orbix Java installation for an example of how to use the DSI.

CORBA

```
// PIDL
module CORBA {
    interface ServerRequest {
        Identifier op_name;
        Context ctx();
        void params(in NVList parms);
        void result(in Any res);
        void except(in Any ex);
    };
};
```

Orbix Java

```
// Java
package org.omg.CORBA;

public abstract class ServerRequest {
    public ServerRequest() {}
    public abstract String op_name();
    public abstract Context ctx();
    public abstract void params(NVList parms);
    public abstract void result(Any a);
    public abstract void except(Any a);
};
```

op_name()

- Synopsis** `public abstract String op_name();`
- Description** Returns the name of the operation being invoked.
- Notes** CORBA-defined.

ctx()

- Synopsis** `public abstract Context ctx();`
- Description** This method returns the `Context` object for this operation invocation. If no `Context` is sent, this method returns `null`.
- Notes** CORBA-defined.
- See Also** “Class `IE.Iona.OrbixWeb.CORBA.Context`” on page 130

params()

- Synopsis** `public abstract void params(NVList parms);`
- Description** This method marshals the parameters from the incoming `ServerRequest` into the supplied `parms NVList`. You should ensure that the `TypeCode` and flags (`ARG_IN`, `ARG_OUT` or `ARG_INOUT`) of each of the parameters are correct.
- The Dynamic Implementation Routine (DIR) must call `params` with `parms` containing `TypeCodes` and flags describing the parameter types expected for the method.
- After invoking `params()` you should use the unmarshalled `in` and `inout` values as parameters to the method invocation.
- When the invocation completes, you should insert the values for any `out` and `inout` parameters into the `parms NVList` before returning.
- If the operation has a return value you must also call “`result()`”.
- For example:
- ```
// import org.omg.CORBA.*;
// Simulate the operations on the grid interface using the DSI.
```

## Class org.omg.CORBA.ServerRequest

---

```
public void invoke(org.omg.CORBA.ServerRequest _req) {
 String _opName = _req.op_name() ;
 org.omg.CORBA.Any _ret = org.omg.CORBA.ORB.init().create_any();
 org.omg.CORBA.NVList _nvl = null;

 if(_opName.equals("set")) {
 _nvl = org.omg.CORBA.ORB.init().create_list(3);

 // Create a new any.
 org.omg.CORBA.Any n = org.omg.CORBA.ORB.init().create_any();

 // Insert the TypeCode(tk_short) into the new Any.
 n.type(org.omg.CORBA.ORB.init().get_primitive_tc
 (org.omg.CORBA.TCKind.tk_short)) ;

 // Insert this Any into the NVList and set the flag to IN.
 _nvl.add_value(null, n, org.omg.CORBA.ARG_IN.value);

 // Create new Any, set Typecode to short, insert into NVList.
 org.omg.CORBA.Any m = org.omg.CORBA.ORB.init().create_any();
 m.type(org.omg.CORBA.ORB.init().get_primitive_tc
 (org.omg.CORBA.TCKind.tk_short));
 _nvl.add_value(null, m, org.omg.CORBA.ARG_IN.value);

 // Create new Any, set Typecode to long, insert into NVList.
 org.omg.CORBA.Any value
 = org.omg.CORBA.ORB.init().create_any();
 value.type(org.omg.CORBA.ORB.init().get_primitive_tc
 (org.omg.CORBA.TCKind.tk_long));
 _nvl.add_value(null, value, org.omg.CORBA.ARG_IN.value);

 // Use params() method to marshal data into _nvl.
 _req.params(_nvl);

 // Get the value of row, col from Any row, col
 // and set this element in the array to the value.
 m_a[n.extract_short()][m.extract_short()] =
 value.extract_long() ;

 return;
 }

 if(_opName.equals("get")) {
 _ret = org.omg.CORBA.ORB.init().create_any();
 }
}
```

```
 _nvl = org.omg.CORBA.ORB.init().create_list(2);

 org.omg.CORBA.Any n = org.omg.CORBA.ORB.init().create_any();
 ntype(org.omg.CORBA.ORB.init().get_primitive_tc
 (org.omg.CORBA.TCKind.tk_short));
 _nvl.add_value(null, n, org.omg.CORBA.ARG_IN.value);

 org.omg.CORBA.Any m = org.omg.CORBA.ORB.init().create_any();
 m.type(org.omg.CORBA.ORB.init().get_primitive_tc
 (org.omg.CORBA.TCKind.tk_short));
 _nvl.add_value(null, m, org.omg.CORBA.ARG_IN.value);
 _req.params(_nvl);
 int t = m_a[n.extract_short()][m.extract_short()];
 _ret.insert_long(t);
 _req.result(_ret);
 return;
}

if (_opName.equals("_get_height")) {
 _ret = org.omg.CORBA.ORB.init().create_any();
 _req.params(_nvl);
 _ret.insert_short(m_height);
 _req.result(_ret);
 return;
}

if (_opName.equals("_get_width")) {
 _ret = org.omg.CORBA.ORB.init().create_any();
 _req.params(_nvl);
 _ret.insert_short(m_width);
 _req.result(_ret);
 return;
}
}
```

### Parameters

|       |                                                                                                                                                    |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| parms | A <code>NVList</code> describing the parameter types for the operation in the order in which they appear in the IDL specification (left to right). |
|-------|----------------------------------------------------------------------------------------------------------------------------------------------------|

**Notes** CORBA-defined.



**See Also** “Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158  
grid\_dsi demonstration

### result()

**Synopsis** void result(in Any res);

**Description** The result() method specifies the return value for the call. If the operation has a void result type, result() should be set to an Any whose type is \_tc\_void.

### Parameters

res                                   An Any containing the return value and type for the operation.

**Notes** CORBA-defined.

**See Also** “Class IE.Iona.OrbixWeb.CORBA.Any” on page 81

### except()

**Synopsis** void except(in Any ex);

**Description** The DIR can call except() at any time to return an exception to the client. The Any passed to except() must contain either a system exception or one of the user exceptions specified in the raises expression of the invoked operation’s IDL definition.

### Parameters

ex                                    An Any containing the exception to be returned to the client.

**Notes** CORBA-defined.

**See Also** “System Exceptions” on page 455  
“Class IE.Iona.OrbixWeb.CORBA.Any” on page 81  
“Class org.omg.CORBA.SystemException” on page 66

## Class org.omg.CORBA.SystemException

**Synopsis**        The Orbix Java system exceptions are organized into a class hierarchy: each system exception is a derived class of `SystemException` (which is in turn a derived class of `java.lang.RuntimeException`). This allows all system exceptions to be caught in one single Java `catch` clause.

`SystemException` provides access to the `minor` exception code and to the `CompletionStatus` of the associated operation. `SystemException` itself is an abstract class; only derived exception classes may be instantiated.

See also “Class `org.omg.CORBA.CompletionStatus`” on page 33 and refer to the chapter “Exception Handling” in the *Orbix Programmer’s Guide Java Edition* .

**Java**            `package org.omg.CORBA;`

```
abstract public class SystemException
 extends java.lang.RuntimeException {
 public int minor;
 public CompletionStatus completed;
}
```

**Notes**         `CORBA`-defined.

# Class org.omg.CORBA.TCKind

**Synopsis**      Class TCKind defines TypeCode kind constant values required by class TypeCode.

Refer to the chapter “IDL to Java Mapping” in the *Orbix Java Edition Programmer’s Guide* for a discussion of the mapping from the IDL type enum to Java.

**Orbix Java**    // Java

```
public final class TCKind {
 public static final int _tk_null = 0;
 public static final int _tk_void = 1;
 public static final int _tk_short = 2;
 public static final int _tk_long = 3;
 public static final int _tk_ushort = 4;
 public static final int _tk_ulong = 5;
 public static final int _tk_float = 6;
 public static final int _tk_double = 7;
 public static final int _tk_boolean = 8;
 public static final int _tk_char = 9;
 public static final int _tk_octet = 10;
 public static final int _tk_any = 11;
 public static final int _tk_TypeCode = 12;
 public static final int _tk_Principal = 13;
 public static final int _tk_objref = 14;
 public static final int _tk_struct = 15;
 public static final int _tk_union = 16;
 public static final int _tk_enum = 17;
 public static final int _tk_string = 18;
 public static final int _tk_sequence = 19;
 public static final int _tk_array = 20;
 public static final int _tk_alias = 21;
 public static final int _tk_except = 22;
 public static final int _tk_longlong = 23;
 public static final int _tk_ulonglong = 24;
 public static final int _tk_longdouble = 25;
 public static final int _tk_wchar = 26;
 public static final int _tk_wstring = 27;
 public static final int _tk_fixed = 28;
```

```
public static final TCKind tk_null = new TCKind(0);
public static final TCKind tk_void = new TCKind(1);
public static final TCKind tk_short = new TCKind(2);
public static final TCKind tk_long = new TCKind(3);
public static final TCKind tk_ushort = new TCKind(4);
public static final TCKind tk_ulong = new TCKind(5);
public static final TCKind tk_float = new TCKind(6);
public static final TCKind tk_double = new TCKind(7);
public static final TCKind tk_boolean = new TCKind(8);
public static final TCKind tk_char = new TCKind(9);
public static final TCKind tk_octet = new TCKind(10);
public static final TCKind tk_any = new TCKind(11);
public static final TCKind tk_TypeCode = new TCKind(12);
public static final TCKind tk_Principal = new TCKind(13);
public static final TCKind tk_objref = new TCKind(14);
public static final TCKind tk_struct = new TCKind(15);
public static final TCKind tk_union = new TCKind(16);
public static final TCKind tk_enum = new TCKind(17);
public static final TCKind tk_string = new TCKind(18);
public static final TCKind tk_sequence = new TCKind(19);
public static final TCKind tk_array = new TCKind(20);
public static final TCKind tk_alias = new TCKind(21);
public static final TCKind tk_except = new TCKind(22);
public static final TCKind tk_longlong = new TCKind(23);
public static final TCKind tk_ulonglong = new TCKind(24);
public static final TCKind tk_longdouble = new TCKind(25);
public static final TCKind tk_wchar = new TCKind(26);
public static final TCKind tk_wstring = new TCKind(27);
public static final TCKind tk_fixed = new TCKind(28);

public int value() throws org.omg.CORBA.SystemException;
public static TCKind from_int(int i)
 throws org.omg.CORBA.SystemException;
}
```

### Notes

CORBA-defined.

**See Also**      “Class `org.omg.CORBA.TypeCode`” on page 71  
                 “Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279

### **value()**

**Synopsis**      `public int value() throws org.omg.CORBA.SystemException;`

**Description**      Returns the integer value associated with a `TCKind` object.

**Notes**          PROGRESS-specific.

### **from\_int()**

**Synopsis**      `public static TCKind from_int(int i)  
                 throws org.omg.CORBA.SystemException;`

**Description**      Returns a reference to a `TCKind` object given an integer value.

#### **Parameters**

`i`                      An integer value identifying a `TCKind` object.

#### **Return Value**

`TCKind`                The `TCKind` object associated with the value specified by `i`.

**Notes**          PROGRESS-specific.



# Class org.omg.CORBA.TypeCode

**Synopsis** For a description of `TypeCode` and implementation of abstract methods listed for this class, see “Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279.

**CORBA**

```
enum TCKind { tk_null, tk_void, tk_short, tk_long, tk_ushort,
tk_ulong, tk_float, tk_double, tk_boolean, tk_char, tk_octet,
tk_any, tk_TypeCode, tk_Principal, tk_objref, tk_struct, tk_union,
tk_enum, tk_string, tk_sequence, tk_array, tk_alias, tk_except,
tk_longlong, tk_ulonglong, tk_longdouble, tk_wchar, tk_wstring,
tk_fixed };
```

```
pseudo interface TypeCode {
 exception Bounds {};
 exception BadKind {};

 // for all TypeCode kinds
 boolean equal(in TypeCode tc);
 TCKind kind();

 // for objref, struct, union, enum, alias, and except
 RepositoryID id() raises (BadKind);
 RepositoryId name() raises (BadKind);

 // for struct, union, enum, and except
 unsigned long member_count() raises (BadKind);
 Identifier member_name(in unsigned long index)
 raises (BadKind, Bounds);

 // for struct, union, and except
 TypeCode member_type(in unsigned long index)
 raises (BadKind, Bounds);

 // for union
 any member_label(in unsigned long index)
 raises (BadKind, Bounds);
 TypeCode discriminator_type() raises (BadKind);
 long default_index() raises (BadKind);
```

## Orbix Programmer's Reference Java Edition

---

```
 // for string, sequence, and array
 unsigned long length() raises (BadKind);
 TypeCode content_type() raises (BadKind);
}
```

### Orbix Java

```
// Java

public abstract class TypeCode {
 public abstract boolean equal(TypeCode tc)
 throws org.omg.CORBA.SystemException;
 public abstract TCKind kind()
 throws org.omg.CORBA.SystemException;

 // for struct, union, enum, and except
 public abstract int member_count()
 throws org.omg.CORBA.SystemException, BadKind;
 public abstract String id()
 throws org.omg.CORBA.SystemException, BadKind;
 public abstract String name()
 throws org.omg.CORBA.SystemException, BadKind;
 public abstract String member_name(int index)
 throws org.omg.CORBA.SystemException, BadKind, Bounds;

 // for struct, union, and except
 public abstract TypeCode member_type(int index)
 throws org.omg.CORBA.SystemException, BadKind, Bounds;

 // for union
 public abstract Any member_label(int index)
 throws org.omg.CORBA.SystemException, BadKind, Bounds;
 public abstract TypeCode discriminator_type()
 throws org.omg.CORBA.SystemException, BadKind;
 public abstract int default_index()
 throws org.omg.CORBA.SystemException, BadKind;

 // for string, sequence, and array
 public abstract int length()
 throws org.omg.CORBA.SystemException, BadKind;
 public abstract TypeCode content_type()
 throws org.omg.CORBA.SystemException, BadKind;
}
```



## Class `org.omg.CORBA.TypeCode`

---

```
 public java.lang.Object clone()
 throws org.omg.CORBA.SystemException;
};
```

**Notes** CORBA-defined.

**See Also** “Class `org.omg.CORBA.TypeCode`” on page 71.

## Class

# org.omg.CORBA.TypeCodePackage.BadKind

**Synopsis**      `BadKind` is a CORBA defined `UserException` that can be thrown by a number of the methods in `TypeCode`. It flags the use of a method that is not available on the `TypeCode` in question.

For more information, see “Class `org.omg.CORBA.TypeCode`” on page 71.

**Java**

```
package org.omg.CORBA.TypeCodePackage;

public final class BadKind extends org.omg.CORBA.UserException {
 public BadKind();
}
```

**Notes**      CORBA-defined.

### **BadKind()**

**Synopsis**      `public BadKind();`

**Description**      Default constructor.

**Notes**      CORBA-defined.

## Class org.omg.CORBA.TypeCodePackage.Bounds

**Synopsis** Bounds is a CORBA defined `UserException` that can be thrown by a number of the methods in `TypeCode`. It flags an attempt to access a member with an invalid index.

For more information, see “Class org.omg.CORBA.TypeCode” on page 71.

**Java**

```
package org.omg.CORBA.TypeCodePackage;

public final class Bounds extends org.omg.CORBA.UserException {
 public Bounds();
}
```

**Notes** CORBA-defined.

### **Bounds()**

**Synopsis** `public Bounds();`

**Description** Default constructor.

**Notes** CORBA-defined.

# Class org.omg.CORBA.UnknownUserException

**Synopsis** UnknownUserException is a derived class of UserException holding a member of type Any, allowing it to contain an unspecified, or unknown, UserException. See also “Class org.omg.CORBA.UserException” page 77.

**Java**

```
package org.omg.CORBA;

public class UnknownUserException extends UserException {
 public Any except;
 public UnknownUserException() {
 super();
 }
 public UnknownUserException(Any a) {
 super();
 except = a;
 }
}
```

**Notes** CORBA-defined.

## UnknownUserException()

**Synopsis**

```
public UnknownUserException();
public UnknownUserException(Any a);
```

**Description** Constructor

**Parameters**

a            An instance of Any.

**Notes** CORBA-defined.

## Class org.omg.CORBA.UserException

**Synopsis** Orbix Java implementations of user exceptions are organized into a class hierarchy. Each user exception is mapped to a derived class of `UserException`, which is a derived class of `java.lang.Exception`. This allows all user exceptions to be caught in one single Java `catch` clause.

See also “Class `org.omg.CORBA.SystemException`” on page 66 and “Class `org.omg.CORBA.UnknownUserException`” on page 76.

**Java**

```
package org.omg.CORBA;

public abstract class UserException extends java.lang.Exception {
 public UserException();
}
```

**Notes** CORBA-defined.



Part II

Package

IE.Iona.OrbixWeb.CORBA





## Class IE.Iona.OrbixWeb.CORBA.Any

**Synopsis** The class `Any` implements the IDL basic type `any`, which allows the specification of values that can express an arbitrary IDL type. This allows a program to handle values whose types are not known at compile time. The IDL type `any` is most often used in code that uses the Interface Repository or the Dynamic Invocation Interface (DII) or with CORBA services in general.

Consider the following interface:

```
// IDL
interface Example {
 void op(in any value);
};
```

A client can construct an `any` to contain an arbitrary type of value and then pass this in a call to operation `op()`. A process receiving an `any` must determine what type of value it stores and then extract the value (using the `TypeCode`). Refer to the chapter “Type any” in the *Orbix Programmer’s Guide Java Edition*.

**Orbix Java** `public class Any extends org.omg.CORBA.Any implements java.lang.Cloneable {`

```
 //constructors
 public Any()
 throws org.omg.CORBA.SystemException;
 public Any(Any a)
 throws org.omg.CORBA.SystemException;
 public Any(int protocol)
 throws org.omg.CORBA.SystemException;
 public Any(String s)
 throws org.omg.CORBA.SystemException;
 public void copy(Any a)
 throws org.omg.CORBA.SystemException;
 public java.lang.Object clone()
 throws org.omg.CORBA.SystemException;
 public boolean equal(org.omg.CORBA.Any _obj)
 throws org.omg.CORBA.SystemException;
 public String toString()
 throws org.omg.CORBA.SystemException;
 public void fromString(String s)
```

```
 throws org.omg.CORBA.SystemException;
public void reset()
 throws org.omg.CORBA.SystemException;
public void type(org.omg.CORBA.TypeCode tc)
 throws org.omg.CORBA.SystemException;

//insertion methods

public void insert_short(int l)
 throws org.omg.CORBA.SystemException;
public void insert_long(int l)
 throws org.omg.CORBA.SystemException;
public void insert_longlong(long l)
 throws org.omg.CORBA.SystemException;
public void insert_ulonglong(long l)
 throws org.omg.CORBA.SystemException;
public void insert_ushort(short s)
 throws org.omg.CORBA.SystemException;
public void insert_ulong(int l)
 throws org.omg.CORBA.SystemException;
public void insert_float(float f)
 throws org.omg.CORBA.SystemException;
public void insert_double(double d)
 throws org.omg.CORBA.SystemException;
public void insert_char(char c)
 throws org.omg.CORBA.SystemException;
public void insert_octet(byte b)
 throws org.omg.CORBA.SystemException;
public void insert_string(String s)
 throws org.omg.CORBA.SystemException;
public void insert_boolean(boolean b)
 throws org.omg.CORBA.SystemException;
public void insert_any(org.omg.CORBA.Any a)
 throws org.omg.CORBA.SystemException;
public void insert_TypeCode(org.omg.CORBA.TypeCode tc)
 throws org.omg.CORBA.SystemException;
public void insert_Object(org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;
public void insert_Object(org.omg.CORBA.Object oref,
 org.omg.CORBA.TypeCode tc)
 throws org.omg.CORBA.SystemException;
public void insert_Streamable(org.omg.CORBA.portable.Streamable s)
 throws org.omg.CORBA.SystemException;
```

```
public void insert_Principal(org.omg.CORBA.Principal p)
 throws org.omg.CORBA.SystemException;
public void insert_wchar(char c)
 throws org.omg.CORBA.SystemException;
public void insert_wstring(String s)
 throws org.omg.CORBA.SystemException;

//input / output stream methods
public void read_value(org.omg.CORBA.portable.InputStream is,
 org.omg.CORBA.TypeCode t)
 throws MARSHAL,org.omg.CORBA.SystemException;
public void write_value(org.omg.CORBA.portable.OutputStream os)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.portable.OutputStream create_output_stream()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.portable.InputStream create_input_stream()
 throws org.omg.CORBA.SystemException;

//extraction methods
public short extract_short()
 throws org.omg.CORBA.SystemException;
public int extract_long()
 throws org.omg.CORBA.SystemException;
public long extract_ulonglong()
 throws org.omg.CORBA.SystemException;
public long extract_longlong()
 throws org.omg.CORBA.SystemException;
public char extract_wchar()
 throws org.omg.CORBA.SystemException;
public String extract_wstring()
 throws org.omg.CORBA.SystemException;
public short extract_ushort()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Principal extract_Principal()
 throws org.omg.CORBA.SystemException;
public int extract_ulong()
 throws org.omg.CORBA.SystemException;
public float extract_float()
 throws org.omg.CORBA.SystemException;
public double extract_double()
 throws org.omg.CORBA.SystemException;
public char extract_char()
 throws org.omg.CORBA.SystemException;
```

```
public byte extract_octet()
 throws org.omg.CORBA.SystemException;
public String extract_string()
 throws org.omg.CORBA.SystemException;
public boolean extract_boolean()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any extract_any()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode extract_TypeCode()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Object extract_Object()
 throws org.omg.CORBA.SystemException;
public void extract_Streamable(
 org.omg.CORBA.portable.Streamable s)
 throws org.omg.CORBA.SystemException;

// Data accessor methods
public org.omg.CORBA.TypeCode type()
 throws org.omg.CORBA.SystemException;
public boolean containsType(TypeCode t)
 throws org.omg.CORBA.SystemException;

}
```

### **Any()**

#### **Synopsis**

```
public Any()
 throws org.omg.CORBA.SystemException;
```

#### **Description**

Create a new *Any* with *Typecode* set to `_tc_null` and *value* set to `null`. This allows the *Any* to be populated using the insertion and extraction methods, for example:

```
org.omg.CORBA.Any a = new IE.Iona.OrbixWeb.CORBA.Any()
// could also have used
// a = org.omg.CORBA.Orb.init().create_any();

a.insertLong(10);
```

For user-defined types the `insert()` method can be used. For example given the following IDL:

```
// IDL
struct details {
 string address;
 string name;
}
```

you can use the following java code to insert the struct into an any:

```
// Java code
details d = // get details struct from somewhere
org.omg.CORBA.Any a = detailsHelper.insert(d);
```

Similarly, objects can be extracted using the Any extraction method or the extraction methods. Refer to the chapter “IDL to Java Mapping” in the *Orbix Programmer’s Guide Java Edition* for more details.

You can also use “Class `org.omg.CORBA.portable.InputStream`” and “Class `org.omg.CORBA.portable.OutputStream`” objects to insert and extract objects from type `Any`.

### Notes

PROGRESS-specific

### See Also

“Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279

“Class `org.omg.CORBA.portable.InputStream`” on page 53

“Class `org.omg.CORBA.portable.OutputStream`” on page 55

The chapter “IDL to Java Mapping” in the *Orbix Java Edition Programmer’s Guide*

### **Any()**

|                    |                                                                                                                                                           |                |                               |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|----------------|-------------------------------|
| <b>Synopsis</b>    | <pre>public Any(Any a)     throws org.omg.CORBA.SystemException;</pre>                                                                                    |                |                               |
| <b>Description</b> | The <code>Any</code> copy constructor, it creates a new <code>Any</code> with the same <code>TypeCode</code> and value as the <code>Any</code> passed in. |                |                               |
| <b>Parameters</b>  | <table><tr><td><code>a</code></td><td>The <code>Any</code> to copy.</td></tr></table>                                                                     | <code>a</code> | The <code>Any</code> to copy. |
| <code>a</code>     | The <code>Any</code> to copy.                                                                                                                             |                |                               |
| <b>Notes</b>       | PROGRESS-specific                                                                                                                                         |                |                               |
| <b>See Also</b>    | “Class <code>IE.Iona.OrbixWeb.CORBA.TypeCode</code> ” on page 279                                                                                         |                |                               |

### **Any()**

|                       |                                                                                                                                                                                                                                                                                                                                                                                            |                       |                                                                        |
|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------|------------------------------------------------------------------------|
| <b>Synopsis</b>       | <pre>public Any(int protocol)     throws org.omg.CORBA.SystemException;</pre>                                                                                                                                                                                                                                                                                                              |                       |                                                                        |
| <b>Description</b>    | Create a new <code>Any</code> for the given protocol type. This protocol can be one of the following: <ul style="list-style-type: none"><li>• <code>IE.Iona.orbixWeb._CORBA.IT_INTEROPERABLE_OR_KIND</code></li><li>• <code>IE.Iona.orbixWeb._CORBA.IT_ORBIX_OR_KIND</code></li></ul> This parameter indicates the marshalling protocol to be associated with the <code>Any</code> object. |                       |                                                                        |
| <b>Parameters</b>     | <table><tr><td><code>protocol</code></td><td>The protocol type (IIOP or Orbix Protocol) for this <code>Any</code>.</td></tr></table>                                                                                                                                                                                                                                                       | <code>protocol</code> | The protocol type (IIOP or Orbix Protocol) for this <code>Any</code> . |
| <code>protocol</code> | The protocol type (IIOP or Orbix Protocol) for this <code>Any</code> .                                                                                                                                                                                                                                                                                                                     |                       |                                                                        |
| <b>Notes</b>          | PROGRESS-specific                                                                                                                                                                                                                                                                                                                                                                          |                       |                                                                        |
| <b>See Also</b>       | “Class <code>IE.Iona.OrbixWeb.CORBA.TypeCode</code> ” on page 279<br>“Class <code>IE.Iona.OrbixWeb._CORBA</code> ” on page 343                                                                                                                                                                                                                                                             |                       |                                                                        |

## Any()

**Synopsis**      `public Any(String s)`

**Description**      Create an `Any` from the `String` passed in.

**Parameters**

`s`                  `Any` data in persistent stringified form, this form of an `Any` can be generated by calling the `toString()` method.

**Notes**              PROGRESS-specific

**See Also**            “Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279  
“`toString()`” on page 96  
“`fromString()`” on page 92

### **clone()**

|                     |                                                                                                                                    |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>     | <pre>public java.lang.Object clone()<br/>    throws org.omg.CORBA.SystemException;</pre>                                           |
| <b>Description</b>  | This method creates a new <code>Any</code> containing a copy of the same data as the original.                                     |
| <b>Return Value</b> | <pre>java.lang.Object</pre> A clone of the original <code>Any</code> .                                                             |
| <b>Exceptions</b>   | A <code>java.lang.Error</code> exception is thrown if this object does not support the <code>java.lang.Cloneable</code> interface. |
| <b>Notes</b>        | PROGRESS-specific                                                                                                                  |
| <b>See Also</b>     | “Class <code>IE.Iona.OrbixWeb.CORBA.TypeCode</code> ” on page 279                                                                  |

### **containsType()**

|                     |                                                                                                                                                                                  |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>     | <pre>public boolean containsType(TypeCode t)<br/>    throws org.omg.CORBA.SystemException;</pre>                                                                                 |
| <b>Description</b>  | This method returns <code>true</code> if the <code>Object</code> within the <code>Any</code> is of the same <code>Type</code> as the <code>TypeCode</code> passed in.            |
| <b>Parameters</b>   | <pre>t</pre> The <code>TypeCode</code> to check for.                                                                                                                             |
| <b>Return Value</b> | <pre>boolean</pre> This value is <code>true</code> if the <code>TypeCode</code> passed in and the <code>TypeCode</code> contained in the <code>Any</code> are the same           |
| <b>Notes</b>        | PROGRESS-specific                                                                                                                                                                |
| <b>See Also</b>     | “Class <code>IE.Iona.OrbixWeb.CORBA.TypeCode</code> ” on page 279<br>“Class <code>org.omg.CORBA.portable.InputStream</code> ” on page 53<br>“ <code>insert()</code> ” on page 93 |



### copy()

**Synopsis**      `public void copy(Any a)`  
                  `throws org.omg.CORBA.SystemException;`

**Description**      Copy data from another Any into this one

**Parameters**

a                      The Any to be copied.

**Notes**              PROGRESS-specific

**See Also**            “Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279

### create\_output\_stream()

**Synopsis**      `public org.omg.CORBA.portable.OutputStream create_output_stream()`  
                  `throws org.omg.CORBA.SystemException;`

**Description**      This method creates an `org.omg.CORBA.portable.OutputStream` object for this Any. This object allows the Any to be populated by calling the `write()` methods declared on `OutputStream` instead of using the `insert()` methods of the Any. It also allows us to access certain objects such as Any, Request and so on, in a uniform manner.

**Return Value**

`OutputStream`              The `OutputStream` representing the Any

**Notes**              CORBA-defined.

**See Also**            “Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279  
                  “Class `org.omg.CORBA.portable.OutputStream`” on page 55  
                  “insert()” on page 93

### **create\_input\_stream()**

**Synopsis**

```
public org.omg.CORBA.portable.InputStream create_input_stream()
 throws org.omg.CORBA.SystemException;
```

**Description**

This method creates an `org.omg.CORBA.portable.InputStream` object for this `Any`, so that the data contained within the `Any` can be accessed through the `read()` methods defined on `InputStream` rather than the `extract()` methods defined on `Any`.

**Return Value**

`InputStream`                      The `InputStream` representing the `Any`.

**Notes**

CORBA-defined.

**See Also**

“Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279  
“Class `org.omg.CORBA.portable.InputStream`” on page 53  
“`extract()`” on page 91

### **equal()**

**Synopsis**

```
public boolean equal(org.omg.CORBA.Any _obj)
```

**Description**

This method compares the type and value of this `Any` with that of the `Any` passed in as a parameter.

**Parameters**

`_obj`                              The `Any` to compare against.

**Return Value**

`boolean`                          Set to `true` if the `Anys` are equal.

**Notes**

CORBA-defined.

**See Also**

“Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279

### **extract()**

#### **Synopsis**

```
public short extract_short()
 throws org.omg.CORBA.SystemException;
public int extract_long()
 throws org.omg.CORBA.SystemException;
public long extract_ulonglong()
 throws org.omg.CORBA.SystemException;
public long extract_longlong()
 throws org.omg.CORBA.SystemException;
public char extract_wchar()
 throws org.omg.CORBA.SystemException;
public String extract_wstring()
 throws org.omg.CORBA.SystemException;
public short extract_ushort()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Principal extract_Principal()
 throws org.omg.CORBA.SystemException;
public int extract_ulong()
 throws org.omg.CORBA.SystemException;
public float extract_float()
 throws org.omg.CORBA.SystemException;
public double extract_double()
 throws org.omg.CORBA.SystemException;
public char extract_char()
 throws org.omg.CORBA.SystemException;
public byte extract_octet()
 throws org.omg.CORBA.SystemException;
public String extract_string()
 throws org.omg.CORBA.SystemException;
public boolean extract_boolean()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any extract_any()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode extract_TypeCode()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Object extract_Object()
 throws org.omg.CORBA.SystemException;
public void extract_Streamable(
 org.omg.CORBA.portable.Streamable s)
 throws org.omg.CORBA.SystemException;
```

**Description** These methods are used to extract the indicated type from the `Any`. You can determine the type of the `Any` using the `org.omg.CORBA.Any` method. You can extract the value using the appropriate extraction method. To extract a user defined type, you can also use the Helper classes, for example:

```
org.omg.CORBA.Any a = // get the any from somewhere
 // for example, through the DII,
 // from one of the CORBA services.

Object val;

switch(a.type().kind()){
 case org.omg.CORBA.TCKind._tc_short:
 val = new Short(a.extract_short());
 break;

 //etc. for other basic types

 default :
 if(a.type().equal(AStructHelper.type()){
 val = AStructHelper.extract(a);
 }
 // else some other user defined types
 break;
};
```

You can also obtain the same kind of result by using class `org.omg.CORBA.portable.InputStream`.

**Notes** CORBA-defined.

**See Also** “Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279  
“Class `org.omg.CORBA.portable.InputStream`” on page 53  
The chapter “IDL to Java Mapping” in the *Orbix Programmer's Guide Java Edition*

### **fromString()**

**Synopsis** `public void fromString(String s)`

**Description** Using the `toString()` method, you can save the state of an `Any` to a `String`. This method allows the state of an `Any` to be regenerated from one of these strings.

### Parameters

s                    The String containing the representation of an Any.

**Exceptions**      An `org.omg.CORBA.BAD_PARAM` exception is thrown if the string representation is incorrect.

**Notes**            PROGRESS-specific

**See Also**        “Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279  
“`toString()`” on page 96

### **insert()**

#### **Synopsis**

```
public void insert_short(short s)
 throws org.omg.CORBA.SystemException;
public void insert_long(int l)
 throws org.omg.CORBA.SystemException;
public void insert_longlong(long l)
 throws org.omg.CORBA.SystemException;
public void insert_ulonglong(long l)
 throws org.omg.CORBA.SystemException;
public void insert_ushort(short s)
 throws org.omg.CORBA.SystemException;
public void insert_ulong(int l)
 throws org.omg.CORBA.SystemException;
public void insert_float(float f)
 throws org.omg.CORBA.SystemException;
public void insert_double(double d)
 throws org.omg.CORBA.SystemException;
public void insert_char(char c)
 throws org.omg.CORBA.SystemException;
public void insert_octet(byte b)
 throws org.omg.CORBA.SystemException;
public void insert_string(String s)
 throws org.omg.CORBA.SystemException;
public void insert_boolean(boolean b)
 throws org.omg.CORBA.SystemException;
public void insert_any(org.omg.CORBA.Any a)
 throws org.omg.CORBA.SystemException;
```

```
public void insert_TypeCode(org.omg.CORBA.TypeCode tc)
 throws org.omg.CORBA.SystemException;
public void insert_Object(org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;
public void insert_Object(org.omg.CORBA.Object oref,
 org.omg.CORBA.TypeCode tc)
 throws org.omg.CORBA.SystemException;
public void insert_Streamable(Streamable s)
 throws org.omg.CORBA.SystemException;
public void insert_Principal(org.omg.CORBA.Principal p)
 throws org.omg.CORBA.SystemException;
public void insert_wchar(char c)
 throws org.omg.CORBA.SystemException;
public void insert_wstring(String s)
 throws org.omg.CORBA.SystemException;
```

**Description** Insert a value of the indicated type into the Any.

Previous values held in the Any are discarded and each insertion method takes a copy of the value inserted.

You can use the <name>Helper class to insert a user-defined type. For example, given the following IDL:

```
//IDL
struct AStruct{
 string str;
 float number;
};
```

Use the insert () method generated on the AStructHelper class:

```
//Java
org.omg.CORBA.Any a = new
IE.Iona.OrbixWeb.CORBA.Any ();

Astruct s = new Astruct ("String", 1.0f);
try {
 AstructHelper.insert (a, s);
}
catch (org.omg.CORBA.SystemException) {
 //do something here
}
```

The same result can be achieved using the "Class org.omg.CORBA.portable.OutputStream"

### Parameters

|                 |                                                        |
|-----------------|--------------------------------------------------------|
| first parameter | The actual value to insert into the Any.               |
| tc              | The <code>TypeCode</code> of the value being inserted. |

**Notes** CORBA-defined.

**See Also** “Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279  
“Class org.omg.CORBA.portable.OutputStream” on page 55  
The chapter “IDL to Java Mapping” in the *Orbix Programmer's Guide Java Edition*

### read\_value()

#### Synopsis

```
public void read_value(org.omg.CORBA.portable.InputStream is,
 org.omg.CORBA.TypeCode t)
 throws org.omg.CORBA.MARSHAL,
 org.omg.CORBA.SystemException;
```

#### Description

This method is used to read an object from an “Class `org.omg.CORBA.portable.InputStream`” into the current Any.

#### Parameters

|    |                                                                     |
|----|---------------------------------------------------------------------|
| is | The <code>InputStream</code> to read the data from.                 |
| t  | The <code>TypeCode</code> of the object to be read from the stream. |

**Exceptions** An `org.omg.CORBA.MARSHAL` exception is thrown if the data in the `InputStream` is not an object of the type specified by the passed in `TypeCode`.

**Notes** CORBA-defined.

**See Also** “Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279

### **reset()**

|                    |                                                                                                                                                                       |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>    | <code>public void reset()</code>                                                                                                                                      |
| <b>Description</b> | Sets the <code>TypeCode</code> to <code>tk_null</code> and the <code>value</code> to <code>null</code> . Use this method when you want to reuse an <code>Any</code> . |
| <b>Notes</b>       | PROGRESS-specific.                                                                                                                                                    |
| <b>See Also</b>    | “Class <code>IE.Iona.OrbixWeb.CORBA.TypeCode</code> ” on page 279                                                                                                     |

### **toString()**

|                     |                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>     | <code>public String toString()</code>                                                                                                                                                                                                                                                                                                                                                                                                                     |
| <b>Description</b>  | Convert the <code>Any</code> to a string. <code>Any</code> s can be freely converted to and from strings.<br>Format:<br>Orbix: " <code>&lt;typecode string&gt; HDR:&lt;marshalled value as hex string&gt;</code> "<br>IIOP: " <code>&lt;typecode string&gt; CDR:&lt;marshalled value as hex string&gt;</code> "<br>You can use the " <code>fromString()</code> " method to perform the reverse process and convert a string back to an <code>Any</code> . |
| <b>Return Value</b> | <code>String</code> A string representation of the <code>Any</code>                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>Notes</b>        | PROGRESS-specific                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <b>See Also</b>     | “Class <code>IE.Iona.OrbixWeb.CORBA.TypeCode</code> ” on page 279<br>“ <code>fromString()</code> ” on page 92                                                                                                                                                                                                                                                                                                                                             |



### type()

**Synopsis**

```
public org.omg.CORBA.TypeCode type()
 throws org.omg.CORBA.SystemException;
```

**Description**

This method returns the `TypeCode` of the `Object` encapsulated within the `Any`.

**Return Value**

`TypeCode`                      The `TypeCode` of the `Object` within the `Any`.

**Notes**

CORBA-defined.

**See Also**

“Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279

### write\_value()

**Synopsis**

```
public void write_value(org.omg.CORBA.portable.OutputStream os)
 throws org.omg.CORBA.SystemException;
```

**Description**

This method writes the object contained within the `Any` into the specified `OutputStream`.

**Parameters**

`os`                              The `OutputStream` to write the data to.

**Notes**

CORBA-defined.

**See Also**

“Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279  
“Class org.omg.CORBA.portable.OutputStream” on page 55

# Interface `IE.Iona.OrbixWeb.CORBA.BOA`

## Synopsis

The server-side element of the CORBA IDL to Java Language mapping specifies a minimal Java API based upon the OMG CORBA BOA pseudo-interface. BOA is an abbreviation of Basic Object Adapter.

In earlier versions of Orbix Java the BOA is implemented as a class extending the `IE.Iona.OrbixWeb.CORBA.ORB` class. By default, any ORB object created is a BOA and thus supported the full server functionality.

The BOA is now an interface which the ORB and the new `BOAImpl` class implement. The ORB delegates the BOA operations to an instance of `BOAImpl`. This class structure cleanly separates the BOA implementation from the ORB implementation while maintaining backward compatibility. This separation means that the BOA implementation class need only be instantiated dynamically when server-side operations are actually used. This prevents unnecessary resource consumption by clients. In addition, it dispenses with static configuration of BOA support to minimize download time of applets that do not require the BOA. All BOA operations should be called on an instance of the ORB; for example `_CORBA.Orbix`.

Interface BOA provides methods that control Orbix Java from the server. These include methods to:

- Activate and deactivate servers.
- Activate and deactivate objects.
- Create and interpret object references.

The methods of this class are invoked through the ORB on the server.

## CORBA

```
// Pseudo IDL

module CORBA {
 interface InterfaceDef; // from Interface Repository // PIDL
 interface ImplementationDef; // from Interface Repository
 interface Object; // an object reference
 interface Principal; // for the authentication service
 typedef sequence <octet, 1024> ReferenceData;

 interface BOA {
```

## Interface IE.Iona.OrbixWeb.CORBA.BOA

---

```
void impl_is_ready (in ImplementationDef impl);
void deactivate_impl (in ImplementationDef impl);
void obj_is_ready (in Object obj, in ImplementationDef
 impl);
void deactivate_obj (in Object obj);

void change_implementation (
 in Object obj,
 in ImplementationDef impl
);

Principal get_principal (
 in Object obj,
 in Environment ev
);

void dispose (in Object obj);

Object create (
 in ReferenceData id,
 in InterfaceDef intf,
 in ImplementationDef impl
);
ReferenceData get_id (in Object obj);
};
};
```

### Orbix Java

```
public interface BOA {

 // General methods
 public java.lang.String toString();

 public void finalize();
 public void shutdown();

 // Event processing methods
 public int processNextEvent(int timeOut)
 throws org.omg.CORBA.SystemException;

 public int processNextEvent()
 throws org.omg.CORBA.SystemException;

 public int processEvents(int timeOut)
```

```
 throws org.omg.CORBA.SystemException;

 public int processEvents()
 throws org.omg.CORBA.SystemException;

 public boolean isEventPending()
 throws org.omg.CORBA.SystemException;

 public void impl_is_ready(java.lang.String serverName,
 int timeOut)
 throws org.omg.CORBA.SystemException;

 public void impl_is_ready(int timeOut)
 throws org.omg.CORBA.SystemException;

 public void impl_is_ready(java.lang.String serverName)
 throws org.omg.CORBA.SystemException;

 public void impl_is_ready()
 throws org.omg.CORBA.SystemException;

 public void deactivate_impl(java.lang.String impl)
 throws org.omg.CORBA.SystemException;

 public void connect(org.omg.CORBA.Object obj)
 throws org.omg.CORBA.SystemException;

 public void connect(org.omg.CORBA.Object obj,
 java.lang.String marker)
 throws org.omg.CORBA.SystemException;

 public void connect(org.omg.CORBA.Object obj,
 IE.Iona.OrbixWeb.Features.LoaderClass loader)
 throws org.omg.CORBA.SystemException;

 public void connect(org.omg.CORBA.Object obj,
 java.lang.String marker,
 IE.Iona.OrbixWeb.Features.LoaderClass loader)
 throws org.omg.CORBA.SystemException;

 public synchronized void disconnect
 (org.omg.CORBA.Object obj)
 throws org.omg.CORBA.SystemException;
```

## Interface IE.Iona.OrbixWeb.CORBA.BOA

---

```
public void dispose(org.omg.CORBA.Object obj)
 throws org.omg.CORBA.SystemException;

public void obj_is_ready(org.omg.CORBA.Object obj,
 java.lang.String impl,
 int timeout)
 throws org.omg.CORBA.SystemException;

public void obj_is_ready(org.omg.CORBA.Object obj,
 java.lang.String impl)
 throws org.omg.CORBA.SystemException;

public void deactivate_obj(org.omg.CORBA.Object obj)
 throws org.omg.CORBA.SystemException;

public void continueThreadDispatch(org.omg.CORBA.Request r);

// No implementation methods
public org.omg.CORBA.Object create(byte[] id,
 java.lang.String intf,
 java.lang.String impl)
 throws org.omg.CORBA.SystemException;

public byte[] get_id (org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;

// Configuration Methods
public boolean setNoHangup(boolean b)
 throws org.omg.CORBA.SystemException;

public static synchronized void
 setProxyServer(java.lang.String host,
 int port)
 throws org.omg.CORBA.SystemException;

public static synchronized void
 enableProxyServer(boolean useProxy)
 throws org.omg.CORBA.SystemException;

public synchronized void
 setServerName(java.lang.String serverName)
 throws org.omg.CORBA.SystemException;
```

```
public void change_implementation(org.omg.CORBA.Object obj,
 java.lang.String impl)
 throws org.omg.CORBA.SystemException;
public boolean enableLoaders(boolean b)
 throws org.omg.CORBA.SystemException;
// Accessor methods
public boolean anyClientsConnected()
 throws org.omg.CORBA.SystemException;

public int numClientsConnected()
 throws org.omg.CORBA.SystemException;

public org.omg.CORBA.Principal get_principal()
 throws org.omg.CORBA.SystemException;

public java.lang.String get_principal_string()
 throws org.omg.CORBA.SystemException;

public org.omg.CORBA.Current get_current()
 throws org.omg.CORBA.SystemException;

public java.lang.String myImplementationName()
 throws org.omg.CORBA.SystemException;

public java.lang.String myMarkerName()
 throws org.omg.CORBA.SystemException;

public java.lang.String myMarkerPattern()
 throws org.omg.CORBA.SystemException;

public java.lang.String myMethodName()
 throws org.omg.CORBA.SystemException;

public short myActivationMode()
 throws org.omg.CORBA.SystemException;

public java.lang.String myHost()
 throws org.omg.CORBA.SystemException;

public java.lang.String myHostIP()
 throws org.omg.CORBA.SystemException;
```

## Interface `IE.Iona.OrbixWeb.CORBA.BOA`

---

```
public static final short perMethodActivationMode;
public static final short persistentActivationMode;
public static final short sharedActivationMode;
public static final short unknownActivationMode;
public static final short unsharedActivationMode;
}
```

- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.ORB`” on page 46  
“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184

### **anyClientsConnected()**

- Synopsis**

```
public boolean anyClientsConnected()
 throws org.omg.CORBA.SystemException;
```
- Description** Determines if there are any connections from clients to this server. This has a different behaviour if the server has been launched as a thread in the thread-per-server mode with the `orbixdj`. In this case the call determines whether or not there are any connections to the process at all, not just whether the connections are only used by the server thread that made the call.
- Return Value** Returns `true` if any clients are connected; returns `false` otherwise.
- Notes** PROGRESS-specific.
- See Also** “`numClientsConnected()`” on page 121

### **change\_implementation()**

- Synopsis**

```
public void change_implementation
 (org.omg.CORBA.Object obj,
 java.lang.String impl)
 throws org.omg.CORBA.SystemException;
```
- Description** Changes the implementation (server name) associated with the object `oref`. You can use this method to overcome the problem of exporting an object reference from a persistent server before `impl_is_ready()` is called. You can use the `BOA.setServerName()` method to change the implementation for all objects created by a server.

Note that if a server creates an object and clients then invoke on this object, subsequent invocations on the object may fail following a call to `BOA.change_implementation()` on that object.

### Parameters

`obj`            The object reference for which the implementation is to change.  
`impl`           The name of the new implementation (server).

### Notes

CORBA-defined.

You are unlikely to need this method.

### See Also

“`impl_is_ready()`” on page 114  
“`setServerName()`” on page 128

## **connect()**

### Synopsis

```
public void connect(org.omg.CORBA.Object obj)
 throws org.omg.CORBA.SystemException;
public void connect(org.omg.CORBA.Object obj,
 IE.Iona.OrbixWeb.Features.LoaderClass loader)
 throws org.omg.CORBA.SystemException;
public void connect(org.omg.CORBA.Object obj,
 java.lang.String marker)
 throws org.omg.CORBA.SystemException;
public void connect(org.omg.CORBA.Object obj
 java.lang.String marker,
 IE.Iona.OrbixWeb.Features.LoaderClass loader)
 throws org.omg.CORBA.SystemException;
```

### Description

Used to explicitly connect object implementations to the ORB. The connect method does the following:

- Places the object into the object table.
- Associates it with a marker.
- Associates it with a loader.
- If there is no such thread running already, starts an event-processing thread in the background.



Instantiating an Orbix Java object automatically calls `connect()` for you. However, for strict CORBA compliance you should explicitly call it in your application code also.

To disconnect objects from the ORB and remove them from the object table call `BOA.disconnect()`. When the last object has been disconnected the event-processing thread is stopped.

If you call `BOA.impl_is_ready()` directly yourself its timeout functionality takes control of the event-processing thread. Therefore, when `BOA.impl_is_ready()` times out and returns, the event-processing thread has stopped.

Sometimes you may not want the instantiation of objects to have the side-effect of starting an event-processing thread. You may have a large number of objects that you wish to initialize fully before allowing events to be invoked upon them by the ORB. To prevent `connect()` from starting the event-processing thread, set the Orbix Java variable `IT_IMPL_READY_IF_CONNECTED` to false. If you are using persistent servers you must:

- ♦ call `setServerName(<serverName>)`
- ♦ or have the `java.lang.System` property `'orbixweb.server_name'` set to the implementation (server) name

before you instantiate any objects and you want to pass them out as object-references before calling `BOA.impl_is_ready()`.

When your persistent server is ready to process events you must call `BOA.impl_is_ready(<serverName>)`.

If `connect()` is called twice on an object that has already been connected it has no effect.

After instantiating an object it is possible to call `disconnect()` on that object to disconnect it from the ORB. You can then call `connect()` to reconnect it again.

For more information on naming objects and associating objects with loaders refer to the chapters “Making Objects Available with Orbix Java” and “Locating Servers at Runtime” in the *Orbix Java Edition Programmer's Guide*.

For more information on `IT_IMPL_READY_IF_CONNECTED` refer to the configuration chapter in the *Orbix Java Edition Administrator's Guide*.

### Parameters

|                     |                                                                      |
|---------------------|----------------------------------------------------------------------|
| <code>obj</code>    | The object implementation that is to be connected to the ORB.        |
| <code>marker</code> | The marker to be given to the object.                                |
| <code>loader</code> | The <code>LoaderClass</code> object to be associated with the object |

### Notes

CORBA-defined.

### See Also

“`disconnect()`” on page 109

“`impl_is_ready()`” on page 114

## **continueThreadDispatch()**

### Synopsis

```
public void continueThreadDispatch(org.omg.CORBA.Request r);
```

### Description

Instructs the Orbix Java runtime to continue dispatching the `Request` in the current thread.

You should use this method in conjunction with `ThreadFilters`. When an instance of `ThreadFilter` receives a `Request` object in its `inRequestPreMarshal` filter point, it can take responsibility from the Orbix Java runtime for scheduling when the `Request` is processed.

Normally the `ThreadFilter` passes the `Request` object into a user-defined queue. This queue is then serviced by one or more user-created threads. They decide when they want to continue dispatching the `Request` by calling the `continueThreadDispatch()` method.

When `continueThreadDispatch()` is called the `Request` object continues to be processed like a normal request. It is passed through filter points, processed by the implementation object and a reply is sent to the client.

The `Request`, however, bypasses any other `ThreadFilters` that are installed but not reached yet.

If an exception (`org.omg.CORBA.SystemException` or `java.lang.Exception`) is thrown while the `Request` is processed the exception is returned to the client.

A `continueThreadDispatch()` call returns when a reply or exception message is sent back to the client.

## Interface `IE.Iona.OrbixWeb.CORBA.BOA`

---

### Parameters

`r` The Request object to be processed.

**Notes** PROGRESS-specific.

**See Also** “Class `org.omg.CORBA.Request`” on page 59  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248  
“Class `IE.Iona.OrbixWeb.Features.ThreadFilter`” on page 337

### `create()`

### Synopsis

```
public org.omg.CORBA.Object create(byte[] id,
 java.lang.String intf,
 java.lang.String impl)
 throws org.omg.SystemException;
```

### Description

This method is currently not implemented and always raises an `org.omg.CORBA.NO_IMPLEMENT` exception when called. You should use `IE.Iona.OrbixWeb.ORB.makeIOR()` or `IE.Iona.OrbixWeb.ORB.string_to_object()` to create object references. The following description is for reader information only.

This method creates a new object reference. It does not create an implementation object. As such, it is only used when an implementation object exists in the server or an appropriate loader is installed.

### Parameters

`id` Opaque identification information, supplied by the caller, and stored in an object. This is an IDL sequence of octets that, in Orbix Java, maps to the object marker.

`intf` The Interface Repository object that specifies the set of interfaces implemented by the object.

`impl` The Implementation Repository entry (server name) that specifies the implementation to be used for the object.

### Exceptions

If the `id` does not match the marker of an object currently resident in (or loaded into) the server address space, `CORBA.BOA.create()` raises a `CORBA.INV_OBJREF` exception.

**Notes** CORBA-defined.

**See Also** “get\_id()” on page 112  
“Interface IE.Iona.OrbixWeb.CORBA.ObjectRef” on page 168  
“Class org.omg.CORBA.ORB” on page 46

### **deactivate\_impl()**

**Synopsis**

```
public void deactivate_impl(java.lang.String impl)
 throws org.omg.SystemException;
```

**Description** A server that has called `impl_is_ready()` to indicate that it has completed initialization and is ready to receive requests, may subsequently indicate to Orbix Java that it wishes to discontinue receiving requests. It does so by calling `deactivate_impl()`, and passing the server name in the parameter `impl`. Calling `deactivate_impl()` causes `impl_is_ready()` to return.

#### **Parameters**

`impl` The server name, as passed to `impl_is_ready()`.

**Notes** CORBA-defined.

**See Also** “impl\_is\_ready()” on page 114

### **deactivate\_obj()**

**Synopsis**

```
public void deactivate_obj(org.omg.CORBA.Object obj)
 throws org.omg.SystemException;
```

**Description** A server (running in unshared activation mode) that has called `obj_is_ready()` to indicate that it has completed initialization and is ready to receive requests, may subsequently indicate to Orbix Java that it wishes to discontinue receiving requests for this object. It does so by calling `deactivate_obj()`, and passing the object whose marker caused the server process to be launched, in the parameter `oref`.

#### **Parameters**

`obj` The object whose marker caused the server to be launched.

**Notes** CORBA-defined.  
**See Also** “obj\_is\_ready()” on page 121

### **disconnect()**

**Synopsis**

```
public synchronized void disconnect(org.omg.CORBA.Object obj)
 throws org.omg.CORBA.SystemException;
```

**Description** Removes the object reference `obj` from the runtime object table. Future invocations on the object fail with an `INV_OBJREF` exception.

When `disconnect()` is called, if `obj` has a `LoaderClass` object associated with it, the loader object’s `save()` method is called. The reason passed to `save()` will be `_CORBA.explicitCall`. For more information refer to the *Orbix Programmer’s Guide Java Edition* .

`disconnect()` has the same behaviour as `BOA.dispose().disconnect()`, and is the preferred method pending the introduction of the Portable Object Adapter to the IDL/Java Language Mapping.

To reconnect an object after it has been disposed call `BOA.connect()` .

### **Parameters**

`obj` The object to be disconnected.

**Notes** CORBA-defined.  
**See Also** “Interface org.omg.CORBA.Object” on page 45  
“connect()” on page 104  
“Interface IE.Iona.OrbixWeb.CORBA.ObjectRef” on page 168  
“save()” on page 325

### **dispose()**

- Synopsis**      `public void dispose(org.omg.CORBA.Object obj)`  
                  `throws org.omg.CORBA.SystemException;`
- Description**    `dispose()` has the same behaviour as `BOA.disconnect()`. However, `disconnect()` is the preferred method pending the introduction of the Portable Object Adapter to the IDL/Java Language Mapping.
- See `BOA.disconnect()` for a description of this method's behaviour.
- Notes**            CORBA-defined.
- See Also**        “Interface `org.omg.CORBA.Object`” on page 45  
                  “`connect()`” on page 104  
                  “Interface `IE.Iona.OrbixWeb.CORBA.ObjectRef`” on page 168  
                  “`save()`” on page 325

### **enableLoaders()**

- Synopsis**      `public boolean enableLoaders(boolean b)`  
                  `throws org.omg.CORBA.SystemException;`
- Description**    Globally enables or disables loaders. See the *Orbix Programmer's Guide Java Edition* for more details.
- Parameters**
- b**            `true` enables the loaders, `false` disables the loaders.
- Return Value**   Returns the previously set value.
- Notes**            PROGRESS-specific.
- See Also**        “Class `IE.Iona.OrbixWeb.Features.LoaderClass`” on page 319

### **enableProxyServer()**

**Synopsis**

```
public static synchronized void
 enableProxyServer(boolean useProxy)
 throws org.omg.CORBA.SystemException;
```

**Description**

This method is provided for supporting the Wonderwall firewall product.

If set to `true`, any CORBA objects created afterwards contain the host name and port number of the proxy server, that is, Wonderwall. If set to `false`, they contain the actual server's host and port.

Use `BOA.setProxyServer()` to set the port and host for the proxy server.

See your *Wonderwall Administrator's Guide* for full details of how to use this method.

**Parameters**

`useProxy`    `true` means any new CORBA objects created contains the port and host of the proxy server.  
`false` means that they contain the actual server host and port.

**Notes**

PROGRESS-specific.

**See Also**

`setProxyServer()` on page 128

### **finalize()**

**Synopsis**

```
public void finalize()
```

**Description**

Cleans up the object table being used by the BOA object. As BOA inherits from ORB it also cleans up its connection table.

When the object table is finalizing, `save()` is called on the `LoaderClass` object associated with each object in the table. The reason given is `IE.Iona.OrbixWeb._CORBA.processTermination`. See the *Orbix Programmer's Guide Java Edition* for more details.

This method is called in two ways:

- By the garbage collector when the server shuts down. To be sure of this you must call the JDK1.1 method `java.lang.System.runFinalizersOnExit(true)`.

- By the user explicitly calling `finalize()` on the BOA object. You must do this just before the server exits. This is particularly important when using loaders, otherwise you cannot be sure that the currently active objects in the server get a chance to `save()` themselves.

**Notes** PROGRESS-specific.

**See Also** “`finalize()`” on page 205  
“Class `IE.Iona.OrbixWeb.Features.LoaderClass`” on page 319

### **get\_current()**

**Synopsis**

```
public org.omg.CORBA.Current get_current()
 throws org.omg.CORBA.SystemException;
```

**Description** Orbix Java returns an instance of `IE.Iona.OrbixWeb.CORBA.Orbcurrent`. You can query this object for information.

The `IT_MULTI_THREADED_SERVER` configuration parameter must be set to true.

Refer to the configuration chapter in the *Orbix Programmer's Guide Java Edition* for more information on `IT_MULTI_THREADED_SERVER`.

**Notes** CORBA-defined.

**See Also** “Class `org.omg.CORBA.ORB`” on page 46  
“Class `IE.Iona.OrbixWeb.CORBA.OrbCurrent`” on page 237

### **get\_id()**

**Synopsis**

```
public byte[] get_id(org.omg.CORBA.Object obj)
 throws org.omg.SystemException;
```

**Description** This method is currently not implemented and always raises an `org.omg.CORBA.NO_IMPLEMENT` exception when called. Orbix Java programmers should use `IE.Iona.OrbixWeb.ObjectRef._marker()` instead. The following description is for reader information.

Returns the identification information for the object `obj` as set in `BOA.create()`.

**Notes** CORBA-defined.



**See Also** “create()” on page 107  
“Interface IE.Iona.OrbixWeb.CORBA.ObjectRef” on page 168

### **get\_principal()**

**Synopsis**

```
public org.omg.CORBA.Principal get_principal()
 throws org.omg.CORBA.SystemException;
```

**Description** This method returns the `Principal` object for the client that made the operation call currently being processed.

Set `IT_MULTI_THREADED_SERVER` to `true` before initializing the ORB.

**Notes** CORBA-defined.

**See Also** “Class org.omg.CORBA.Principal” on page 58  
“get\_principal\_string()” on page 113  
“Class IE.Iona.OrbixWeb.CORBA.Principal” on page 244

### **get\_principal\_string()**

**Synopsis**

```
public java.lang.String get_principal_string()
 throws org.omg.CORBA.SystemException;
```

**Description** This method returns a string version of the `Principal` object for the client that made the operation call currently being processed.

Set `IT_MULTI_THREADED_SERVER` to `true` before initializing the ORB.

**Notes** PROGRESS-specific.

**See Also** “Class org.omg.CORBA.Principal” on page 58  
“get\_principal()” on page 113  
“Class IE.Iona.OrbixWeb.CORBA.Principal” on page 244

### **impl\_is\_ready()**

#### **Synopsis**

```
public void impl_is_ready()
 throws org.omg.CORBA.SystemException;
public void impl_is_ready(java.lang.String serverName)
 throws org.omg.CORBA.SystemException;
public void impl_is_ready(int timeOut)
 throws org.omg.CORBA.SystemException;
public void impl_is_ready(java.lang.String serverName,
 int timeOut)
 throws org.omg.CORBA.SystemException;
```

#### **Description**

Once you register a server with Orbix Java the daemon may automatically launch the server if an operation is invoked on one of its objects. You can also launch a server persistently (manually).

Once launched, the server initializes itself and creates any objects it requires. This automatically connects the objects to the ORB and optionally calls `impl_is_ready()` to use this call's timeout facility.

The `impl_is_ready()` method normally does not return immediately. It blocks the server until an event occurs, handles the event, and re-blocks the server to await another event. The methods `BOA.processEvents()` and `BOA.processNextEvent()` provide alternative ways of handling events.

The `impl_is_ready()` method returns only when:

- A timeout occurs.  
This occurs when the server has no clients for the timeout duration, or because none of its clients use it for that period.
- An exception occurs while waiting for an incoming event.
- The function `BOA.deactivate_impl()` is called.

If you are using persistent servers with the daemon and want to create objects and export them before processing events then you must call

```
BOA.impl_is_ready(<serverName>, 0)
```

before creating any objects. This contacts the daemon, finds out what port the persistent server is expected to be listening on and makes sure that all the created objects contain the correct port number.

## Interface `IE.Iona.OrbixWeb.CORBA.BOA`

---

Persistent servers, once they have called `impl_is_ready()`, behave as shared activation mode servers. The `serverName` specified must match an unused registered server name or an exception is raised.

If a server is registered as unshared or per-method, `impl_is_ready()` fails if the server is launched manually.

Normally you must register a server in the Implementation Repository before it can call `impl_is_ready()`. However, if you specify the `-u` switch to the Orbix Java daemon, a persistent server can call `impl_is_ready()` without being registered in the Implementation Repository. Refer to the *Orbix Programmer's Guide Java Edition* for more information on unregistered servers.

### Parameters

`serverName`      The `serverName` parameter is optional if the server is launched by Orbix Java. It is mandatory if the server is launched manually or externally to Orbix Java. You should always pass `serverName` explicitly.

If the `serverName` parameter is specified, it must match exactly the server name in the Implementation Repository.

`timeOut` Indicates the number of milliseconds to wait between events. A timeout occurs if Orbix Java waits longer than the specified timeout for the next event.

A timeout of zero indicates that `impl_is_ready()` should process one event, presuming that there is one pending, and then return immediately.

A timeout does not cause `impl_is_ready()` to raise an exception.

The default timeout can be passed explicitly as `getConfigItem("IT_DEFAULT_TIMEOUT")`.

An infinite timeout can be specified by using `getConfigItem("IT_INFINITE_TIMEOUT")`.

The `timeOut` parameter is meaningless for the per-method call activation mode, since the server terminates once the operation call that caused it to be launched has completed.

Calling `BOA.setNoHangup(true)` changes the time out behaviour of `impl_is_ready()`. Instead of timing out after an elapsed period between events it times out after an elapsed period between client connections. For more details see `BOA.setNoHangup()`.

**Notes** CORBA-defined.

**See Also**

- “`deactivate_impl()`” on page 108
- “`connect()`” on page 104
- “`obj_is_ready()`” on page 121
- “`processEvents()`” on page 122
- “`setNoHangup()`” on page 127
- “`setServerName()`” on page 128
- “`getConfigItem()`” on page 206

### **`isEventPending()`**

**Synopsis**

```
public boolean isEventPending()
 throws org.omg.CORBA.SystemException;
```

**Description**

Tests if there is an outstanding event waiting in the Orbix Java event queue. If it returns `true`, a subsequent call to `BOA.processNextEvent()`, `BOA.processEvents()` or `BOA.impl_is_ready()` removes the event from the event queue and processes it.

`isEventPending()` is normally used with `BOA.processNextEvent()` and `BOA.processEvents()` rather than with `impl_is_ready()`.

### **Return Value**

`true`    There is an event pending.  
`false`    There is no event pending.

**Notes**            PROGRESS-specific.

**See Also**

- “`impl_is_ready()`” on page 114
- “`processEvents()`” on page 122
- “`processNextEvent()`” on page 125

### **`myActivationMode()`**

**Synopsis**

```
public short myActivationMode()
 throws org.omg.CORBA.SystemException;
```

**Description**

Determines the primary activation mode with which the server was launched: shared, unshared, persistent, or per-method.

For more information on activation modes see the chapter “Registration and Activation of Servers” in the *Orbix Programmer's Guide Java Edition* .

**Return Value** Returns one of the following values:

|                                       |                                                                          |
|---------------------------------------|--------------------------------------------------------------------------|
| <code>persistentActivationMode</code> | Indicates that the server was launched manually.                         |
| <code>sharedActivationMode</code>     | Indicates that the server was automatically launched in shared mode.     |
| <code>unsharedActivationMode</code>   | Indicates that the server was automatically launched in unshared mode.   |
| <code>perMethodActivationMode</code>  | Indicates that the server was automatically launched in per-method mode. |
| <code>unknownActivationMode</code>    | Orbix Java cannot determine the mode in which the server was launched.   |

**Notes** PROGRESS-specific.

### **myHost()**

**Synopsis**

```
public java.lang.String myHost()
 throws org.omg.CORBA.SystemException;
```

**Description**

If proxy servers are enabled, returns the proxy server host name.

Otherwise, if the variable `IT_IORS_USE_DNS` is set to `false`, it returns the IP address of the local host.

If the variable `IT_IORS_USE_DNS` has been set to `true`, it returns the local host name. Refer to the `IT_IORS_USE_DNS` configuration parameter in the *Orbix Administrator's Guide Java Edition* for more details.

- Notes** PROGRESS-specific.
- See Also** “enableProxyServer()” on page 111  
“setProxyServer()” on page 128

### **myHostIP()**

- Synopsis**

```
public java.lang.String myHostIP()
 throws org.omg.CORBA.SystemException;
```
- Description** Returns the local host’s IP address.  
If the proxy server has been enabled, returns the IP address of the proxy server.
- Notes** PROGRESS-specific.
- See Also** “enableProxyServer()” on page 111  
“setProxyServer()” on page 128

### **myImplementationName()**

- Synopsis**

```
public java.lang.String myImplementationName()
 throws org.omg.CORBA.SystemException;
```
- Description** Returns the server name.  
For automatically launched servers, this name is passed to the server by the daemon. It is same name as that with which the server is registered in the Implementation Repository.  
For a persistent server, the contents of the string are undefined until `CORBA.BOA.impl_is_ready()`, `CORBA.BOA.obj_is_ready()` or `CORBA.ORB.setServerName()` is called.
- Notes** PROGRESS-specific.
- See Also** “impl\_is\_ready()” on page 114  
“setServerName()” on page 128

### **myMarkerName()**

- Synopsis**      `public java.lang.String myMarkerName()  
                  throws org.omg.CORBA.SystemException;`
- Description**    Returns the marker name of the activation object that caused the server to be launched. For a persistent or a per-method server, this is `null`.
- Notes**          PROGRESS-specific.
- See Also**      “myMarkerPattern()” on page 120

### **myMarkerPattern()**

- Synopsis**      `public java.lang.String myMarkerPattern()  
                  throws org.omg.CORBA.SystemException;`
- Description**    Returns the marker pattern which the activation object matched in the Implementation Repository and caused this server to be launched.  
  
For a persistent or per-method server, this is `null`.
- Notes**          PROGRESS-specific.
- See Also**      “myMarkerName()” on page 120

### **myMethodName()**

- Synopsis**      `public java.lang.String myMethodName()  
                  throws org.omg.CORBA.SystemException;`
- Description**    Returns the name of the method that caused the server to be launched. For a server not launched on a per-method basis this is `null`.
- Notes**          PROGRESS-specific.



### **numClientsConnected()**

**Synopsis**

```
public int numClientsConnected()
 throws org.omg.CORBA.SystemException;
```

**Description**

Returns the number of clients that are currently connected to the server.

This acts differently if the server is launched as a thread in the thread-per-server mode with the `orbixdj`. In this case the call determines the number of classes in the process, and not just whether those connections are only used by the server thread that made the call.

**Notes**

PROGRESS-specific.

### **obj\_is\_ready()**

**Synopsis**

```
public void obj_is_ready (org.omg.CORBA.Object obj,
 java.lang.String impl,
 int timeOut)
 throws org.omg.CORBA.SystemException;
public void obj_is_ready (org.omg.CORBA.Object obj,
 String impl)
 throws SystemException;
```

**Description**

A server running in the unshared activation mode (with one registered object per process) can call the `BOA.obj_is_ready()` method on the `_CORBA.Orbix` object to indicate that it has completed its initialization. The server remains active and receives requests for its registered object until:

- It calls `BOA.deactivate_obj()`.
- The call to `obj_is_ready()` times out.
- An exception is raised while waiting for events.

**Parameters**

|                   |                                                |
|-------------------|------------------------------------------------|
| <code>obj</code>  | The registered object that the server manages. |
| <code>impl</code> | The server name.                               |

`timeOut` The timeout period. A server can time out either because it has no clients for the timeout duration, or because none of its clients uses it for that period.

The default timeout can be passed explicitly as

```
_OrbixWeb.ORB(ORB.init()).getConfigItem("IT_DEFAULT_TIMEOUT").
```

An infinite timeout can be specified by passing

```
_OrbixWeb.ORB(ORB.init()).getConfigItem("IT_INFINITE_TIMEOUT").
```

Calling `BOA.setNoHangup(true)` changes the time out behaviour of `obj_is_ready()`. Instead of timing out after an elapsed period between events it times out after an elapsed period between client connections. For more details see `BOA.setNoHangup()`.

**Notes** CORBA-defined.

**See Also** “deactivate\_obj()” on page 108  
“impl\_is\_ready()” on page 114  
“setNoHangup()” on page 127

### processEvents()

**Synopsis**

```
public int processEvents()
 throws org.omg.CORBA.SystemException;
public int processEvents(int timeOut)
 throws org.omg.CORBA.SystemException;
```

**Description**

If a zero timeout period is given to `BOA.impl_is_ready()` or `BOA.obj_is_ready()`, the call returns immediately—allowing a program to subsequently state at what points it is willing to accept incoming Orbix Java events.

There are three kinds of event:

- ◆ Operation requests
- ◆ Connections from clients
- ◆ Disconnections of clients

The method `processEvents()` blocks the server until an event arrives, handles the event, and continues to process events, until none arrives within the timeout period. It has the same effect as calling `BOA.processNextEvent()` repeatedly until it times out.

The method `processEvents()` is similar in functionality to `impl_is_ready()` (or `obj_is_ready()`) because it processes any number of events until it times out. However, use of `processEvents()` does not initialize the server and therefore does not fulfil a server's requirement to call `impl_is_ready()` (or `obj_is_ready()`).

One example of using `processEvents()` is where a manually launched server wishes to interact with Orbix Java (for example, by calling a remote operation or by passing out or allowing clients to connect to it) before it is ready to handle incoming events from clients.

Before it interacts with Orbix Java, it must call `impl_is_ready()` (or `obj_is_ready()`) with a zero timeout thereby initializing the server and allowing clients to connect. The server can then do whatever other initialization work must be done and calls `processEvents()` when it is ready to handle incoming events from clients.

### Parameters

`timeOut` Indicates the number of milliseconds to wait between events; a timeout occurs if Orbix Java waits longer than the specified timeout for the next event.

A timeout of zero indicates that `processEvents()` should process one event (presuming that there is one pending) and then return immediately.

A timeout does not cause `processEvents()` to raise an exception.

The default timeout can be passed explicitly as `_OrbixWeb.ORB(ORB.init()).getConfigItem("IT_DEFAULT_TIMEOUT")`.

An infinite timeout can be specified by passing `_OrbixWeb.ORB(ORB.init()).getConfigItem("IT_INFINITE_TIMEOUT")`.

Calling `BOA.setNoHangup(true)` changes the time out behaviour of `processEvents()`. Instead of timing out after an elapsed period between events it times out after an elapsed period between client connections. For more details see “`setNoHangup()`” on page 127.

**Return Value** Always returns 1.

**Notes** PROGRESS-specific.

**See Also** “`impl_is_ready()`” on page 114  
“`obj_is_ready()`” on page 121  
“`processNextEvent()`” on page 125  
“`setServerName()`” on page 128  
“`getConfigItem()`” on page 206

### **processNextEvent()**

#### **Synopsis**

```
public void processNextEvent ()
 throws org.omg.CORBA.SystemException;
public void processNextEvent(int timeout)
 throws org.omg.CORBA.SystemException;
```

#### **Description**

A programmer may want more control over the handling of events in a server.

There are three kinds of events:

- ◆ Operation requests
- ◆ Connections from clients
- ◆ Disconnections of clients

This method blocks the server until an event arrives, handles that one event, and normally returns zero.

If a zero timeout period is given to `BOA.impl_is_ready()` or `BOA.obj_is_ready()`, the server initializes and returns immediately. This allows a program to subsequently state at what point it is willing to accept incoming Orbix Java events. This can be done by calling `_CORBA.Orbix.processNextEvent()`.

### Parameters

`timeOut` Indicates the number of milliseconds to wait for an event; a timeout occurs if Orbix Java waits longer than the specified timeout for the next event.

A timeout of zero indicates that `processNextEvent()` should process one event (presuming that there is one pending) and then return immediately.

A timeout causes `processNextEvent()` to return 1.

The default timeout can be passed explicitly as `_OrbixWeb.ORB(ORB.init()).getConfigItem("IT_DEFAULT_TIMEOUT")`.

An infinite timeout can be specified by passing `_OrbixWeb.ORB(ORB.init()).getConfigItem("IT_INFINITE_TIMEOUT")`.

Calling `BOA.setNoHangup(true)` changes the time out behaviour of `processNextEvent()`. Instead of timing out after an elapsed period between events it times out after an elapsed period between client connections. For more details see "`setNoHangup()`" on page 127.

**Return** Normally returns 0 (false). Returns 1 (true) if the server has been deactivated or if the call to `processNextEvent()` times out.

**Notes** PROGRESS-specific.

**See Also** "`impl_is_ready()`" on page 114  
"`obj_is_ready()`" on page 121  
"`processNextEvent()`" on page 125  
"`setServerName()`" on page 128  
"`getConfigItem()`" on page 206

### setNoHangup()

**Synopsis**

```
public boolean setNoHangup(boolean b)
 throws org.omg.CORBA.SystemException;
```

**Description**

By default, the `BOA.impl_is_ready()`, `BOA.obj_is_ready()`, `BOA.processEvents()` and `BOA.processNextEvent()` methods time out when a (user-defined or default) time period has elapsed between events. An event is an incoming operation call, or the connection or disconnection by a client.

This means that the methods mentioned above can timeout when clients are still connected but have been idle for a period of time. If you want a server to remain active while it has any clients connected, active or not, call the function `setNoHangup(true)` on the `_CORBA.Orbix` object.

**Parameters**

- b        When `true` is passed as the parameter, the timeout period to `impl_is_ready()`, `obj_is_ready()`, `processEvents()`, and `processNextEvent()` specifies the amount of time a server waits while there are no client connections to it. The event handler does not time out until all clients are disconnected.

When `false` is passed as the parameter, the timeout period to `impl_is_ready()`, `obj_is_ready()`, `processEvents()`, and `processNextEvent()` specifies the amount of time a server waits while there are no events (operation calls, connections, disconnections). These calls time out if the specified period elapses between events.

The default setting is `false`.

**Return Value**

Returns the previously set value.

**Notes**

PROGRESS-specific.

**See Also**

“`impl_is_ready()`” on page 114  
“`processEvents()`” on page 122  
“`processNextEvent()`” on page 125

### setProxyServer()

**Synopsis**

```
public synchronized void setProxyServer(java.lang.String host,
 int port)
 throws org.omg.CORBA.SystemException;
```

**Description**

This method is provided for supporting the Wonderwall firewall product.

It sets the values for the host name and port number for the proxy server (Wonderwall).

If `BOA.enableProxyServer()` is set to `true`, any CORBA objects created contain the host name and port number as specified by this method.

Refer to the *Wonderwall Administrator's Guide* for full details of how to use this method.

**Parameters**

- `host`    The name of the host on which your firewall proxy server (Wonderwall) is running.
- `port`    The port number on which your firewall proxy server (Wonderwall) is listening.

**Notes**

PROGRESS-specific.

**See Also**

“enableProxyServer()” on page 111

### setServerName()

**Synopsis**

```
public synchronized void setServerName
 (java.lang.String serverName)
 throws org.omg.CORBA.SystemException;
```

**Description**

Sets the server name for the current server.

**Notes**

PROGRESS-specific.

**See Also**

“change\_implementation()” on page 103

“impl\_is\_ready()” on page 114

“myImplementationName()” on page 119



### **shutdown()**

- Synopsis** `public void shutdown(wait_for_completion);`
- Description** Shuts down the BOA and ORB when called on an ORB instance. The `wait_for_completion` flag is not currently supported by Orbix Java and can be ignored.
- Notes** PROGRESS-specific.
- See Also** “finalize()” on page 205  
“Class `IE.Iona.OrbixWeb.Features.LoaderClass`” on page 319

### **toString()**

- Synopsis** `public java.lang.String toString();`
- Description** This method can be used to check if the `_CORBA.Orbix` object is an ORB or BOA object.
- Return Value** Returns the string “`IE.Iona.OrbixWeb.CORBA.BOA`”.
- Notes** PROGRESS-specific.
- See Also** “toString()” on page 235

## Class IE.Iona.OrbixWeb.CORBA.Context

### Synopsis

The Java class `Context` implements the OMG pseudo-interface `Context`. A context is intended to represent information about the client that is inconvenient to pass via parameters.

An IDL operation can specify that a `Context` is to be provided with the client's mapping for particular identifiers (properties)—it does this by listing these identifiers following the operation declaration in a `context` clause. An IDL operation that specifies a `context` clause is mapped to a Java method that takes an extra input parameter of type `org.omg.CORBA.Context`, at the end of the parameter list. A client can optionally maintain one or more `Context` objects, which provide a mapping from identifiers (string names) to string values. A `Context` object contains a list of properties; each property consists of a name and a string value associated with that name and can be passed to a method that takes a `Context` parameter.

You can arrange `Contexts` in a hierarchy by specifying parent-child relationships among them. In this case, a child passed to an operation also includes the identifiers of its parent(s). The called operation can decide whether to use just the context actually passed, or the hierarchy above it.

---

**Note:** The use of the `Context` constructor has been deprecated in Orbix Java. You should use the `IT_create` static methods instead.

---

### CORBA

```
// Pseudo IDL

pseudo interface Context {
 readonly attribute Identifier context_name;
 readonly attribute Context parent;

 Context create_child(
 in Identifier child_ctx_name);

 void set_one value(
 in Identifier propname, in any propvalue);
 void set_values(in NVList values);
 void delete_values(in Identifier propname);
```

## Class IE.Iona.OrbixWeb.CORBA.Context

---

```
 NVList get_values(in Identifier start_scope,
 in Flags op_flags,
 in Identifier pattern);
};
```

### Orbix Java

```
// Java

package IE.Iona.OrbixWeb.CORBA;

public class Context extends org.omg.CORBA.Context{
 // Constructors
 public Context();
 public Context(String name);
 public Context(Context parent);
 public Context(String name, Context parent);

 // Methods
 public org.omg.CORBA.Context create_child(String
 child_ctx_name)
 throws SystemException;
 public void delete_values(String prop_name)
 throws SystemException;
 public org.omg.CORBA.NVList get_values(
 String start_scope,
 Flags op_flags, String prop_name)
 throws SystemException;
 public void set_one_value(String prop_name,
 org.omg.CORBA.Any val)
 throws SystemException;

 public void set_values(org.omg.CORBA.NVList vals);
 throws SystemException;
 public String toString();
 throws SystemException;
 public java.lang.Object clone();
 throws SystemException;
 public boolean equals(java.lang.Object _obj);
 throws SystemException;

 // Object Methods
 public static Context IT_create();
 throws SystemException;
```

```
public static Context IT_create(String name);
 throws SystemException;
public static Context IT_create(Context parent);
 throws SystemException;
public static Context IT_create(String name,
 Context parent);
 throws SystemException;
public static Context _nil();
 throws SystemException;

// Data Accessor Methods
public String context_name();
 throws SystemException;
public Context parent();
 throws SystemException;
public int get_count();
 throws SystemException;
public int get_count_all();
 throws SystemException;
}
```

**See Also**      “Class IE.Iona.OrbixWeb.CORBA.ContextIterator” on page 142  
                 “Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158

### **Context()**

**Synopsis**      `public Context();`

**Description**      Creates a new context that is not a child context.

**Notes**      PROGRESS-specific.

**See Also**      “create\_child()” on page 134  
                 “IT\_create()” on page 137  
                 Other Context constructors.

### **Context()**

**Synopsis**      `public Context(String name);`

**Description**      Creates a new context (not a child context) with a specified name.

### Parameters

`name`                      The name of the context.

**Notes**                      PROGRESS-specific.

**See Also**                    “`create_child()`” on page 134  
“`IT_create()`” on page 137  
Other `Context` constructors.

### **Context()**

**Synopsis**                    `public Context(Context parent);`

**Description**                Creates a new child context.

### Parameters

`parent`                      The parent context.

**Notes**                      PROGRESS-specific.

**See Also**                    “`create_child()`” on page 134  
“`IT_create()`” on page 137  
Other `Context` constructors.

### **Context()**

**Synopsis**                    `public Context(String name, Context parent);`

**Description**                Creates a new child context with a specified name.

### Parameters

`name`                        The name of the context.

`parent`                      The parent context.

**Notes**                      PROGRESS-specific.

**See Also**       “create\_child()” on page 134  
                  “IT\_create()” on page 137  
                  Other Context constructors.

### **`_nil()`**

**Synopsis**       public Static Context \_nil();  
**Description**   Returns a nil object reference for a Context object.  
**Notes**         PROGRESS-specific.

### **`context_name()`**

**Synopsis**       public String context\_name();  
**Description**   Returns the name of the Context object.  
**Notes**         CORBA-defined.  
**See Also**     “create\_child()” on page 134

### **`create_child()`**

**Synopsis**       public org.omg.CORBA.Context create\_child(String  
                  child\_ctx\_name);  
**Description**   Creates a child context of the current context. When a child context is passed as a parameter to an operation, any searches (using `IE.Iona.OrbixWeb.CORBA.Context.get_values()`) look in parent contexts if necessary to find matching property names.

#### **Parameters**

|                       |                                                                                           |
|-----------------------|-------------------------------------------------------------------------------------------|
| <code>ctx_name</code> | The name of the child context. Context object names follow the rules for IDL identifiers. |
|-----------------------|-------------------------------------------------------------------------------------------|

#### **Return Value**

|         |                            |
|---------|----------------------------|
| Context | The newly-created Context. |
|---------|----------------------------|

**Notes** CORBA-defined.

**See Also** “get\_values()” on page 136

### **delete\_values()**

**Synopsis**

```
public void delete_values(String prop_name)
 throws SystemException;
```

**Description** Deletes the specified property value(s) from the context. The search scope is limited to the Context object on which the invocation is made.

#### **Parameters**

|           |                                                                                                        |
|-----------|--------------------------------------------------------------------------------------------------------|
| prop_name | The property name to be deleted. If prop_name has a trailing ‘*’, all matching properties are deleted. |
|-----------|--------------------------------------------------------------------------------------------------------|

**Notes** CORBA-defined.

### **get\_count()**

**Synopsis**

```
public int get_count();
```

**Description** Finds the number of properties/value pairs in the context.

**Notes** PROGRESS-specific.

**See Also** “get\_count\_all()” on page 135

### **get\_count\_all()**

**Synopsis**

```
public int get_count_all();
```

**Description** Finds the number of properties/value pairs in this context and all its parent contexts.

**Notes** PROGRESS-specific.

**See Also** “get\_count()” on page 135

### **get\_values()**

**Synopsis**

```
public org.omg.CORBA.NVList get_values(
 String start_scope,
 int op_flags, String prop_name);
```

**Description**

Retrieves the specified context property values.

**Parameters**

|                          |                                                                                                                                                                                                                                                                |
|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>start_scope</code> | The context in which the search for the values requested should be started. The name of a direct or indirect parent context may be specified to this parameter. If the null string is passed, the search begins in the context that is the target of the call. |
| <code>op_flags</code>    | By default, searching propagates upwards to parent contexts; if <code>_CORBA.CTX_RESTRICT_SCOPE</code> is specified, searching is limited to the specified search scope or context object.                                                                     |
| <code>prop_name</code>   | If <code>prop_name</code> has a trailing '*', all matching properties and their values are returned.                                                                                                                                                           |

**Return Value**

`NVList` An `NVList` object to contain the returned property values.

**Notes**

CORBA-defined.

**See Also**

"Class `IE.Iona.OrbixWeb.CORBA.NVList`" on page 158



### IT\_create()

**Synopsis**

```
public static Context IT_create();
public static Context IT_create(String name);
public static Context IT_create(Context parent);
public static Context IT_create(String name, Context parent);
```

**Description**

In the absence of a CORBA specified way to create a (top level) `Context` pseudo object, Orbix Java provides the `IT_create()` method to initialize an object reference for a `Context`.

Use of this method is recommended in preference to Java `new` to ensure portability across future Orbix Java versions.

**Parameters**

|                     |                          |
|---------------------|--------------------------|
| <code>name</code>   | The name of the context. |
| <code>parent</code> | The parent context.      |

**Notes**

PROGRESS-specific.

**See Also**

“`create_child()`” on page 134  
Other `Context` constructors.

### parent()

**Synopsis**

```
public Context parent();
```

**Description**

Returns the parent of the `Context` object.

**Notes**

CORBA-defined.

**See Also**

“`create_child()`” on page 134

### set\_one\_value()

**Synopsis**

```
public void set_one_value(String prop_name,
 org.omg.CORBA.Any val);
```

**Description**

Adds property name and value to context. Although the `value` member is of type `Any`, the type of the `Any` must be a string.

### Parameters

|                        |                                   |
|------------------------|-----------------------------------|
| <code>prop_name</code> | The name of the property to add.  |
| <code>val</code>       | The value of the property to add. |

**Notes** CORBA-defined.

**See Also** “`set_values()`” on page 138

### **set\_values()**

**Synopsis** `public void set_values(org.omg.CORBA.NVList vals);`

**Description** Sets one or more property values in the context. The previous value of the property, if any, is discarded.

### Parameters

|                     |                                                                                                                                                                                                                                                                                    |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>values</code> | An <code>NVList</code> containing the <code>property_name:values</code> to add or change. In the <code>NVList</code> , the <code>flags</code> field must be set to zero, and the <code>TypeCode</code> associated with an attribute value must be <code>_CORBA._tc_string</code> . |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Notes** CORBA-defined.

**See Also** “`set_one_value()`” on page 137

## Class IE.Iona.OrbixWeb.CORBA.ContextList

**Synopsis** The Java class `ContextList` implements the CORBA pseudo-object type `ContextList`. A `ContextList` is used in the DII to describe the context strings required for a particular operation. The list stores them as `Context` objects.

Refer to the chapter “Dynamic Invocation Interface” in the *Orbix Programmer’s Guide Java Edition* for further details.

**CORBA** `// Pseudo IDL`

```
pseudo interface ContextList {
 readonly attribute unsigned long count;
 void add(in string ctx);
 string item(in unsigned long index) raises (CORBA::Bounds);
 void remove(in unsigned long index) raises (CORBA::Bounds);
};
```

**Orbix Java** `// Java`

```
public class ContextList extends org.omg.CORBA.ContextList
{
 public ContextList()

 public int count();
 public void add(java.lang.String ctx)
 throws org.omg.CORBA.SystemException;
 public java.lang.String item(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
 public void remove(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
}
```

**Notes** CORBA-defined.

**See Also** “contexts()” on page 256  
“Class org.omg.CORBA.Context” on page 35  
“Class IE.Iona.OrbixWeb.CORBA.Context” on page 130

### ContextList()

- Synopsis**      `public ContextList();`
- Description**      Default constructor.
- Notes**      PROGRESS-specific. See `org.omg.CORBA.ORB.create_context_list()` for CORBA-defined ways to create a `ContextList`.
- See Also**      “Class `org.omg.CORBA.ORB`” on page 46

### add()

- Synopsis**      `public void add(java.lang.String ctx)`  
                  throws `org.omg.CORBA.SystemException;`
- Description**      Uses `ctx` to create an `org.omg.CORBA.Context` object and adds that object to the end of the list of contexts.
- Parameters**
- |                  |                                                                         |
|------------------|-------------------------------------------------------------------------|
| <code>ctx</code> | A string describing the variable or pattern the context should contain. |
|------------------|-------------------------------------------------------------------------|
- Notes**      CORBA-defined.

### count()

- Synopsis**      `public int count() throws org.omg.CORBA.SystemException;`
- Description**      Returns the number of elements in the `ContextList`.
- Return Value**
- |                  |                                 |
|------------------|---------------------------------|
| <code>int</code> | Number of elements in the list. |
|------------------|---------------------------------|
- Notes**      CORBA-defined.

### item()

**Synopsis**

```
public java.lang.String item(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
```

**Description**

Returns the item at the given index. The first item is at index 0.

**Parameters**

index                      Position within list to be returned.

**Return Value**

java.lang.String          The string identifier for the context at index.

**Notes**

CORBA-defined.

### remove()

**Synopsis**

```
public void remove(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
```

**Description**

Removes the item at the given index. The first item is at index 0.

**Parameters**

index                      The position within the list of the item to be removed.

**Notes**

CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.ContextIterator

**Synopsis** Class ContextIterator defines a Java iterator class for Context.

**Orbix Java**

```
public class ContextIterator {
 public ContextIterator() throws org.omg.CORBA.SystemException;
 public ContextIterator(org.omg.CORBA.Context ctx)
 throws org.omg.CORBA.SystemException;

 public void setList org.omg.CORBA.Context ctx)
 throws org.omg.CORBA.SystemException;
 public String next() throws org.omg.CORBA.SystemException;
};
```

**Notes** PROGRESS-specific.

**See also** “Class org.omg.CORBA.Context” on page 35  
“Class org.omg.CORBA.ContextList” on page 37  
“Class IE.Iona.OrbixWeb.CORBA.Context” on page 130

### ContextIterator()

**Synopsis** public ContextIterator() throws org.omg.CORBA.SystemException;

**Description** Constructor. Creates an iterator without specifying which context object the iterator uses to traverse. You can use the method “setList ()” subsequently to set the context object.

**Notes** PROGRESS-specific.

**See Also** “setList()” on page 143

### ContextIterator()

**Synopsis**      `public ContextIterator(org.omg.CORBA.Context ctx)`  
                  throws `org.omg.CORBA.SystemException;`

**Description**      Constructor. Creates an iterator for context `ctx`.

**Parameters**

`ctx`                      A context object.

**Notes**              PROGRESS-specific.

### next()

**Synopsis**      `public String next() throws org.omg.CORBA.SystemException;`

**Description**      Returns the next item in the list or `null` if at the end. The  $i^{\text{th}}$  call returns the property name and the  $i+1^{\text{th}}$  call returns the property value within the Context.

**Return Value**

`String`                      Property name or property value.

**Notes**              PROGRESS-specific.

### setList()

**Synopsis**      `public void setList(org.omg.CORBA.Context ctx)`  
                  throws `org.omg.CORBA.SystemException;`

**Description**      If a context object has not been specified for the iterator, you can use this method to set the context object. If a context object has been set, you can use this method to replace the context object (if the `ctx` parameter is not the current context) or to reset the iterator position for the current context (if the `ctx` parameter is the current context).

### Parameters

`ctx`

Either a new context, in which case this becomes the context to be traversed by the iterator, or the current context in which case the iterator is reset.

### Notes

PROGRESS-specific.



## Class IE.Iona.OrbixWeb.CORBA.Environment

**Synopsis** The `Environment` class provides a vehicle for dealing with exceptions in those cases where true exception mechanics are unavailable or undesirable.

For example, in the DII exceptions raised by remote invocation are stored in an `Environment` member variable in the `Request` object after the invocation returns. DII clients should test the value of this `Environment` variable by calling the `env()` method on the `Request` object. If the returned `java.lang.Exception` is `null`, no exception was raised. If it is not `null`, the returned exception should be examined and acted on in an appropriate manner.

Refer to the chapter "Dynamic Invocation Interface" in the *Orbix Programmer's Guide Java Edition* for more details.

**Orbix Java**

```
// Java

package IE.Iona.OrbixWeb.CORBA;

public class Environment
 extends org.omg.CORBA.Environment {

 void exception(java.lang.Exception except);
 java.lang.Exception exception();
 void clear();
};
```

**Notes** CORBA-defined

**See Also** "Class `org.omg.CORBA.Request`" on page 59

### **exception()**

**Synopsis** `public void exception(java.lang.Exception except);`

**Description** Sets the exception member variable in the `Environment` object to `except`.

**Notes** CORBA-defined.

### **exception()**

- Synopsis**      `public java.lang.Exception exception();`
- Description**      Extracts the exception contained in the `Environment` object.
- Return Value**
- `java.lang.Exception`      The returned exception.
- Notes**              CORBA-defined.

### **clear()**

- Synopsis**      `public void clear();`
- Description**      Sets the exception contained within the `Environment` object to null.
- Notes**              CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.ExceptionList

**Synopsis** The Java class `ExceptionList` implements the CORBA pseudo-object type `ExceptionList`. An `ExceptionList` is used in the DII to describe the exceptions that can be raised by IDL operations. It maintains a modifiable list of `Typecodes`. See the "Dynamic Invocation Interface" chapter in the *Orbix Programmer's Guide Java Edition* for more details.

**CORBA**

```
// Pseudo IDL

pseudo interface ExceptionList {
 readonly attribute unsigned long count;
 void add(in Typecode exc);
 TypeCode item(in unsigned long index) raises (CORBA::Bounds);
 void remove(in unsigned long index) raises (CORBA::Bounds);
};
```

**Orbix Java**

```
// Java
public class ExceptionList extends org.omg.CORBA.ExceptionList
{
 public ExceptionList();

 public int count();
 public void add(TypeCode exc)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.TypeCode item(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
 public void remove(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
}
```

**Notes** CORBA-defined.

**See Also** "exceptions()" on page 259  
"\_create\_request()" on page 170  
"Class IE.Iona.OrbixWeb.CORBA.TypeCode" on page 279

### ExceptionList()

- Synopsis** `public ExceptionList();`
- Description** Default constructor.
- Notes** PROGRESS-specific. See `create_exception_list()` in "Class `org.omg.CORBA.ORB`" for CORBA-defined ways to create an `ExceptionList`.
- See Also** "Class `org.omg.CORBA.ORB`" on page 46

### add()

- Synopsis** `public void add(org.omg.CORBA.TypeCode exc)  
throws org.omg.CORBA.SystemException;`
- Description** Adds `exc` to the end of the list of exception `TypeCodes`.
- Parameters**
- |                  |                                                                                                        |
|------------------|--------------------------------------------------------------------------------------------------------|
| <code>exc</code> | The <code>TypeCode</code> to be added to the list. Should be a <code>TypeCode</code> for an exception. |
|------------------|--------------------------------------------------------------------------------------------------------|
- Notes** CORBA-defined.

### count()

- Synopsis** `public int count() throws org.omg.CORBA.SystemException;`
- Description** Returns the number of elements in the `ExceptionList`.
- Return Value**
- |                  |                                 |
|------------------|---------------------------------|
| <code>int</code> | Number of elements in the list. |
|------------------|---------------------------------|
- Notes** CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.ExceptionList

---

### item()

**Synopsis**

```
public org.omg.CORBA.TypeCode item(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
```

**Description**

Returns the item at the given index. The first item is at index 0.

**Parameters**

index                      Position within list to be returned.

**Return Value**

TypeCode                      The item at the position specified by index.

**Notes**

CORBA-defined.

### remove()

**Synopsis**

```
public void remove(int index)
 throws org.omg.CORBA.Bounds,
 org.omg.CORBA.SystemException;
```

**Description**

Removes the item at the given index. The first item is at index 0.

**Parameters**

index                      The position within the list of the item to be removed.

**Notes**

CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.InitService

**Synopsis** The `InitService` class is responsible for maintaining a set of IORs (Interoperable Object References) that you can retrieve by calling `ORB.resolve_initial_references()`. The `InitService` class can be useful for example, if you need to access more than one Naming Service host from the same client, and you do not want to use a federated Naming Service.

**Orbix Java**

```
// Java

public class InitService {

 // Constructor
 public InitService(ORB);

 // Methods
 public static void initialise();;
 ...
}
```

**Notes** PROGRESS-specific.

**See Also** "Class IE.Iona.OrbixWeb.CORBA.ORB "on page 184

### **InitService()**

**Synopsis** `public InitService(ORB orb);`

**Description** The default constructor. Takes the specified ORB as a parameter, enabling support for multiple ORBs.

**Notes** PROGRESS-specific.

### **initialise()**

**Synopsis**

```
public synchronized void initialise(ORB orb);
```

**Description**

Initializes the IORs for each service (for example, the Naming Service or the Trading Object Service) for the nominated ORB. It uses configuration information such as `IT_NS_HOSTNAME` and `IT_NS_PORT` when creating these IORs.

This method can be useful for example, if you wish to run two mirrored (not federated) NS hosts. While the client is running it can substitute “backup” configuration into the `IT_NS_HOSTNAME` and `IT_NS_PORT` configuration parameters using `setConfigItem()`. The client can then call `resolve_initial_references()` again to update the IOR to point to the backup NS.

Having to create a new ORB in this situation is not always ideal. The existing client ORB may already have other session information (for example, connections to servers, loaders, filters) that the client does not want to lose in the event that the NS fails.

**Notes**

PROGRESS-specific.

**See Also**

*Orbix Administrator's Guide Java Edition*

"Class IE.Iona.OrbixWeb.Features.OrbConfig " on page 330

# Class IE.Iona.OrbixWeb.CORBA.NamedValue

**Synopsis** The Java class `NamedValue` implements the IDL pseudo-object type `NamedValue` that is used only as an element of an `NVList`, chiefly in the DII. A `NamedValue` describes a parameter to a `Request`. It contains an optional name, an any value and labelling flags.

**CORBA** // Pseudo IDL

```
pseudo interface NamedValue {
 readonly attribute Identifier name;
 readonly attribute any value;
 readonly attribute Flags flags;
};
```

**Orbix Java** // Java

```
public class NamedValue extends org.omg.CORBA.NamedValue
 implements java.lang.Cloneable
{
 // Constructors
 public NamedValue() throws org.omg.CORBA.SystemException;
 public NamedValue(String name, org.omg.CORBA.Any value,
 int arg_modes)
 throws org.omg.CORBA.SystemException;
 public NamedValue(NamedValue nv)
 throws org.omg.CORBA.SystemException;

 // Methods
 public java.lang.Object clone()
 throws org.omg.CORBA.SystemException;
 public boolean equals(java.lang.Object _obj)
 throws org.omg.CORBA.SystemException;
 public String toString() throws org.omg.CORBA.SystemException;
```



## Class IE.Iona.OrbixWeb.CORBA.NamedValue

---

```
// Data Accessor Methods
public String name() throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any value()
 throws org.omg.CORBA.SystemException;
public int flags() throws org.omg.CORBA.SystemException;
public static NamedValue _nil()
 throws org.omg.CORBA.SystemException;
};
```

**Notes** CORBA-defined.

**See Also** “Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158  
“Class IE.Iona.OrbixWeb.CORBA.Request” on page 248

### NamedValue()

**Synopsis** public NamedValue() throws org.omg.CORBA.SystemException;

**Description** Default constructor.

**Notes** PROGRESS-specific.

**See Also** “add()” on page 161  
“add\_item()” on page 162  
“add\_value()” on page 162

### NamedValue()

**Synopsis** public NamedValue(String name, org.omg.CORBA.Any value,  
int arg\_modes) throws org.omg.CORBA.SystemException;

**Description** Constructor that supports the initialization of NamedValue member data with specified values.

### Parameters

|       |                                                                                                                                                  |
|-------|--------------------------------------------------------------------------------------------------------------------------------------------------|
| name  | Name associated with the <code>NamedValue</code> .                                                                                               |
| value | The object contained within the <code>NamedValue</code> .                                                                                        |
| modes | Parameter passing modes<br><code>org.omg.CORBA.ARG_IN</code> ,<br><code>org.omg.CORBA.ARG_OUT</code> ,<br><code>org.omg.CORBA.ARG_INOUT</code> . |

**Notes** PROGRESS-specific.

**See Also** “add()” on page 161  
“add\_item()” on page 162  
“add\_value()” on page 162

### **NamedValue()**

**Synopsis**

```
public NamedValue(NamedValue nv)
 throws org.omg.CORBA.SystemException;
```

**Description** Copy constructor.

### Parameters

|    |                                      |
|----|--------------------------------------|
| nv | The <code>NamedValue</code> to copy. |
|----|--------------------------------------|

**Notes** PROGRESS-specific.

**See Also** “add()” on page 161  
“add\_item()” on page 162  
“add\_value()” on page 162

### **clone()**

**Synopsis**

```
public java.lang.Object clone()
 throws org.omg.CORBA.SystemException;
```

**Description**

Copies the current `NamedValue` to a new `NamedValue` object and returns the new object.

**Notes**

PROGRESS-specific.

### **equals()**

**Synopsis**

```
public boolean equals(java.lang.Object _obj)
 throws org.omg.CORBA.SystemException;
```

**Description**

Compares the current `NamedValue` to parameter `_obj`. If `_obj` is not a `NamedValue` object or the name, flags, and value members of `_obj` are not equal to those of the current object, this method returns `false`; otherwise, it returns `true`.

**Parameters**

|                   |                                                                                               |
|-------------------|-----------------------------------------------------------------------------------------------|
| <code>_obj</code> | <code>NamedValue</code> object against which the current <code>NamedValue</code> is compared. |
|-------------------|-----------------------------------------------------------------------------------------------|

**Return Value**

|                      |                                                                       |
|----------------------|-----------------------------------------------------------------------|
| <code>boolean</code> | <code>true</code> if objects are equal; <code>false</code> otherwise. |
|----------------------|-----------------------------------------------------------------------|

**Notes**

PROGRESS-specific.

### **toString()**

**Synopsis** `public String toString() throws org.omg.CORBA.SystemException;`

**Description** Converts the name and value of the `NamedValue` object to a human-readable string of the form:

`<name>, <value>`

**Return Value**

`String` Human readable form of `NamedValue` object.

**Notes** PROGRESS-specific.

### **name()**

**Synopsis** `public String name() throws org.omg.CORBA.SystemException;`

**Description** Returns the (optional) name associated with the `NamedValue`. This is the name of a parameter or argument to a request.

**Notes** CORBA-defined.

### **value()**

**Synopsis** `public org.omg.CORBA.Any value()  
throws org.omg.CORBA.SystemException;`

**Description** Returns a reference to the `org.omg.CORBA.Any` object contained in the `NamedValue`.

**Return Value**

`Any` Reference to object contained in the `NamedValue`.

**Notes** CORBA-defined.

### **flags()**

**Synopsis** `public int flags() throws org.omg.CORBA.SystemException;`

**Description** Returns the parameter mode associated with the `NamedValue`.

**Return Value**

`int` Flags associated with the `NamedValue`.

**Notes** CORBA-defined.

**See Also** `org.omg.CORBA.Flags`

### **\_nil()**

**Synopsis** `public static NamedValue _nil()  
throws org.omg.CORBA.SystemException;`

**Description** Returns a nil object reference for a `NamedValue`.

**Notes** CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.NVList

**Synopsis** The Java class `NVList` implements the CORBA pseudo-object type `NVList`. An `NVList` is a list of `NamedValue` elements. A `NamedValue` describes an argument to a Request.

**CORBA**

```
// Pseudo IDL

pseudo interface NVList {
 readonly attribute unsigned long count;
 NamedValue add(in Flags flags);
 NamedValue add_item(in Identifier item_name, in Flags flags);
 NamedValue add_value(in Identifier item_name, in any val,
 in Flags flags);
 NamedValue item(in unsigned long index) raises (CORBA::Bounds);
 void remove(in unsigned long index) raises (CORBA::Bounds);
};
```

**Orbix Java**

```
// Java
public class NVList extends org.omg.CORBA.NVList
 implements java.lang.Cloneable {

 public NVList() throws org.omg.CORBA.SystemException;
 public NVList(int size)
 throws org.omg.CORBA.SystemException;
 public NVList(NVList nvl)
 throws org.omg.CORBA.SystemException;

 public boolean equals(java.lang.Object _obj)
 throws org.omg.CORBA.SystemException;
 public Object clone()
 throws org.omg.CORBA.SystemException;

 public org.omg.CORBA.NamedValue add(int item_flags)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.NamedValue add_item(String item_name,
 int item_flags)
 throws org.omg.CORBA.SystemException;
```

## Class IE.Iona.OrbixWeb.CORBA.NVList

---

```
public org.omg.CORBA.NamedValue add_value(
 String item_name,
 org.omg.CORBA.Any value,
 int item_flags)
 throws org.omg.CORBA.SystemException;

public int count() throws org.omg.CORBA.SystemException;
public org.omg.CORBA.NamedValue item(int index)
 throws Bounds, org.omg.CORBA.SystemException;
public void remove(int index)
 throws Bounds, org.omg.CORBA.SystemException;

public static NVList _nil()
 throws org.omg.CORBA.SystemException;
};
```

**Notes** CORBA-defined.

**See Also** “Class org.omg.CORBA.NamedValue” on page 43  
“Class org.omg.CORBA.Request” on page 59

### NVList()

**Synopsis** public NVList() throws org.omg.CORBA.SystemException;

**Description** Default constructor.

**Notes** PROGRESS-specific.

**See Also** create\_list() and create\_operation\_list() in “Class org.omg.CORBA.ORB” on page 46

### **NVList()**

|                    |                                                                                                                                                                                                                        |                   |                                 |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------|---------------------------------|
| <b>Synopsis</b>    | <code>public NVList(int size) throws org.omg.CORBA.SystemException;</code>                                                                                                                                             |                   |                                 |
| <b>Description</b> | Constructs an <code>NVList</code> of length <code>size</code> .                                                                                                                                                        |                   |                                 |
| <b>Parameters</b>  | <table><tr><td><code>size</code></td><td>Length of <code>NVList</code>.</td></tr></table>                                                                                                                              | <code>size</code> | Length of <code>NVList</code> . |
| <code>size</code>  | Length of <code>NVList</code> .                                                                                                                                                                                        |                   |                                 |
| <b>Notes</b>       | PROGRESS-specific. See the methods <code>create_list()</code> and <code>create_operation_list()</code> in "Class <code>org.omg.CORBA.ORB</code> " on page 46 for CORBA-defined ways to create an <code>NVList</code> . |                   |                                 |

### **NVList()**

|                    |                                                                                        |                  |                              |
|--------------------|----------------------------------------------------------------------------------------|------------------|------------------------------|
| <b>Synopsis</b>    | <code>public NVList(NVList nvl) throws org.omg.CORBA.SystemException;</code>           |                  |                              |
| <b>Description</b> | Copy constructor.                                                                      |                  |                              |
| <b>Parameters</b>  | <table><tr><td><code>nvl</code></td><td><code>NVList</code> to copy.</td></tr></table> | <code>nvl</code> | <code>NVList</code> to copy. |
| <code>nvl</code>   | <code>NVList</code> to copy.                                                           |                  |                              |
| <b>Notes</b>       | PROGRESS-specific.                                                                     |                  |                              |

### **equals()**

|                    |                                                                                                                             |                   |                                                   |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------|-------------------|---------------------------------------------------|
| <b>Synopsis</b>    | <code>public boolean equals(java.lang.Object _obj)</code><br><code>throws org.omg.CORBA.SystemException;</code>             |                   |                                                   |
| <b>Description</b> | Compare two <code>NVList</code> objects for equality. <code>NVList</code> objects are equal if they have the same contents. |                   |                                                   |
| <b>Parameters</b>  | <table><tr><td><code>_obj</code></td><td>An <code>NVList</code> object to compare against.</td></tr></table>                | <code>_obj</code> | An <code>NVList</code> object to compare against. |
| <code>_obj</code>  | An <code>NVList</code> object to compare against.                                                                           |                   |                                                   |



### Return Value

boolean                    true if the objects have the same contents,  
false otherwise.

**Notes**                    PROGRESS-specific.

### clone()

**Synopsis**                    public Object clone() throws org.omg.CORBA.SystemException;

**Description**                Copies the current NVList to a new NVList object and returns the new object.

### Return Value

Object                      A copy of the current NVList object.

**Notes**                    PROGRESS-specific.

### add()

**Synopsis**                    public org.omg.CORBA.NamedValue add(int item\_flags)  
                              throws org.omg.CORBA.SystemException;

**Description**                Creates an unnamed NamedValue, initializing only the Flags, and adds it to the list.

### Parameters

item\_flags                    org.omg.CORBA.ARG\_IN,  
                                  org.omg.CORBA.ARG\_OUT,  
                                  org.omg.CORBA.ARG\_INOUT

### Return Value

NamedValue                    New NamedValue instance.

**Notes**                    CORBA-defined.

### **add\_item()**

**Synopsis**

```
public org.omg.CORBA.NamedValue add_item(String item_name,
 int item_flags)
 throws org.omg.CORBA.SystemException;
```

**Description**

Creates a `NamedValue` with name and flags initialized, and adds it to the list.

**Parameters**

|                         |                                                                                                                     |
|-------------------------|---------------------------------------------------------------------------------------------------------------------|
| <code>item_name</code>  | Name of item.                                                                                                       |
| <code>item_flags</code> | <code>org.omg.CORBA.ARG_IN</code> ,<br><code>org.omg.CORBA.ARG_OUT</code> ,<br><code>org.omg.CORBA.ARG_INOUT</code> |

**Return Value**

|                         |                                                     |
|-------------------------|-----------------------------------------------------|
| <code>NamedValue</code> | New <code>NamedValue</code> instance added to list. |
|-------------------------|-----------------------------------------------------|

**Notes**

CORBA-defined.

### **add\_value()**

**Synopsis**

```
public org.omg.CORBA.NamedValue add_value(String item_name,
 org.omg.CORBA.Any value,
 int item_flags)
 throws org.omg.CORBA.SystemException;
```

**Description**

Creates a `NamedValue` with name, value and flags initialized and adds it to the list.

**Parameters**

|                         |                                                                                            |
|-------------------------|--------------------------------------------------------------------------------------------|
| <code>item_name</code>  | Name of item.                                                                              |
| <code>value</code>      | Value of item.                                                                             |
| <code>item_flags</code> | <code>CORBA.ARG_IN</code> , <code>CORBA.ARG_OUT</code> ,<br><code>CORBA.ARG_INOUT</code> . |



### **`_nil()`**

**Synopsis**      `public static NVList _nil() throws org.omg.CORBA.SystemException;`  
**Description**      Returns a nil object reference for an NVList object.  
**Notes**              CORBA-defined.

### **`remove()`**

**Synopsis**      `public void remove(int index)`  
                  `throws Bounds, org.omg.CORBA.SystemException;`  
**Description**      Removes the item at the given index. The first item is at index 0.  
**Parameters**

|                    |                                                         |
|--------------------|---------------------------------------------------------|
| <code>index</code> | The position within the list of the item to be removed. |
|--------------------|---------------------------------------------------------|

**Return Value**

|                  |                                     |
|------------------|-------------------------------------|
| <code>int</code> | Returns 1 on success, 0 on failure. |
|------------------|-------------------------------------|

**Notes**              CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.NVListIterator

**Synopsis** Class `NVListIterator` defines a Java iterator class for `NVList` which returns the next `NamedValue` in the list.

**Orbix Java**

```
// Java

public class NVListIterator {
 // Constructors
 public NVListIterator() throws org.omg.CORBA.SystemException;
 public NVListIterator(NVList nvl)
 throws org.omg.CORBA.SystemException;

 // Methods
 public void setList(NVList nvl)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.NamedValue next()
 throws org.omg.CORBA.SystemException;
};
```

**Notes** PROGRESS-specific.

**See also** “Class `org.omg.CORBA.NVList`” on page 44  
“Class `org.omg.CORBA.NamedValue`” on page 43

### **NVListIterator()**

**Synopsis**

```
public NVListIterator() throws org.omg.CORBA.SystemException;
```

**Description** Constructor. Creates an iterator without specifying which `NVList` object the iterator uses to traverse. You can subsequently use the method `CORBA.NVList.setList()` to set the `NVList` object.

**Notes** PROGRESS-specific.

**See Also** “`setList()`” on page 167

### **NVListIterator()**

**Synopsis**      `public NVListIterator(NVList nvl)`  
                  throws `org.omg.CORBA.SystemException;`

**Description**      Constructor. Creates an iterator for `NVList nvl`.

**Parameters**

`nvl`                      The `NVList` object for which an iterator is to be created.

**Return Value**

`NVListIterator`              The iterator for `nvl`.

**Notes**              PROGRESS-specific.

### **next()**

**Synopsis**      `public org.omg.CORBA.NamedValue next()`  
                  throws `org.omg.CORBA.SystemException;`

**Description**      The  $i^{\text{th}}$  call returns the  $i^{\text{th}}$  `NamedValue` object in the `NVList`.

**Return Value**

`NamedValue`                      An element in the `NVList`.

**Notes**              PROGRESS-specific.

## Class `IE.Iona.OrbixWeb.CORBA.NVListIterator`

---

### `setList()`

#### Synopsis

```
public void setList(NVList nvl)
 throws org.omg.CORBA.SystemException;
```

#### Description

If an `NVList` object has not been specified for the iterator, you can use this method to set the `NVList` object. If an `NVList` object has been set, you can use this method to replace the `NVList` object (if the `nvl` parameter is not the current `NVList`) or to reset the iterator position for the current `NVList` (if `nvl` is the current `NVList`).

#### Parameters

|                  |                                                                                                                                                                |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>nvl</code> | Either a new <code>NVList</code> object to associate with the iterator or the current <code>NVList</code> object in which case the iterator position is reset. |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|

#### Notes

PROGRESS-specific.

# Interface IE.Iona.OrbixWeb.CORBA.ObjectRef

**Synopsis**      ObjectRef is a Java interface that extends the implementation methods for the IDL Object interface.

This interface is implemented by proxy objects generated by the Orbix Java runtime.

In Orbix Java, all objects that implement ObjectRef hold their own full object reference in their member data. ObjectRef defines extra methods to retrieve object reference fields in string format and to convert between object references and strings.

## CORBA

```
// PIDL

interface ObjectRef {
 boolean is_a(in String Identifier);
 boolean is_equivalent(Object that);
 boolean non_existent();
 unsigned long hash(in unsigned long maximum);
 boolean is_nil();
 Object _duplicate();
 void release();
 InterfaceDef get_interface();
 Status create_request(
 in Context ctx,
 in Identifier operation,
 in NVList arg_list,
 in NamedValue result,
 out Request request,
 in Flags req_flags);
 Status create_request(
 in Context ctx,
 in Identifier operation,
 in NVList arg_list,
 in NamedValue result,
```



## Interface IE.Iona.OrbixWeb.CORBA.ObjectRef

---

```
 int ExceptionList exclist,
 out Request request,
 in Flags req_flags);
};
```

**Orbix Java** See “Interface org.omg.CORBA.Object” on page 45

```
// Java
package IE.Iona.OrbixWeb.CORBA;

public interface ObjectRef extends
 org.omg.CORBA.Object {
 // Methods
 public String _host();
 public int _port();
 public String _id();
 public String _name();
 public String _implementation();
 public String _marker();
 public boolean _marker(String marker);
 public String _interfaceHost();
 public String _interfaceImplementation();
 public String _interfaceMarker();
 public String _object_to_string();
 public String _object_to_string(int kind);
 public String toString();
 public boolean _isRemote();
 public void _IT_PING();
 public LoaderClass _loader ();
 public java.lang.Object _deref ();
 public void _save ();
 public boolean _hasValidOpenChannel ();
}
```

**See Also** “Interface org.omg.CORBA.Object” on page 45

### **`_create_request()`**

**Synopsis**

```
Request _create_request(Context ctx,
 String operation,
 NVList arg_list,
 NamedValue result);
```

**Description**

Constructs an `org.omg.CORBA.Request` object. See “`_request()`” on page 180 for an alternative way to create a `Request`. See the chapter “Dynamic Invocation Interface” in the *Orbix Programmer's Guide Java Edition* for examples of the use of this function.

**Parameters**

|                        |                                                                                                                                                                                                                                                                                                                                              |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>ctx</code>       | Context object, if any, to be sent in the <code>Request</code> . If the <code>ctx</code> argument to <code>_create_request()</code> is null, the <code>Context</code> may be added by calling the <code>ctx()</code> function on the <code>Request</code> object.                                                                            |
| <code>operation</code> | The name of the operation.                                                                                                                                                                                                                                                                                                                   |
| <code>arg_list</code>  | The parameter (each parameter in the list is of type <code>NamedValue</code> ). If the <code>arg_list</code> argument of the constructor is null, the arguments must be added by calling the <code>arguments()</code> method on the <code>Request</code> object—one call to <code>arguments()</code> for each argument that is to be passed. |
| <code>result</code>    | Contains the return value of the operation.                                                                                                                                                                                                                                                                                                  |

**Return Value**

The constructed `Request` object.

**Notes**

CORBA-defined. This function is part of the Dynamic Invocation Interface.

**See Also**

“`_request()`” on page 180  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248  
“Class `IE.Iona.OrbixWeb.CORBA.Context`” on page 130  
“`arguments()`” on page 256  
“`ctx()`” on page 258  
“Class `IE.Iona.OrbixWeb.CORBA.NVList`” on page 158

### `_create_request()`

**Synopsis**

```
Request _create_request(Context ctx,
 String operation,
 NVList arg_list,
 NamedValue result,
 ExceptionList exclist,
 ContextList ctxlist);
```

**Description**

Constructs an `org.omg.CORBA.Request` object. See “`_request()`” on page 180 for an alternative way to create a `Request`. See the chapter “Dynamic Invocation Interface” in the *Orbix Programmer’s Guide Java Edition* for examples of the use of this function.

**Parameters**

|                        |                                                                                                                                                                                                                                                                                                                                      |
|------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>ctx</code>       | Context object, if any, to be sent in the <code>Request</code> . If the <code>ctx</code> argument to <code>_create_request()</code> is null, the Context may be added by calling the <code>ctx()</code> function on the <code>Request</code> object.                                                                                 |
| <code>operation</code> | The name of the operation.                                                                                                                                                                                                                                                                                                           |
| <code>arg_list</code>  | The parameter (each parameter in the list is of type <code>NamedValue</code> ). If the <code>arg_list</code> argument of the constructor is null, the arguments must be added by calling the <code>arguments()</code> method on the <code>Request</code> object—one call to <code>arguments()</code> for each argument to be passed. |
| <code>result</code>    | Contains the return value of the operation.                                                                                                                                                                                                                                                                                          |
| <code>exclist</code>   | Allows an application to provide a list of <code>TypeCodes</code> for all user-defined exceptions that may result when the <code>Request</code> is invoked.                                                                                                                                                                          |
| <code>ctxlist</code>   | Allows an application to provide a list of Context strings that must be supplied with the <code>Request</code> invocation.                                                                                                                                                                                                           |

**Return Value** The constructed `Request` object.

**Notes** CORBA-defined. This function is part of the Dynamic Invocation Interface.

**See Also**

- “\_request()” on page 180
- “Class IE.Iona.OrbixWeb.CORBA.Request” on page 248
- “Class IE.Iona.OrbixWeb.CORBA.Context” on page 130
- “Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158
- “Class IE.Iona.OrbixWeb.CORBA.NamedValue” on page 152
- “Class IE.Iona.OrbixWeb.CORBA.ExceptionList” on page 147
- “Class IE.Iona.OrbixWeb.CORBA.ContextList” on page 139

### **\_deref()**

**Synopsis**      `public java.lang.Object _deref();`

**Description**      In the TIE approach, two objects exist: the TIE object and the true object. The reference returned by `_deref()` is that of the true implementation object.

This function is defined to allow ‘casting’ from an interface class to an implementation class. In the TIE approach, a direct cast down is not permitted because an implementation class does not inherit from its IDL Java class. For example:

```
//Java
//TIE Implementation.
//Account is the CORBA object,
//Account_i is the implementation class.
Account acc;
Account_i acc_i = (Account_i)acc; //Illegal
```

You may wish to use a function defined on an implementation class but not in the IDL interface. To use this function requires a reference to the implementation class. The IDL compiler generates a `_deref()` method defined for all TIE interface classes that returns a reference to the implementation class, if it exists.

Also when using the `ImplBase` approach, the IDL compiler generates a `_deref()` method that returns a reference to the `ImplBase` object. However, `_deref()` could be implemented in the implementation class as follows:

## Interface IE.Iona.OrbixWeb.CORBA.ObjectRef

---

```
//Java
public class Account_i extends Account {
 java.lang.Object _deref() { return this; }
};
```

**Notes** PROGRESS-specific.

### \_get\_implementation();

**Synopsis** `public ImplementationDef _get_implementation();`

**Description** Find the name of the target object's server as registered in the Implementation Repository. For a local object in a server, this is the server's name if it is known, otherwise it is the process identifier of the server process. For an object created in a client, it is the process identifier of the client process. Note that the server name will be known if the server is launched by the Orbix daemon; or if it is launched manually and the server name is passed to

```
IE.Iona.OrbixWeb.CORBA.BOA.impl_is_ready() or set by
IE.Iona.OrbixWeb.CORBA.BOA.setServerName().
```

**Notes** CORBA-defined.

### \_get\_interface\_def();

**Synopsis** `public InterfaceDef _get_interface_def();`

**Description** Returns a reference to an object in the Interface Repository that describes the interface to this object.

The Interface Repository must have been previously populated with this information for this command to work.

**Notes** CORBA-defined.

### **\_hash()**

**Synopsis**      `public int _hash(int maximum);`

**Description**      Every object reference has an internal identifier associated with it—a value that remains constant throughout the lifetime of the object reference.

The `_hash()` function returns a hashed value determined via a hashing function from the internal identifier. Two different object references may yield the same hashed value. However, if two object references return different hash values, these object references are known to be for different objects.

#### **Parameters**

|                      |                                                                                                                                                                                                                              |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>maximum</code> | The maximum value to be returned from the hash function. For example, setting <code>maximum</code> to 7 partitions the object reference space into a maximum of 8 sub-spaces (because the lower bound of the function is 0). |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Return Value**      A hashed value for the object reference in the range 0...maximum.

**Notes**              CORBA-defined.

### **\_hasValidOpenChannel()**

**Synopsis**      `public boolean _hasValidOpenChannel();`

**Description**      This method returns `true` if there is a valid open connection between this process and the process in which this object resides.

#### **Return Value**

|                      |                                                                                                                                   |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------|
| <code>boolean</code> | Returns <code>true</code> if there is a valid, open connection between this process and the process in which this object resides. |
|----------------------|-----------------------------------------------------------------------------------------------------------------------------------|

**Notes**              PROGRESS-specific.

**See Also**          `IE.Iona.OrbixWeb.CORBA.ORB.hasValidOpenChannel()`

### `_host()`

- Synopsis** `public String _host();`
- Description** Returns the name of the host on which the target object is located.
- Notes** PROGRESS-specific.

### `_id()`

- Synopsis** `public String _id();`
- Description** Returns the object's Interface Repository ID.
- Notes** PROGRESS-specific.

### `_implementation()`

- Synopsis** `public String _implementation();`
- Description** Find the name of the target object's server as registered in the Implementation Repository. For a local object in a server, this is the server's name if known, otherwise it is the process identifier of the server process. For an object created in a client, it is the process identifier of the client process. Note that the server name is known if the server is launched by the Orbix daemon; or if it is launched manually and the server name is passed to `IE.Iona.OrbixWeb.CORBA.BOA.impl_is_ready()` or set by `IE.Iona.OrbixWeb.CORBA.BOA.setServerName()`.
- Notes** PROGRESS-specific. The CORBA-defined version of this function is “`_get_interface_def()`,” on page 173
- See Also** “`_get_implementation()`,” on page 173

### **\_interfaceHost()**

- Synopsis**      `public String _interfaceHost();`
- Description**      Returns the name of a host running the Interface Repository server that stores the target object's IDL definition.
- Notes**              PROGRESS-specific.

### **\_interfaceImplementation()**

- Synopsis**      `public String _interfaceImplementation();`
- Description**      Returns the object's Interface Repository server name. The default is "IR".
- Notes**              PROGRESS-specific.

### **\_interfaceMarker()**

- Synopsis**      `public String _interfaceMarker();`
- Description**      Returns the name of the target object's interface.
- Notes**              PROGRESS-specific.

### **\_is\_a()**

- Synopsis**      `public boolean _is_a(String logical_type_id);`
- Description**      Determines if the target object is an instance of the type specified in `logical_type_id` or is an instance of a derived type of the type in `logical_type_id`.



## Interface `IE.Iona.OrbixWeb.CORBA.ObjectRef`

---

### Parameters

|                              |                                                                                                                                                 |
|------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>logical_type_id</code> | The fully scoped name of the IDL interface. You should use a forward slash ('/') rather than a scope operator ('.') to delimit scope in a name. |
|------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|

### Return Value

|                    |                                                                                                                                     |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------|
| <code>true</code>  | The object is an instance of the type specified by <code>logical_type_id</code> or is an instance of a type derived from that type. |
| <code>false</code> | The object is not an instance of that type or any of its derived types.                                                             |

**Notes** CORBA-defined.

**See Also** “Interface `org.omg.CORBA.Object`” on page 45  
“`_non_existent()`” on page 180

### `_is_equivalent()`

#### Synopsis

```
public boolean _is_equivalent(Object that);
```

#### Description

Tests if two object references are equivalent. Two object references are said to be equivalent if they have the same object reference, or they both refer to the same object.

#### Parameters

|                  |                                                                           |
|------------------|---------------------------------------------------------------------------|
| <code>obj</code> | The object that is to be compared for equivalence with the target object. |
|------------------|---------------------------------------------------------------------------|

### Return Value

|                    |                                                                                                                                                     |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>true</code>  | The object reference refers to the same object.                                                                                                     |
| <code>false</code> | This return value does not mean that the object references are not equivalent—only that the ORB cannot confirm that they reference the same object. |

**Notes** CORBA-defined.

**See Also** “Interface `org.omg.CORBA.Object`” on page 45  
“`_is_a()`” on page 176

### **`_isRemote()`**

**Synopsis** `public boolean _isRemote();`

**Description** Returns `true` if the reference is to a remote object, `false` otherwise.

**Notes** PROGRESS-specific.

### **`IT_PING()`**

**Synopsis** `public void _IT_PING();`

**Description** This method verifies that a remote object exists. If no connection exists to the target object's server, Orbix Java attempts to create a connection, relaunching the server if necessary. If this fails, or the object is not located in the server specified in the object reference, an `INVALID_OBJREF` system exception is thrown.

The target object is guaranteed to exist if this operation completes normally.

**Notes** PROGRESS-specific.

**See Also** “`noReconnectOnFailure()`” on page 221

### `_loader()`

|                    |                                                                                                                                                |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>    | <code>public LoaderClass _loader();</code>                                                                                                     |
| <b>Description</b> | Returns the <code>loaderClass</code> object associated with this object. This call is only available within the objects' server process space. |
| <b>Notes</b>       | PROGRESS-specific.                                                                                                                             |

### `_marker()`

|                    |                                       |
|--------------------|---------------------------------------|
| <b>Synopsis</b>    | <code>public String _marker();</code> |
| <b>Description</b> | Returns the object's marker.          |
| <b>Notes</b>       | PROGRESS-specific.                    |

### `_marker()`

|                     |                                                                                                                                               |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>     | <code>public boolean _marker(String marker);</code>                                                                                           |
| <b>Description</b>  | This method attempts to reset an object's marker to the string specified.                                                                     |
| <b>Return Value</b> |                                                                                                                                               |
| <code>true</code>   | The object's marker was successfully changed.                                                                                                 |
| <code>false</code>  | There was a problem assigning the new marker to the object. This is typically because an object already exists that has the specified marker. |
| <b>Notes</b>        | PROGRESS-specific.                                                                                                                            |

### **\_name()**

**Synopsis**      `public String _name();`

**Description**      Returns the object's interface name.

**Notes**      PROGRESS-specific.

### **\_non\_existent()**

**Synopsis**      `public boolean _non_existent();`

**Description**      Tests if the target exists. Normally this function is invoked on a proxy and determines whether the real object exists.

#### **Return Value**

`true`                      The object does not exist (it does not raise an exception if the object does not exist).

`false`                     The object exists.

**Notes**      CORBA-defined.

### **\_port()**

**Synopsis**      `public int _port();`

**Description**      Returns the object's server listening port.

**Notes**      PROGRESS-specific.

### **\_request()**

**Synopsis**      `public org.omg.CORBA.Request _request(String operation);`

**Description**      Constructs an `org.omg.CORBA.Request` on the target object. This is the shorter form of `IE.Iona.OrbixWeb.CORBA.ObjectRef._create_request()`.

## Interface `IE.Iona.OrbixWeb.CORBA.ObjectRef`

---

You may add arguments and contexts after construction using `IE.Iona.OrbixWeb.CORBA.Request.arguments()` and `IE.Iona.OrbixWeb.CORBA.Request.ctx()`. See the chapter “Dynamic Invocation Interface” in the *Orbix Programmer’s Guide Java Edition* for examples of the use of this function.

### Parameters

`operation`                      The name of the operation.

### Return Value

`Request`                        The `Request` object constructed.

**Notes**                        CORBA-defined.

**See Also**                    “`_create_request()`” on page 170  
“`arguments()`” on page 256  
“`ctx()`” on page 258

### `_object_to_string()`

#### Synopsis

```
public String _object_to_string();
```

#### Description

Converts the target object’s reference to a string. The format of that string depends on the communication protocol used to create that object.

If you are using the IIOP protocol, this function creates a stringified Interoperable Object Reference, which is a string of hexadecimal numbers, beginning with the string ‘IOR:’.

If you are using the Orbix protocol, a stringified object reference has the form:

```
:\host:serverName:marker:IR_host:IR_Server:interfaceMarker
```

See “`object_to_string()`” on page 222 for an explanation of these fields.

**Return Value**                Returns a stringified object reference.

**Notes**                        PROGRESS-specific.

**See Also**                    “`object_to_string()`” on page 222  
“`_object_to_string()`” on page 182

### **`_object_to_string()`**

**Synopsis**

```
public String _object_to_string(int kind);
```

**Description**

Converts the target object's reference to a string. The format of the string returned is determined by the value of parameter `kind`.

If the value of `kind` is `IT_ORBIX_OR_KIND`, the string returned is the standard Orbix Protocol object reference string format:

```
:\host:serverName:marker:IR_host:IR_Server:interfaceMarker
```

See “`_object_to_string()`” on page 222 for an explanation of these fields.

If the value of `kind` is `IT_INTEROPERABLE_OR_KIND`, then the string returned is a CORBA Interoperable Object Reference (IOR) for use with the Internet Inter-ORB Protocol (IIOP) as described in the chapter “ORB Interoperability” in the *Orbix Programmer's Guide Java Edition* .

**Return Value**

Returns a stringified object reference.

**Notes**

PROGRESS-specific.

**See Also**

“`_object_to_string()`” on page 222  
“`_object_to_string()`” on page 182

### **`_save()`**

**Synopsis**

```
public void _save();
```

**Description**

Calls the `save()` method on the `LoaderClass` associated with this object. The reason provided is `_CORBA.explicitCall`.

Call `_save()` when you want to make the state of the object persistent but

- ◆ do not wish to wait until the server exits (see “`finalize()`” on page 111),
- ◆ and want to keep the object registered with the ORB (see “`disconnect()`” on page 109).

## Interface `IE.Iona.OrbixWeb.CORBA.ObjectRef`

---

The implementation of `save()` in the default `LoaderClass` object does nothing.

You must call `_save()` in the same server space as the target object. If you call it in a client process (on a proxy), there is no effect.

### Notes

PROGRESS-specific.

### See Also

“`explicit_call`” on page 344

“`disconnect()`” on page 109

“`dispose()`” on page 110

“`finalize()`” on page 111

“Class `IE.Iona.OrbixWeb.Features.LoaderClass`” on page 319

“`save()`” on page 325

# Class IE.Iona.OrbixWeb.CORBA.ORB

## Synopsis

Class ORB implements the OMG CORBA ORB pseudo-interface and adds a number of methods specific to Orbix Java.

ORB provides a set of methods that control Orbix Java from the client. These include operations to convert between strings and object references, and operations for use with the Dynamic Invocation Interface (DII).

To maintain portability of your client-side CORBA code, you must use only those methods defined in pseudo IDL and defined on `org.omg.CORBA.ORB`. To use these methods, invoke on the ORB object as follows:

```
ORB.init(args,null).<method name>
```

To access the Orbix Java value added methods, use the `_OrbixWeb` conversion function as follows:

```
_OrbixWeb.ORB(ORB.init(args,null)).<Orbix Java
specific method name>
```

or equivalently

```
_CORBA.Orbix.<Orbix Java specific method name>
```

## CORBA

```
// Pseudo IDL

pseudo interface ORB {

 exception InvalidName {};

 // Typedefs
 typedef string ObjectId;
 typedef sequence<ObjectId> ObjectIdList;

 // Service methods
 ObjectIdList list_initial_services();
 Object resolve_initial_references
 (in ObjectId object_name)
 raises(InvalidName);
};
```



```
// Object Reference methods
string object_to_string(in Object obj);
Object string_to_object(in string str);
// Creation methods
NVList create_list(in long count);
NVList create_operation_list
 (in OperationDef oper);
NamedValue create_named_value(in String name,
 in Any value,
 in Flags flags);

ExceptionList create_exception_list();
ContextList create_context_list();
Context get_default_context();
Environment create_environment();
Any create_any();
OutputStream create_output_stream();

// Typecode creation
TypeCode create_struct_tc
 (in RepositoryId id,
 in Identifier name,
 in StructMemberSeq members);
TypeCode create_union_tc
 (in RepositoryId id,
 in Identifier name,
 in TypeCode discriminator_type,
 in UnionMemberSeq members);
TypeCode create_enum_tc
 (in RepositoryId id,
 in Identifier name,
 in EnumMemberSeq members);
TypeCode create_alias_tc
 (in RepositoryId id,
 in Identifier name,
 in TypeCode original_type);
TypeCode create_exception_tc
 (in RepositoryId id,
 in Identifier name,
 in StructMemberSeq members);
```

```
TypeCode create_interface_tc
 (in RepositoryId id,
 in Identifier name);
TypeCode create_string_tc
 (in unsigned long bound);
TypeCode create_wstring_tc
 (in unsigned long bound);
TypeCode create_sequence_tc
 (in unsigned long bound,
 in TypeCode element_type);
TypeCode create_recursive_sequence_tc
 (in unsigned long bound,
 in unsigned long offset);
TypeCode create_array_tc
 (in unsigned long length,
 in TypeCode element_type);
TypeCode get_primitive_tc(in TCKind tcKind);

// Invocation methods
void send_multiple_requests_oneway
 (in RequestSeq req);
void send_multiple_requests_deferred
 (in RequestSeq req);
boolean poll_next_response();
Request get_next_response();

// Server-side methods
void connect(Object obj);
void disconnect(Object obj);
Current get_current();

// Additional operations for Java mapping

// additional methods for ORB initialization go
// here, but only appear in the mapped Java
// Java signatures
// public static ORB init
// (Strings[] args,
// Properties props);
// public static ORB init
// (Applet app,
// Properties props);
// public static ORB init();
```

## Class IE.Iona.OrbixWeb.CORBA.ORB

---

```
// abstract protected void set_parameters
// (String[] args,
// java.util.Properties props);

// abstract protected void set_parameters
// (java.applet.Applet app,
// java.util.Properties props);
};
```

### Orbix Java

```
public class ORB extends IE.Iona.OrbixWeb.CORBA.singletonORB {
 public String[] baseInterfacesOf(String derivedStubClass)
 throws org.omg.create_opSystemException;
 public boolean closeConnection(org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;
 public boolean collocated()
 throws org.omg.CORBA.SystemException;
 public boolean collocated(boolean b)
 throws org.omg.CORBA.SystemException;
 public final OrbConfig config()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.TypeCode create_alias_tc(
 String id,
 String name,
 org.omg.CORBA.TypeCode original_type)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.Any create_any()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.TypeCode create_array_tc(int length,
 org.omg.CORBA.TypeCode element_type)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.ContextList create_context_list()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.TypeCode create_enum_tc(String id,
 String name,
 String[] members)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.Environment create_environment()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.ExceptionList create_exception_list()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.TypeCode create_exception_tc(
 String id,
 String name,
```

```
 org.omg.CORBA.StructMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_interface_tc(String id,
 String name)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.NVList create_list(int count)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.NamedValue create_named_value(
 String name,
 org.omg.CORBA.Any value,
 int flags)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.NVList
 create_operation_list(org.omg.CORBA.OperationDef oper)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.portable.OutputStream create_output_stream()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_recursive_sequence_tc(
 int bound,
 int offset)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_sequence_tc(
 int bound,
 TypeCode element_type)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_string_tc(int bound)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_struct_tc(
 String id,
 String name,
 org.omg.CORBA.StructMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_union_tc(
 String id,
 String name,
 org.omg.CORBA.TypeCode disc_type,
 org.omg.CORBA.UnionMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_wstring_tc(int bound)
 throws org.omg.CORBA.SystemException;
public int defaultTxTimeout(int val)
 throws org.omg.CORBA.SystemException;
```

```
public void finalize()
 throws org.omg.CORBA.SystemException;
public static String getConfigItem (String name)
 throws org.omg.CORBA.SystemException;
public static Properties getConfiguration ()
 throws org.omg.CORBA.SystemException;
public DaemonMgr[] getDaemonConnections ()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Context get_default_context()
 throws org.omg.CORBA.SystemException;
public int getHostPort(String hostname)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Principal get_my_principal()
 throws org.omg.CORBA.SystemException;
public IT_reqTransformer getMyReqTransformer()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Request get_next_response()
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode get_primitive_tc(
 org.omg.CORBA.TCKind tcKind)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Principal get_principal()
 throws org.omg.CORBA.SystemException;
public static IT_reqTransformer getTransformer(String server,
 String host)
 throws org.omg.CORBA.SystemException;
public String get_principal_string()
 throws org.omg.CORBA.SystemException;
public boolean isValidOpenChannel(ObjectRef oref)
 throws org.omg.CORBA.SystemException;
public boolean isValidOpenChannel(org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;
static public synchronized org.omg.CORBA.ORB init ()
 throws org.omg.CORBA.SystemException;
static public org.omg.CORBA.ORB init (String[] args,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException,
 org.omg.CORBA.INITIALIZE;
static public org.omg.CORBA.ORB init(java.util.Properties props)
 throws org.omg.CORBA.SystemException,
 org.omg.CORBA.INITIALIZE;
static public org.omg.CORBA.ORB init (java.applet.Applet app,
 java.util.Properties props)
```

```
 throws org.omg.CORBA.SystemException,
 org.omg.CORBA.INITIALIZE;
public boolean isBaseInterfaceOf(String derivedStubClass,
 String maybeABase)
 throws org.omg.CORBA.SystemException;
public boolean isBaseInterfaceOf(org.omg.CORBA.Object obj,
 String maybeABase)
 throws org.omg.CORBA.SystemException;
public String[] list_initial_services()
 throws org.omg.CORBA.SystemException;
public final void locator(locatorClass l)
 throws org.omg.CORBA.SystemException;
public String makeIOR(String ip_addr,
 int port,
 String orbixHost,
 String server,
 String marker,
 String typeID)
 throws org.omg.CORBA.SystemException;
public String makeIOR(String ip_addr,
 int port,
 byte[] objKey,
 String typeID)
 throws org.omg.CORBA.SystemException;
public int maxConnectRetries(int retries)
 throws org.omg.CORBA.SystemException;
public String myHost() {
 throws org.omg.CORBA.SystemException;
public static ORB _nil()
 throws org.omg.CORBA.SystemException;
public boolean noReconnectOnFailure(boolean b)
 throws org.omg.CORBA.SystemException;
public String object_to_string(org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;
public boolean pingDuringBind(boolean pingOn)
 throws org.omg.CORBA.SystemException;
public boolean poll_next_response()
 throws org.omg.CORBA.SystemException;
public void reSizeConnectionTable(int size)
 throws org.omg.CORBA.SystemException;
public void registerIOCallback(ioCallback cb)
 throws org.omg.CORBA.SystemException;
```

## Class IE.Iona.OrbixWeb.CORBA.ORB

---

```
public org.omg.CORBA.Object resolve_initial_references(
 String serviceName)
 throws org.omg.CORBA.SystemException;
public void send_multiple_requests_deferred(
 org.omg.CORBA.Request[] requests)
 throws org.omg.CORBA.SystemException;
public void send_multiple_requests_oneway(
 org.omg.CORBA.Request[] requests)
 throws org.omg.CORBA.SystemException;
public static void setConfigItem (String name, String value)
 throws org.omg.CORBA.SystemException;
public static void setConfiguration (Properties props)
 throws org.omg.CORBA.SystemException;
public static int setDiagnostics(int level)
 throws org.omg.CORBA.SystemException;
public void setHostPort (String hostname, int port)
 throws org.omg.CORBA.SystemException;
public IT_reqTransformer setMyReqTransformer(
 IT_reqTransformer new_transform)
 throws org.omg.CORBA.SystemException;
public void set_parameters (String[] args,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException;
public void set_parameters (java.applet.Applet app,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException;
public void set_principal (String new_user)
 throws org.omg.CORBA.SystemException;
public void set_principal (org.omg.CORBA.Principal new_user)
 throws org.omg.CORBA.SystemException;
public void setReqTransformer (IT_reqTransformer new_transform,
 String serverName,
 String host)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Object string_to_object (String host,
 String IR_host,
 String ServerName,
 String marker,
 String IR_server,
 String interfaceName)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Object string_to_object (String s)
 throws org.omg.CORBA.SystemException;
```

```
public String toString()
 throws org.omg.CORBA.SystemException;

public void unregisterIOCallback()
 throws org.omg.CORBA.SystemException;
}
```

**Notes**

CORBA-defined.

**See Also**

“Class org.omg.CORBA.ORB” on page 46  
“Class org.omg.CORBA.ORBPackage.InvalidName” on page 52  
“Class IE.Iona.OrbixWeb.\_OrbixWeb” on page 349  
“Interface IE.Iona.OrbixWeb.CORBA.BOA” on page 98

**Server-Side:**

See “Interface IE.Iona.OrbixWeb.CORBA.BOA” on page 98 for details.

```
public boolean anyClientsConnected()
public void change_implementation(org.omg.CORBA.Object obj,
 java.lang.String impl)
public void connect(org.omg.CORBA.Object obj)
public void connect(org.omg.CORBA.Object obj,
 LoaderClass loader)
public void connect(org.omg.CORBA.Object obj,
 String marker)
public void connect(org.omg.CORBA.Object obj,
 String marker,
 LoaderClass loader)
public void continueThreadDispatch (org.omg.CORBA.Request r)
public org.omg.CORBA.Object create(byte[] id,
 java.lang.String intf,
 java.lang.String impl)
public void deactivate_impl (String impl)
public void deactivate_obj(org.omg.CORBA.Object obj)
public void disconnect(org.omg.CORBA.Object obj)
public void dispose (org.omg.CORBA.Object obj)
public boolean enableLoaders (boolean b)
public boolean filterBadConnectAttempts (boolean b)
public org.omg.CORBA.Current get_current()
public byte[] get_id(org.omg.CORBA.Object obj)
public org.omg.CORBA.Principal get_principal
 (org.omg.CORBA.Object obj)
public void impl_is_ready ()
public void impl_is_ready (String serverName)
public void impl_is_ready (String serverName, int timeout)
```



```
public void impl_is_ready (int timeOut)
public boolean isEventPending ()
public short myActivationMode ()
public String myImplementationName ()
public String myMarkerName ()
public String myMarkerPattern ()
public String myMethodName ()
public int numClientsConnected ()
public void obj_is_ready (org.omg.CORBA.Object obj,
 java.lang.String impl,
 int timeOut)
public void obj_is_ready (org.omg.CORBA.Object obj,
 java.lang.String impl)
public int processEvents ()
public int processEvents (int timeOut)
public int processNextEvent (int timeOut)
public int processNextEvent ()
public org.omg.CORBA.Current set_current()
public boolean setNoHangup (boolean b)
public synchronized void setServerName (String serverName)
```

### **baseInterfacesOf()**

#### **Synopsis**

```
public String[] baseInterfacesOf(String derivedStubClass)
 throws org.omg.CORBA.SystemException;
```

#### **Description**

For a given Java stub, return a list of supported IDL interfaces. The interface `derivedStubClass` is also returned in the sequence, because it is considered a base interface of itself.

#### **Return Value**

String []                      An array of strings containing all the base interfaces for this type of object.

#### **Notes**

PROGRESS-specific.

#### **See Also**

The method `isBaseInterfaceOf()` in “Class `org.omg.CORBA.ORB`” on page 46.

### **closeConnection()**

|                     |                                                                                                                      |         |                                              |
|---------------------|----------------------------------------------------------------------------------------------------------------------|---------|----------------------------------------------|
| <b>Synopsis</b>     | <pre>public boolean closeConnection(org.omg.CORBA.Object oref)     throws org.omg.CORBA.SystemException;</pre>       |         |                                              |
| <b>Description</b>  | Used to explicitly close a connection associated with an object. Returns true if connection was successfully closed. |         |                                              |
| <b>Parameters</b>   | <table><tr><td>oref</td><td>The object whose connection is to be closed.</td></tr></table>                           | oref    | The object whose connection is to be closed. |
| oref                | The object whose connection is to be closed.                                                                         |         |                                              |
| <b>Return Value</b> | <table><tr><td>boolean</td><td>Returns true if the call was successful.</td></tr></table>                            | boolean | Returns true if the call was successful.     |
| boolean             | Returns true if the call was successful.                                                                             |         |                                              |
| <b>Notes</b>        | PROGRESS-specific.                                                                                                   |         |                                              |
| <b>See Also</b>     | “Class org.omg.CORBA.ORB” on page 46                                                                                 |         |                                              |

### **collocated()**

|                     |                                                                                                                                                                   |         |                                                                                        |
|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|----------------------------------------------------------------------------------------|
| <b>Synopsis</b>     | <pre>public boolean collocated()     throws org.omg.CORBA.SystemException;</pre>                                                                                  |         |                                                                                        |
| <b>Description</b>  | This method returns true if collocation is set. If set to true, bind() and string_to_object(), invocations to objects outside this address space are not allowed. |         |                                                                                        |
| <b>Return Value</b> | <table><tr><td>boolean</td><td>Returns true if collocation is set, otherwise it returns false (the default is false).</td></tr></table>                           | boolean | Returns true if collocation is set, otherwise it returns false (the default is false). |
| boolean             | Returns true if collocation is set, otherwise it returns false (the default is false).                                                                            |         |                                                                                        |
| <b>Notes</b>        | PROGRESS-specific.                                                                                                                                                |         |                                                                                        |
| <b>See Also</b>     | string_to_object() in “Class org.omg.CORBA.ORB” on page 46.                                                                                                       |         |                                                                                        |

### collocated()

**Synopsis**

```
public boolean collocated(boolean b)
 throws org.omg.CORBA.SystemException;
```

**Description**

This methods sets collocation flag to boolean value passed in and returns the previous value. If collocation is set to `true`, `bind()` and `string_to_object()`, invocations to objects outside this address space are not allowed. By default, collocation is set to `false` (off).

**Parameters**

`b`                                      The new setting for collocation flag.

**Return Value**

`boolean`                                The old value of the collocated flag.

**Notes**

PROGRESS-specific.

**See Also**

`collocated()` in “Class `org.omg.CORBA.ORB`” on page 46

### config()

**Synopsis**

```
public final OrbConfig config();
```

**Description**

This method initializes per-ORB configuration. It enables you to get and set Orbix Java configuration parameters for the ORB, using the methods provided in class `IE.Iona.OrbixWeb.Features.OrbConfig`.

`OrbConfig` calls should be made on the object returned by calling `config()` on the selected ORB. For example,  
`myOrb.config().getConfigItem("IT_BIND_USING_Iiop").`

**Notes**

PROGRESS-specific.

**See Also**

“Class `IE.Iona.OrbixWeb.Features.OrbConfig`” on page 330

### create\_tc()

#### Synopsis

```
public org.omg.CORBA.TypeCode create_alias_tc(
 String id,
 String name,
 org.omg.CORBA.TypeCode original_type)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_array_tc(
 int length,
 org.omg.CORBA.TypeCode element_type)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_enum_tc(String id,
 String name,
 String[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_exception_tc(
 String id,
 String name,
 org.omg.CORBA.StructMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_interface_tc(String id,
 String name)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_recursive_sequence_tc(
 int bound,
 int offset)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_sequence_tc(public
 int bound,
 TypeCode element_type)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_string_tc(int bound)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_struct_tc(
 String id,
 String name,
 org.omg.CORBA.StructMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_union_tc(
 String id,
 String name,
 org.omg.CORBA.TypeCode disc_type,
 org.omg.CORBA.UnionMember[] members)
```

```
throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_wstring_tc(int bound)
 throws org.omg.CORBA.SystemException;
```

### Description

Creates a new `TypeCode` for a specified IDL type. See the Interface Repository section of the CORBA specification.

Normally the `TypeCodes` describing IDL types are generated automatically in the Helper classes or are accessible from the Interface Repository.

In some situations, such as bridges between ORBs, `TypeCodes` need to be constructed outside of any Interface Repository. You can do this using the `create_<type>_tc()` methods on the ORB pseudo-object.

Refer to “Class `org.omg.CORBA.TypeCode`” on page 71 for details of parameters.

For example:

For an array `TypeCode` the methods available are `length()`, which returns the size of this dimension of the array, and `content_type()` which returns the `TypeCode` for the contents of the array.

---

**Note:** For a multi-dimensional array, this is also an array `TypeCode`.

---

The parameters for `create_array_tc()` correspond to the values that represent the length of the array and the `TypeCode` of the elements contained in the array. So to create a `TypeCode` for a 2-dimensional array of `longs` you can use the following code:

```
import IE.Iona.OrbixWeb._CORBA;
import org.omg.CORBA.TypeCode;
import org.omg.CORBA.ORB;
// create a TypeCode for an array defined as follows in IDL
// typedef long LongArray[4][5];

TypeCode tempTC=
 ORB.init().create_array_tc(5,_CORBA._tc_long);
TypeCode tc =
 ORB.init().create_array_tc(4,
 tempTC);
```

### Parameters

|      |                                                                                                                                                                                                                                                                                                                                                            |
|------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| id   | The <code>RepositoryId</code> String for the object described in the CORBA specification. This is a string of the form "IDL:/<ident1>/<ident2>/.../<identn>:<version number>". For example, for the grid interface the <code>RepositoryId</code> is "IDL:grid:1.0". If the Helper classes are available, the <code>id()</code> method returns this string. |
| name | The name of the IDL type.                                                                                                                                                                                                                                                                                                                                  |

### Return Value

|                       |                                      |
|-----------------------|--------------------------------------|
| <code>TypeCode</code> | The <code>TypeCode</code> generated. |
|-----------------------|--------------------------------------|

**Notes** CORBA-defined.

**See Also** "Class `org.omg.CORBA.ORB`" on page 46  
"Class `IE.Iona.OrbixWeb.CORBA.ORB`" on page 184

### **create\_any()**

**Synopsis**

```
public org.omg.CORBA.Any create_any()
 throws org.omg.CORBA.SystemException;
```

**Description** Creates a new empty "Class `IE.Iona.OrbixWeb.CORBA.Any`".

### Return Value

|                                |                            |
|--------------------------------|----------------------------|
| <code>org.omg.CORBA.Any</code> | The new <code>Any</code> . |
|--------------------------------|----------------------------|

**Notes** CORBA-defined.

**See Also** "Class `IE.Iona.OrbixWeb.CORBA.Any`" on page 81"

### **create\_context\_list()**

**Synopsis**

```
public org.omg.CORBA.ContextList create_context_list()
 throws org.omg.CORBA.SystemException;
```

**Description**

When making an invocation using the DII on an IDL operation that has a `Context` specified, you must pass a `ContextList` parameter to the `_create_request()` method in “Interface `org.omg.CORBA.Object`” on page 45. This method allows you to create an empty “Class `org.omg.CORBA.ContextList`” on page 37.

**Return Value**

`contextList`                      An empty `ContextList` object.

**Notes**

CORBA-defined.

**See Also**

“Class `org.omg.CORBA.ORB`” on page 46  
“Class `org.omg.CORBA.ContextList`” on page 37  
“Class `IE.Iona.OrbixWeb.CORBA.ContextList`” on page 139  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248  
“Class `org.omg.CORBA.Context`” on page 35  
`_create_request()` method in “Interface `org.omg.CORBA.Object`” on page 45

### **create\_environment()**

**Synopsis**

```
public org.omg.CORBA.Environment create_environment()
 throws org.omg.CORBA.SystemException;
```

**Description**

The “Class `org.omg.CORBA.Environment`” object is used with the DII to allow exception information to be returned from an operation invocation. This methods creates a new empty `Environment` object that you can use as a parameter to the `_create_request()` method in “Interface `org.omg.CORBA.Object`” on page 45.

**Return Value**

`Environment`                      A new empty `Environment` object.

**Notes**

CORBA-defined.

**See Also**      “Class org.omg.CORBA.ORB” on page 46  
                 “Class org.omg.CORBA.ContextList” on page 37  
                 “Class IE.Iona.OrbixWeb.CORBA.Request” on page 248  
                 “Class IE.Iona.OrbixWeb.CORBA.Environment” on page 145  
                 “Class org.omg.CORBA.Environment” on page 41  
                 `_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### **create\_exception\_list()**

**Synopsis**

```
public org.omg.CORBA.ExceptionList create_exception_list()
 throws org.omg.CORBA.SystemException;
```

**Description**    An “Class org.omg.CORBA.ExceptionList” is used by the DII to describe the exceptions that can be raised by IDL operations. This method creates an empty `ExceptionList` to be inserted into the `Request`.

### **Return Value**

`ExceptionList`      An empty `ExceptionList`.

**Notes**          CORBA-defined.

**See Also**      “Class org.omg.CORBA.ORB” on page 46  
                 “Class org.omg.CORBA.ExceptionList” on page 42  
                 “Class IE.Iona.OrbixWeb.CORBA.Request” on page 248  
                 “Class IE.Iona.OrbixWeb.CORBA.Environment” on page 145  
                 “Class org.omg.CORBA.Environment” on page 41  
                 `_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### **create\_list()**

**Synopsis**

```
public org.omg.CORBA.NVList create_list(int count)
 throws org.omg.CORBA.SystemException;
```

**Description**    Creates an empty “Class org.omg.CORBA.NVList” for use as a parameter type or for use as a way to describe the arguments to an operation invocation when using the `_create_request()` method in “Interface org.omg.CORBA.Object”



`add_item()` is the only way to add an item to an `NVList`. `get_length()` returns number of times `add_item()` was called. The `NVList` always starts with element number 0.

### Parameters

`count`                      The size of the `NVList` to create.

### Return Value

`NVList`                      The empty `NVList` returned by this method.

**Notes**                      CORBA-defined.

**See Also**                      “Class `org.omg.CORBA.ORB`” on page 46  
                                    “Class `org.omg.CORBA.NVList`” on page 44  
                                    “Class `IE.Iona.OrbixWeb.CORBA.NVList`” on page 158  
                                    “Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248  
                                    “Class `IE.Iona.OrbixWeb.CORBA.NamedValue`” on page 152  
                                    “Class `org.omg.CORBA.NamedValue`” on page 43  
                                    `_create_request()` method in “Interface `org.omg.CORBA.Object`” on page 45

### **create\_named\_value()**

#### **Synopsis**

```
public org.omg.CORBA.NamedValue create_named_value(
 String name,
 org.omg.CORBA.Any value,
 int flags)
 throws org.omg.CORBA.SystemException;
```

#### **Description**

Creates an empty “Class `org.omg.CORBA.NamedValue`”. You can insert this into a “Class `IE.Iona.OrbixWeb.CORBA.NVList`” when using the DII as one of the parameters to the operation invocation.

#### **Parameters**

`name`                          The name of the `NamedValue`.  
`value`                          An `Any` to be inserted into the value of the `NamedValue`.

flags Indicates whether this is an IN, OUT or INOUT parameter.

### Return Value

NameValue The NamedValue constructed by this method call.

**Notes** CORBA-defined.

**See Also** “Class org.omg.CORBA.ORB” on page 46  
“Class org.omg.CORBA.NVList” on page 44  
“Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158  
“Class IE.Iona.OrbixWeb.CORBA.Request” on page 248  
“Class IE.Iona.OrbixWeb.CORBA.NamedValue” on page 152  
“Class org.omg.CORBA.NamedValue” on page 43  
\_create\_request() method in “Interface org.omg.CORBA.Object” on page 45

### create\_operation\_list()

#### Synopsis

```
public org.omg.CORBA.NVList
 create_operation_list(org.omg.CORBA.OperationDef oper)
 throws org.omg.CORBA.SystemException;
```

#### Description

Create a new NVList for use with operation invocations when using the DII.

The returned NVList is the correct length, each of the NamedValues contained within has a valid name and the correct flags (for the parameter passing mode, either ARG\_IN, ARG\_OUT or ARG\_INOUT).

The value part of the NamedValue is empty—you must populate it with correct values. For a NamedValue with flag set to ARG\_IN or ARG\_INOUT the value must be initialized.

The IFR must be populated for this call to work.

For example, consider the following used to call the first operation on an Object. You can use the following code to set up the NVList for the parameters:

```
org.omg.CORBA.Object ref = // get the reference from somewhere :
 // For example :
 // - from a file and then call
 // string_to_object(),
 // - from the naming service
 // - using the bind call
org.omg.CORBA.InterfaceDef iDefRef = null;
org.omg.CORBA.OperationDef[] oDef = null;
org.omg.CORBA.NVList nvl = null;
try {
 iDefRef = ref._get_interface();
 oDef =
 iDefRef.contents(org.omg.CORBA.DefinitionKind.dk_Operation,
 true);
 if(oDef != null){
 nvl = ORB.init().create_operation_list(oDef[0]);
 }
}
catch(org.omg.CORBA.SystemException e){
 // do something
}

// continue on with DII invocation
```

### Parameters

|      |                                                                                  |
|------|----------------------------------------------------------------------------------|
| oper | A reference to an org.omg.CORBA.OperationDef object in the Interface Repository. |
|------|----------------------------------------------------------------------------------|

### Return Value

|        |                                                                                                                                               |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| NVList | NVList set-up for this operation invocation; the correct number of the NamedValue and the NamedValues have a valid name and the correct flag. |
|--------|-----------------------------------------------------------------------------------------------------------------------------------------------|

### Notes

CORBA-defined.

**See Also**      “Class org.omg.CORBA.ORB” on page 46  
                 “Class org.omg.CORBA.NVList” on page 44  
                 “Class IE.Iona.OrbixWeb.CORBA.NVList” on page 158  
                 “Class IE.Iona.OrbixWeb.CORBA.Request” on page 248  
                 “Class IE.Iona.OrbixWeb.CORBA.NamedValue” on page 152  
                 `_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### **create\_output\_stream()**

**Synopsis**      `public org.omg.CORBA.portable.OutputStream create_output_stream()  
                 throws org.omg.CORBA.SystemException;`

**Description**      The `Input/OutputStream` classes provide methods for the reading and writing of all of the mapped IDL types to and from streams. Their implementations are used inside the ORB to marshal parameters and to insert and extract complex data types into and from `Any`s and `Requests`.

The streaming APIs are found in the “Class `org.omg.CORBA.portable.Streamable`” package.

The ORB object is used as a factory to create an output stream. You can create an input stream from an output stream.

### **Return Value**

`OutputStream`      A new `OutputStream` object.

**Notes**      CORBA-defined.

**See Also**      “Class org.omg.CORBA.portable.Streamable” on page 57  
                 “Class org.omg.CORBA.portable.InputStream” on page 53  
                 “Class org.omg.CORBA.portable.OutputStream” on page 55  
                 “Class IE.Iona.OrbixWeb.CORBA.Request” on page 248

### defaultTxTimeout()

**Synopsis**

```
public int defaultTxTimeout(int val)
 throws org.omg.CORBA.SystemException;
```

**Description**

Sets the default timeout (in milliseconds) for all `Requests`, and returns the previous setting. The default is an infinite timeout, which has a value of zero.

This value is ignored when establishing the initial connection to an object. It only comes into affect when the connection has been established.

**Parameters**

|                  |                                                   |
|------------------|---------------------------------------------------|
| <code>val</code> | The new connection timeout value in milliseconds. |
|------------------|---------------------------------------------------|

**Return Value**

|                  |                                             |
|------------------|---------------------------------------------|
| <code>int</code> | The previous <code>Tx</code> timeout value. |
|------------------|---------------------------------------------|

**Notes**

PROGRESS-specific.

**See Also**

`IT_INFINITE_TIMEOUT` in class “Class IE.Iona.OrbixWeb.\_CORBA” on page 343

### finalize()

**Synopsis**

```
public void finalize()
 throws org.omg.CORBA.SystemException;
```

**Description**

You can use this method in a client to clean up the Connections Table. To ensure that all connections are correctly cleaned up, you must call this method before the client exits.

In a server this method is used to call the loaders for all the objects in a process.

If you want to ensure that your objects are correctly saved you *must* call this method before you exit your program. This is because Java does not have destructors and the `finalize()` method for an object is not guaranteed to be called. For each of your objects in the server the `save()` method in class `IE.Iona.OrbixWeb.Features.LoaderClass` is called with the reason set to `'processTermination'` in class `IE.Iona.OrbixWeb._CORBA`.

This method has no effect for in-process servers.

The `finalize()` method is now deprecated. Calls to `finalize()` now call `shutdown()` internally.

**Notes** PROGRESS-specific.

**See Also** “Class `IE.Iona.OrbixWeb.Features.LoaderClass`” on page 319  
“`shutdown()`” on page 129

### **getConfigItem()**

**Synopsis**

```
public String getConfigItem (String name)
 throws org.omg.CORBA.SystemException;
```

**Description** This method gets the value of the configuration property item specified by name.  
For example, the following code:

```
String iiopString = ORB.init().getConfigItem (
 "IT_BIND_USING_IIOP");
boolean iiop = iiopString.equals("true");
```

sets the value of the `iiop` boolean flag to `true` if IIOP is the default protocol.

#### **Parameters**

`name` The name of the property to get the value of.

#### **Return Value**

`String` A `String` representing the value of the specified property.

**Notes** PROGRESS-specific.

**See Also** “`setConfiguration()`” on page 229

### `getConfiguration()`

**Synopsis**

```
public Properties getConfiguration ()
 throws org.omg.CORBA.SystemException;
```

**Description**

Gets the `java.util.Properties` object containing the configuration for this process. See the configuration chapter in the *Orbix Administrator's Guide Java Edition* for further information. This object then allows you to query process configuration.

```
java.util.Properties props = ORB.init().getConfiguration();

String iiopString = props.getProperty (
 "IT_BIND_USING_IIOP");

boolean iiop = iiopString.equals("true");
```

**Return Value**

`Properties`                      The `Properties` object for this process.

**Notes**

PROGRESS-specific

**See Also**

“`getConfigItem()`” on page 206  
“`setConfigItem()`” on page 228

### `getDaemonConnections()`

**Synopsis**

```
public DaemonMgr[] getDaemonConnections ()
 throws org.omg.CORBA.SystemException;
```

**Description**

This method returns an array of Orbix Java daemon client proxies. These daemon manager objects allow processes to query or set (like calling the `putit` and `catit` utilities) information in the Implementation Repository.

It also allows explicit management of Orbix Java daemon connections. For example, most systems have a physical limit on the number of connections you can have open at any given time. It may be necessary to close connections to the daemon, once connections to your servers have been established.

```
import IE.Iona.OrbixWeb.CORBA.DaemonMgr;
// call this method if you have run out of resources
```

```
// and want to free up some connections that are not being used
public static void freeResources() {
 DaemonMgr[] dList =
 _OrbixWeb.ORB(ORB.init()).getDaemonConnections();
 try {
 System.out.println("Calling freeResources : len == " +
 dList.length);

 for(int i = 0; i < dList.length; i++){
 System.out.println(
 "Closing Connection to daemon : host " +
 dList[i]._host());
 _OrbixWeb.ORB(ORB.init()).closeConnection(dList[i]);
 }
 }
 catch(java.lang.NullPointerException e){
 }
}
```

### Return Value

DaemonMgr[]                      An array of Orbix daemon client proxy objects.

**Notes**                      PROGRESS-specific.

**See Also**                    “closeConnection()” on page 194

### **get\_default\_context()**

#### Synopsis

```
public org.omg.CORBA.Context get_default_context()
 throws org.omg.CORBA.SystemException;
```

#### Description

This operation returns a reference to the default process “Class org.omg.CORBA.Context” object. You can then use this for the Context parameter to an invocation.

#### Return Value

context                              The default Context object for this process.



**Notes** CORBA-defined.

**See Also** “Class org.omg.CORBA.ORB” on page 46  
“Class org.omg.CORBA.Context” on page 35  
“Class IE.Iona.OrbixWeb.CORBA.Context” on page 130

### **getHostPort()**

**Synopsis**

```
public int getHostPort(String hostname)
 throws org.omg.CORBA.SystemException;
```

**Description** Get the TCP/IP port on which this process tries to contact the Orbix Java daemon process located at hostname. This method is only relevant when binding to an object using the proprietary Orbix protocol. This method is deprecated.

#### **Parameters**

hostname                      The hostname for the daemon process.

#### **Return Value**

int                              The port number for the daemon process located at hostname.

**Notes** PROGRESS-specific.

**See Also** *Orbix Administrator's Guide Java Edition*

### **get\_my\_principal()**

**Synopsis**

```
public org.omg.CORBA.Principal get_my_principal()
 throws org.omg.CORBA.SystemException;
```

**Description** This method returns the “Class org.omg.CORBA.Principal” user name associated with this process. Orbix Java adds this Principal to outgoing requests by for identification purposes.

#### **Return Value**

Principal                      The username for this process.

**Notes** PROGRESS-specific.

**See Also** “Class org.omg.CORBA.Principal” on page 58  
“Class IE.Iona.OrbixWeb.CORBA.Principal” on page 244  
“Class IE.Iona.OrbixWeb.CORBA.OrbCurrent” on page 237

### **getMyReqTransformer()**

**Synopsis**

```
public IT_reqTransformer getMyReqTransformer()
 throws org.omg.CORBA.SystemException;
```

**Description** The method returns the “Class IE.Iona.OrbixWeb.Features.IT\_reqTransformer” object associated with this process. This `IT_reqTransformer` is applied to all invocations leaving this process.

The `IT_reqTransformer` is a class that receives all invocations just before they leave or immediately after they arrive at an Orbix Java process. This class allows you to modify this incoming or outgoing data.

#### **Return Value**

`IT_reqTransformer` The `IT_reqTransformer` object associated with the current process.

**Notes** PROGRESS-specific.

**See Also** “Class IE.Iona.OrbixWeb.Features.IT\_reqTransformer” on page 316  
“setReqTransformer()” on page 232

### **get\_next\_response()**

**Synopsis**

```
public org.omg.CORBA.Request get_next_response()
 throws org.omg.CORBA.SystemException;
```

**Description** You can call this method to determine the outcome of the individual requests specified in a `send_multiple_requests_oneway()` call. This method blocks until a response is available.

The order in which the replies are returned is not necessarily the same as the order in which they were sent. In a multi-threaded or multi-process environment some requests may be processed faster than others.

### Return Value

Request                      The next available response.

**Notes**                      CORBA-defined.

**See Also**                    “Class org.omg.CORBA.ORB” on page 46

### get\_principal()

**Synopsis**

```
public org.omg.CORBA.Principal get_principal()
 throws org.omg.CORBA.SystemException;
```

**Description**                In a client process this method returns the class `org.omg.CORBA.Principal` username associated with this process. However, in a server process it returns the principal of the client whose `Request` is currently being processed if `IT_MULTI_THREADED_SERVER` configuration parameter is `true`.

### Return Value

Principal                      In a client this is the user name of this process. In a server this returns the user name of the client.

**Notes**                      CORBA-defined.

**See Also**                    “Class org.omg.CORBA.ORB” on page 46  
“Class org.omg.CORBA.Principal” on page 58  
“Class IE.Iona.OrbixWeb.CORBA.OrbCurrent” on page 237

### getTransformer()

**Synopsis**

```
public static IT_reqTransformer getTransformer(String server,
 String host)
 throws org.omg.CORBA.SystemException;
```

**Description**                You can call this method to determine the `IT_reqTransformer` for a specified server and (optionally) a host.

If a process level transformer has been set using the `setMyReqTransformer()` method, this `IT_reqTransformer` object is returned immediately.

Otherwise, if an `IT_reqTransformer` is set for a particular server and host (using the `setReqTransformer()` method), this `IT_reqTransformer` object is returned.

Finally, if a transformer was set for the server only, this `IT_reqTransformer` object is returned.

### Return Value

`IT_reqTransformer`      The requested transformer object for the specified server and (optionally) host.

**Notes**                    PROGRESS-specific.

**See Also**                “Class `IE.Iona.OrbixWeb.Features.IT_reqTransformer`” on page 316

## **get\_principal\_string()**

### Synopsis

```
public String get_principal_string()
 throws org.omg.CORBA.SystemException;
```

### Description

In a client, this method returns the user name (`Principal`) associated with this process in string form. This `Principal` is added to outgoing requests by Orbix Java for identification processes.

In a server, this method returns the user name of the client whose invocation is currently being processed.

### Return Value

`String`                    In a client, the user name associated with this process.  
  
In a server, the user name of the client whose invocation is currently being processed if `IT_MULTI_THREADED_SERVER` is `true` (otherwise, not thread safe).

**Notes**                    PROGRESS-specific.

**See Also**      “Class org.omg.CORBA.ORB” on page 46  
                 “Class IE.Iona.OrbixWeb.CORBA.OrbCurrent” on page 237

### **hasValidOpenChannel()**

**Synopsis**

```
public boolean hasValidOpenChannel (ObjectRef oref)
 throws org.omg.CORBA.SystemException;
public boolean hasValidOpenChannel (org.omg.CORBA.Object oref)
 throws org.omg.CORBA.SystemException;
```

**Description**      This method returns `true` if there is a valid open connection between this process and the process in which the object `Oref` resides.

#### **Parameters**

`oref`                      The object whose connection is checked.

#### **Return Value**

`boolean`                      This is `true` if there is a valid, open connection between this process and the process in which `oref` resides.

**Notes**                      PROGRESS-specific.

### **init()**

**Synopsis**

```
static public org.omg.CORBA.ORB init ()
 throws org.omg.CORBA.SystemException,
 org.omg.CORBA.INITIALIZE;

static public org.omg.CORBA.ORB init (String[] args,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException,
 org.omg.CORBA.INITIALIZE;

static public org.omg.CORBA.ORB init (java.util.Properties props)
 throws org.omg.CORBA.SystemException,
```

```
 org.omg.CORBA.INITIALIZE;
static public org.omg.CORBA.ORB init (java.applet.Applet app,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException,
 org.omg.CORBA.INITIALIZE;
```

**Description** The `init()` method configures the ORB object and returns a reference to the current ORB object.

Order of configurations (in order of increasing priority):

- Defaults
- External configuration file
- Properties
- Applet tags
- Command-line parameters

The `init (String[] args, java.util.Properties props)` method configures using command-line parameters.

The call to initialize Orbix Java from an application's `main()` method is shown in the following code sample. This code also illustrates how an application that wishes to use other command-line parameters can ignore the ORB parameters, because the Orbix Java parameters all start with the string `"-OrbixWeb."`.

```
 // Initialize the ORB.
 try {
 IE.Iona.OrbixWeb.CORBA.ORB.init (args, null);
 }
 catch (Exception ex) {
 System.err.println ("argument error: "+ex);
 System.exit(1);
 }

 // Read in the command-line parameters, and ignore any of
 // the OrbixWeb parameters.

 for (int i = 0; i < args.length; i++) {
 String ignore = "-OrbixWeb.";

```

```
if (args[i].length() < ignore.length() ||
 !(args[i].substring(0, ignore.length()).equalsIgnoreCase
 (ignore))
 {
 // this is a non-OrbixWeb command-line parameter,
 // take appropriate action.
 }
}
// Your application initialization code can continue below...
```

This mechanism allows Orbix Java to search for configuration parameters both in the application command-line arguments, and in the system properties.

The `init(java.util.Properties props)` method configures Orbix Java using system properties.

If you use either of these mechanisms, the added benefit is that you can also use the Java system properties for parameters. However, there is no standard way you can set Java system properties. The JDK, for example, uses a file containing a list of the property names and values, and most browsers do not allow any properties to be set. The most useful way to use this functionality is to pass parameters using the JDK Java interpreter's `-D` command-line argument. This supplements the command-line argument support already shown.

The `init (java.applet.Applet app, java.util.Properties props)` method configures Orbix Java using applet tags.

The call to initialize Orbix Java from inside an applet's `init()` method is as follows:

```
public void init () {
 // Initialize the ORB.
 try {
 IE.Iona.OrbixWeb.CORBA.ORB.init (this, null);
 }
 catch (Exception ex) {
 System.err.println ("bad applet tag: "+ex);
 }
 // Your applet initialization code can continue below...
}
```

The initialization method is passed `this`; the applet object itself.

This mechanism allows Orbix Java to search for configuration parameters both in the applet tags, and in the system properties.

### Singleton ORB

An `ORB.init()` call with no parameters returns an instance of `IE.Iona.OrbixWeb.CORBA.singletonORB`. There is only one instance of the singleton ORB in a virtual machine. The singleton ORB restricted functionality is mainly for applet security reasons. You can call the following operations on the singleton ORB:

```
create_list()
create_named_value()
create_exception_list()
create_context_list()
get_default_context()
create_environment()
create_xxx_tc()
 (where xxx is a defined Typecode type)
get_primitive_tc()
create_any()
create_output_stream()
```

An attempt to call any other ORB operations on the singleton ORB results in a system exception.

### Fully Functional ORB

Any of the forms of `ORB.init()` with parameters returns a new, fully-functional ORB. In earlier versions of Orbix Java, each call in the same VM returns the same ORB (`_CORBA.Orbix`). In this version, each call returns a different new ORB. This adds considerable flexibility to some applications, because each new ORB is completely independent from any other. For example, ORB configuration, connections, listener ports and server object tables are all per-ORB. Multiple ORBs also facilitate applet separation.

#### Notes

CORBA-defined.

#### See Also

`set_parameters()` in “Class `org.omg.CORBA.ORB`” on page 46  
“`getConfigItem()`” on page 206  
“`setConfigItem()`” on page 228  
“`setConfiguration()`” on page 229  
“`getConfigItem()`” on page 206



### isBaseInterfaceOf()

**Synopsis**

```
public boolean isBaseInterfaceOf(String derivedStubClass,
 String maybeABase)
 throws org.omg.CORBA.SystemException;
public boolean isBaseInterfaceOf(org.omg.CORBA.Object obj,
 String maybeABase)
```

**Description**

This method determines whether the interface of the stub class `derivedStubClass` or the object reference `obj` is derived from the interface `maybeABase`.

**Parameters**

|                               |                                            |
|-------------------------------|--------------------------------------------|
| <code>derivedStubClass</code> | Name of the class to check.                |
| <code>obj</code>              | An object reference to the class to check. |
| <code>maybeABase</code>       | Name of the interface to check.            |

**Return Value**

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>boolean</code> | Return <code>true</code> if <code>derivedStubClass</code> or <code>obj</code> is derived from <code>maybeABase</code> . |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**Notes**

PROGRESS-specific.

**See Also**

“Class `org.omg.CORBA.ORB`” on page 46

### list\_initial\_services()

**Synopsis**

```
public String[] list_initial_services()
 throws org.omg.CORBA.SystemException;
```

**Description**

This method returns a list of the available Services. At present only three are available by default:

- The Naming Service (NS).
- The Interface Repository (IFR).
- The Trader Service.

You can add other services using the `IT_INITIAL_REFERENCES` configuration parameter. Refer to the *Orbix Administrator's Guide Java Edition* for details.

### Return Value

String[]                      A list of the currently available services

**Notes**                      CORBA-defined.

**See Also**                    `resolve_initial_references` in “Class `org.omg.CORBA.ORB`” on page 46

### **locator()**

**Synopsis**                    `public final void locator(locatorClass l);`

**Description**                This method enables you to create a user-defined locator. If you do not create a user-defined locator, the Orbix Java default locator mechanism is used when required. If you wish to override the default locator with a new class inheriting from `CORBA.locatorClass`, you should assign an object of your new class to the `locator()` method.

This new locator class is created on a per-ORB basis, enabling support for multiple ORBs.

**Notes**                      PROGRESS-specific.

**See Also**                    “Class `IE.Iona.OrbixWeb.Features.locatorClass`” on page 327

### **makeIOR()**

**Synopsis**                    `public String makeIOR(String ip_addr,  
                                                int port,  
                                                String orbixHost,  
                                                String server,  
                                                String marker,  
                                                String typeID)  
                        throws org.omg.CORBA.SystemException;  
public String makeIOR(String ip_addr,  
                                                int port,  
                                                byte[] objKey,  
                                                String typeID)  
                        throws org.omg.CORBA.SystemException;`

**Description** You can use this method to create a reference to a remote object.

The `ip_addr`, `port` and `typeID` are the respective standard elements of the IOR (Interoperable Object Reference, for use with IIOP). `server`, `marker` and `orbixHost` are fields of the Orbix object reference from which the IOR object key is created. If '`ip_addr`' is null, '`orbixhost`' is also used as the host field of the IOR.

The `objKey` is the opaque object key part of the IOR as required by the CORBA specification. This can be a non-Orbix object Key. The Orbix object key is made up of the `orbixHost`, `server` and `marker`.

### Parameters

|                        |                                                                                                                                                                                                                                                                                                                                                                  |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>ip_addr</code>   | IP address or hostname of the IOR                                                                                                                                                                                                                                                                                                                                |
| <code>port</code>      | TCP/IP port number of the IOR                                                                                                                                                                                                                                                                                                                                    |
| <code>orbixHost</code> | Orbix object reference hostname or IP address.                                                                                                                                                                                                                                                                                                                   |
| <code>server</code>    | The name of the target object's server as registered in the Implementation Repository and also as specified to <code>CORBA.BOA.impl_is_ready()</code> , <code>CORBA.BOA.object_is_ready()</code> or set by <code>setServerName()</code> .                                                                                                                        |
| <code>marker</code>    | The object marker name. This can be chosen by the application, or can be a string of digits chosen by Orbix Java.<br><br>If null, it matches any marker.                                                                                                                                                                                                         |
| <code>typeID</code>    | Orbix object reference object <code>typeID</code> , described in the CORBA Specification section 7.6, as a string of the form “IDL:/<ident1>/<ident2>/.../<identn>:<version number>”. For example, for the grid interface the <code>RepositoryId</code> is "IDL:grid:1.0". If the Helper classes are available, the <code>id()</code> method return this string. |
| <code>objKey</code>    | Opaque object key part of the IOR.                                                                                                                                                                                                                                                                                                                               |

### Return Value

String                      The IOR constructed from the method parameters.

**Notes**                      PROGRESS-specific.

**See Also**                    `object_to_string()` in “Class `org.omg.CORBA.ORB`” on page 46  
“`object_to_string()`” on page 222

### **maxConnectRetries()**

#### **Synopsis**

```
public int maxConnectRetries(int retries)
 throws org.omg.CORBA.SystemException;
```

#### **Description**

This method sets the maximum connection retries and returns the old value. The default value is 5.

If an operation call cannot be made on the first attempt because the transport (for example, TCP/IP) connection cannot be established, Orbix Java retries the attempt every two seconds until either the call can be made or until there are too many retries.

---

**Note:** The value set by `maxConnectRetries()` is ignored when connecting to the Orbix Java daemon. It is only used when connecting to servers.

---

### Return Value

int                              The previous maximum connection retries value.

**Notes**                      PROGRESS-specific.

**See Also**                    *Orbix Administrator's Guide Java Edition*

### `myHost()`

**Synopsis**

```
public java.lang.String myHost()
 throws org.omg.CORBA.SystemException;
```

**Description**

If the variable `IT_IORS_USE_DNS` is set to `false`, returns the local host's IP address.

If the variable `IT_IORS_USE_DNS` is set to `true`, returns the local host's name.

See the *Orbix Administrator's Guide Java Edition* for more details on `IT_IORS_USE_DNS`.

**Notes**

PROGRESS-specific.

### `_nil()`

**Synopsis**

```
public static IE.Iona.OrbixWeb.CORBA.ORB _nil();
```

**Description**

Returns a nil ORB object.

Defined to always be a Java `null` in the IDL-to-Java mapping.

**Notes**

PROGRESS-specific.

### `noReconnectOnFailure()`

**Synopsis**

```
public boolean noReconnectOnFailure(boolean b)
 throws org.omg.CORBA.SystemException;
```

**Description**

When an Orbix Java client first contacts a server, a single communications channel is established between the client-server pair. This connection is used for all subsequent communications between the client and the server (presuming that bidirectional IIOP or the Orbix protocol is used). If you are using pure IIOP and you have callback object in your client, a separate connection is created from the server to the client. The connection is closed only when the client or the server exits, or the client calls `ORB.closeConnection()`.

If a connection from the client to the server is closed, the next invocation by the client (presuming the client is still up) causes the Orbix Java runtime to transparently try to automatically re-establish the connection. This may involve relaunching the server.

You can change this default behavior by passing `true` to the function `ORB.noReconnectOnFailure()`. Then, all client attempts to contact a server subsequent to closure of the communications channel raise an `org.omg.CORBA.COMM_FAILURE` system exception. This behavior is not guaranteed for `oneway` calls.

### Parameters

`b`            True means always return `org.omg.CORBA.COMM_FAILURE` exceptions for invocations after a connection has been closed.  
  
              False means always try to re-establish the connection.

**Return Value**    Returns the previously-set value.

**Notes**            PROGRESS-specific.

### **object\_to\_string()**

#### Synopsis

```
public java.lang.String object_to_string
 (org.omg.CORBA.Object obj);
```

#### Description

Converts an object reference to a string. If `obj` is an Interoperable Object Reference (IOR), the return value is a stringified IOR. If `obj` is an Orbix Java object reference, the resulting `String` conforms to the Orbix communications protocol object reference format.

You do not need to know the structure of an object reference.

#### Parameters

`obj`            The object whose string representation you wish to obtain.

**Notes**            CORBA-defined.

**See Also**        `object_to_string()` in "Class `org.omg.CORBA.ORB`" on page 46  
                  "`string_to_object()`" on page 234

### pingDuringBind()

**Synopsis**

```
public boolean pingDuringBind(boolean pingOn)
 throws org.omg.CORBA.SystemException;
```

**Description**

By default, the `bind()` method (defined in the Helper class for an interface) raises an exception if the object on which the `bind()` is attempted is unknown to Orbix Java. Doing so requires Orbix Java to ping the desired object (the `ping` operation is defined by Orbix Java and it has no effect on the target object). The pinging causes the target server process to be activated if necessary, and confirms that this server recognizes the target object.

You may wish to improve efficiency by disabling pinging, which reduces the overall number of remote invocations. You can disable pinging by using `ORB.pingDuringBind()` and passing `false` to the parameter `pingOn`.

If `pingDuringBind(false)` is called:

- ◆ A `bind()` to an unavailable object does not immediately raise an exception. Subsequent requests using the object reference returned from `bind()` fail by raising the system exception `org.omg.CORBA.INV_OBJREF`.
- ◆ If a hostname is specified to `bind()`, the `bind()` does not itself make any remote calls; it simply sets up a proxy with the required fields.

**Parameters**

`b` Returns the previous setting. The default is `true`.

**Notes**

PROGRESS-specific.

**See Also**

“IT\_PING()” on page 178

### **poll\_next\_response()**

**Synopsis**

```
public boolean poll_next_response()
 throws org.omg.CORBA.SystemException;
```

**Description**

Determines whether or not a response is in the response queue. The method returns immediately. It does not affect the response queue.

Normally used after invoking `ORB.send_multiple_requests_deferred()`. If a response has arrived you can get it by calling `ORB.get_next_response()`.

You can also use `poll_next_response()` when using `Request.send_deferred()`. However, you still have to use `Request.get_response()` to determine whether a response has arrived for a particular request.

If you wish to find out whether a response has been received for a particular request, call `org.omg.CORBA.Request.get_response()` on that `Request` object. Unlike `poll_next_response()`, `Request.get_response()` takes the response off the response queue and unmarshals it.

**Return Value**

`true`     A response has been received.  
`false`    No response has been received.

**Notes**

CORBA-defined.

**See Also**

“`get_next_response()`” on page 210  
“`send_multiple_requests_deferred()`” on page 227  
“`get_response()`” on page 261  
“`send_deferred()`” on page 265

### **reSizeConnectionTable()**

**Synopsis**

```
public void reSizeConnectionTable(int size)
 throws org.omg.CORBA.SystemException;
```

**Description**

Sets the maximum size for the hash table of connection objects to `size`. There is one connection object for every connection between the client and a server process.



If the number of currently-open connections is greater than the maximum size, Orbix Java automatically shuts down the oldest connections until the number of open connections is less than 80% of size.

The default size is 100 and is set by `IT_CONNECT_TABLE_SIZE_DEFAULT`.

### Parameters

`size` The maximum capacity to which you want to resize the connection table.

### Notes

PROGRESS-specific.

### **registerIOCallback()**

### Synopsis

```
public void registerIOCallback
 (IE.Iona.OrbixWeb.CORBA.Features.ioCallback cb)
 throws org.omg.CORBA.SystemException;
```

### Description

Registers an object that implements "Interface `IE.Iona.OrbixWeb.Features.ioCallback`". This object is informed of connection establishment and connection termination events.

A connection is opened when a client first communicates with the server; and it is closed when the client terminates or the communication's level reports a break in service between the server and client.

A client or server application may register a callback object which is informed when either of the two events occur. This callback object must implement the Interface `IE.Iona.OrbixWeb.Features.ioCallback`.

This interface contains the following operations:

```
public void OpenCallBack
 (String serverName, Object conn)
public void CloseCallBack
 (String serverName, Object conn)
```

Only one `ioCallback` object can be registered at a time. If you register a second `ioCallback` object, it replaces the previous `ioCallback` object.

To unregister the `ioCallback` use `unregisterIOCallback()`.

### Parameters

`cb` The `ioCallback` object to be registered. It is informed of any connections being established or broken.

**Notes** PROGRESS-specific.

**See Also** “`unregisterIOCallback()`” on page 236  
“Interface `IE.Iona.OrbixWeb.Features.ioCallback`” on page 313

### **resolve\_initial\_references()**

#### Synopsis

```
public org.omg.CORBA.Object
 resolve_initial_references(java.lang.String serviceName)
 throws org.omg.CORBA.SystemException;
```

#### Description

Returns an object reference through which a service (for example, Interface Repository or a CORBA service such as the Naming Service) can be used.

The list of available services is found calling `list_initial_services()`.

The default list of available services is:

- The Naming Service (NS): “NameService”
- The Interface Repository (IFR): “InterfaceRepository”
- The Trader Service: “TradingService”

You can also add other services using the `IT_INITIAL_REFERENCES` configuration parameter.

This is the CORBA-defined way for obtaining your first object reference. You can also use the Orbix Java value-added method `bind()`.

#### Parameters

`serviceName` The name of the desired service. You can obtain a list of services supported by Orbix Java using `ORB.list_initial_services()`.

**Return Value** Returns an object reference for the desired service. The object reference returned must be narrowed to the correct object type. For example, the object reference returned from resolving the name 'NameService' must be narrowed to the IDL type NamingContext.

**Notes** CORBA-defined.

**See Also** "list\_initial\_services()" on page 217

### **send\_multiple\_requests\_deferred()**

**Synopsis**

```
public void send_multiple_requests_deferred
 (org.omg.CORBA.Request[] req)
 throws org.omg.CORBA.SystemException;
```

**Description** Sends a number of requests in parallel. It does not wait for the requests to finish before returning to the caller.

The caller can use `ORB.get_next_response()`, `ORB.poll_next_response()` and `CORBA.Request.get_response()` to determine the outcome of the requests.

#### **Parameters**

`req` A sequence of Request objects.

**Notes** CORBA-defined.

**See Also** "get\_next\_response()" on page 210  
"poll\_next\_response()" on page 224  
"send\_multiple\_requests\_oneway()" on page 228  
"get\_response()" on page 261  
"send\_deferred()" on page 265

### **send\_multiple\_requests\_oneway()**

**Synopsis**

```
public void send_multiple_requests_oneway
 (org.omg.CORBA.Request[] req)
 throws org.omg.CORBA.SystemException;
```

**Description**

Sends a number of requests in parallel. It does not wait for the requests to finish before returning to the caller.

There is no response to the requests even if the operations being invoked are defined in IDL as two-way operations.

**Parameters**

`req`     A sequence of request objects. The operations in this sequence do not have to be IDL *oneway* operations. The caller does not expect a response, nor does it expect *out* or *inout* parameters to be updated.

**Notes**

CORBA-defined.

**See Also**

“`send_multiple_requests_deferred()`” on page 227  
“`send_oneway()`” on page 265

### **setConfigItem()**

**Synopsis**

```
public void setConfigItem(java.lang.String name,
 java.lang.String value)
 throws org.omg.CORBA.SystemException;
```

**Description**

Sets the configuration parameter `name` to `value`.

Orbix Java applications read in their configuration settings from the Orbix Java configuration files, as specified in `iona.cfg`. Sometimes, however, you may want to change configuration settings dynamically at runtime. Orbix Java provides this method to allow you to do this.

If you want to change multiple settings at the same time you can use `ORB.setConfiguration()`.

See the *Orbix Administrator's Guide Java Edition* for a list of the available configuration settings.

**Notes**

PROGRESS-specific.

**See Also** “getConfigItem()” on page 206  
“setConfiguration()” on page 229

### **setConfiguration()**

**Synopsis**

```
public void setConfiguration
 (java.util.Properties configuration)
 throws org.omg.CORBA.SystemException;
```

**Description** Sets the variables passed in by `configuration`. Any variables not listed in `configuration` remain at their previous (usually the default) value.

Orbix Java applications read in their configuration settings from the Orbix Java configuration files, as specified in `iona.cfg`. Sometimes, however, you may want to change configuration settings dynamically at runtime. Orbix Java provides this method to allow you to do this.

If you want to change individual settings you can use `ORB.getConfigItem()`.

See the *Orbix Administrator's Guide Java Edition* for a list of configuration settings.

**Notes** PROGRESS-specific.

**See Also** “setConfigItem()” on page 228  
“getConfigItem()” on page 206

### **setDiagnostics()**

**Synopsis**

```
public int setDiagnostics(int level)
 throws org.omg.CORBA.SystemException;
```

**Description** Controls the level of diagnostic messages output by Orbix Java. Returns the previous setting. Orbix Java provides diagnostics for various components, each associated with a particular `level`.

**Parameters** The `level` parameter must be in the range of 0–255.

| <b>level</b> | <b>Diagnostics Component</b> |
|--------------|------------------------------|
| 0            | No diagnostics               |
| 1            | LO                           |

|     |            |
|-----|------------|
| 2   | HI         |
| 4   | ORB        |
| 8   | BOA        |
| 16  | PROXY      |
| 32  | REQUEST    |
| 64  | CONNECTION |
| 128 | DETAILED   |

To obtain diagnostics output from particular components, add the values associated with the components together. The values `LO` and `HI` correspond to the diagnostic levels 1 and 2 from earlier versions of Orbix Java, and are provided for backwards compatibility.

The `DETAILED` level is of special significance, as this controls the amount of diagnostics produced by the components. Setting this means that all diagnostics from the selected components are output.

For example, obtaining detailed diagnostics associated with the `BOA` and `Requests`. You can do this by adding  $8 + 32 + 128 = 168$ , and passing this total to `setDiagnostics()`.

You can obtain full diagnostic output by setting the value to 255 (the result of adding all levels together). This produces very comprehensive output including full buffer dumps of messages.

**Return Value** Returns the previous setting.

**Notes** PROGRESS-specific.

### **setHostPort()**

**Synopsis**

```
public void setHostPort(java.lang.String hostname,
 int port)
 throws org.omg.CORBA.SystemException;
```

**Description** Sets the daemon port for a given host, and allows the default port selection to be over-ridden dynamically. This only has effect when binding to an object using the Orbix protocol.

This method is deprecated.

**Notes** PROGRESS-specific.  
**See Also** “getHostPort()” on page 209

### setMyReqTransformer()

**Synopsis**

```
public IE.Iona.OrbixWeb.CORBA.IT_reqTransformer
 setMyReqTransformer
 (IE.Iona.OrbixWeb.CORBA.IT_reqTransformer new_transformer)
 throws org.omg.CORBA.SystemException;
```

**Description** Sets a global request transformer object. It overrides any other transformers that may have been set. Request transformers are an PROGRESS-specific mechanism for encrypting and decrypting requests.

To set a transformer for a particular server on a particular host you can use `ORB.setReqTransformer()`.

For full details on how to use request transformers see the *Orbix Programmer's Guide Java Edition*.

**Return Value** Returns the previous transformer.

**Notes** PROGRESS-specific.

**See Also** “Class IE.Iona.OrbixWeb.Features.IT\_reqTransformer” on page 316  
“getMyReqTransformer()” on page 210  
“setMyReqTransformer()” on page 231  
“setReqTransformer()” on page 232

### set\_parameters()

**Synopsis**

```
public void set_parameters(java.lang.String[] args,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException;
public void set_parametersS(java.applet.Applet app,
 java.util.Properties props)
 throws org.omg.CORBA.SystemException;
```

**Description** Sets the configuration parameters for the current ORB object and can only be called after `ORB.init()` is called at least once.

This method has the same behavior as the `ORB.init()` methods with the same parameters. However, unlike `ORB.init()`, `set_parameters()` does not initialize the ORB object nor does it return an ORB object.

See `init()` for more details.

**Notes** PROGRESS-specific.

**See Also** “`init()`” on page 213

### **set\_principal()**

**Synopsis**

```
public void set_principal(java.lang.String new_user)
 throws org.omg.CORBA.SystemException;
public void set_principal(org.omg.CORBA.Principal new_user)
 throws org.omg.CORBA.SystemException;
```

**Description** This method sets the `Principal` for the client.  
This is a CORBA concept which identifies a client.  
By default it is the client's user name.

**Notes** CORBA-defined.

**See Also** “Class `org.omg.CORBA.Principal`” on page 58  
`get_principal_string()` in  
“Interface `IE.Iona.OrbixWeb.CORBA.BOA`” on page 98  
“`get_principal()`” on page 211  
“Class `IE.Iona.OrbixWeb.CORBA.Principal`” on page 244

### **setReqTransformer()**

**Synopsis**

```
public void setReqTransformer
(IE.Iona.OrbixWeb.CORBA.IT_reqTransformer new_transformer,
 java.lang.String serverName,
 java.lang.String host)
 throws org.omg.CORBA.SystemException;
```

**Description** Registers a request transformer object for a particular server name and host.  
All communication between the client that invokes `setReqTransformer()` and the server on the particular host pass through the registered request transformer.



If `host` is `null`, communications between the client and all servers with the name `serverName`, regardless of host, are subject to the request transformer.

If `serverName` is `null`, the method has no effect.

Request transformers are an PROGRESS-specific mechanism for encrypting and decrypting requests.

To set a global transformer for all communications, you can use `ORB.setMyReqTransformer()`. This overrides any transformers that you may have set using `setReqTransformer()`.

For full details on how to use request transformers refer to the *Orbix Programmer's Reference Java Edition*.

### Parameters

|                              |                                                                                                                                                                                                                              |
|------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>new_transformer</code> | The transformer object to be registered for the given <code>host</code> and <code>serverName</code> .                                                                                                                        |
| <code>serverName</code>      | The server with all communication encrypted and decrypted using <code>new_transformer</code> .                                                                                                                               |
| <code>host</code>            | The <code>host</code> on which the server is registered.<br>If this is <code>null</code> , communication with all servers registered as <code>serverName</code> is decrypted and encrypted by <code>new_transformer</code> . |

**Notes** PROGRESS-specific.

**See Also** “Class `IE.Iona.OrbixWeb.Features.IT_reqTransformer`” on page 316  
“`getMyReqTransformer()`” on page 210  
“`setMyReqTransformer()`” on page 231  
“`setReqTransformer()`” on page 232

### **string\_to\_object()**

|                     |                                                                                                                                                                                                                                                                                                                                                          |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>     | <pre>public org.omg.CORBA.Object string_to_object (java.lang.String s)     throws org.omg.CORBA.SystemException;</pre>                                                                                                                                                                                                                                   |
| <b>Description</b>  | <p>Converts the stringified object reference <i>s</i> to an object reference.</p> <p>No network communication occurs and so you do not know whether or not the target object exists until you invoke upon the object.</p> <p>When the object is invoked upon for the first time, Orbix Java attempts to establish a connection to the target server.</p> |
| <b>Parameters</b>   | <p><i>s</i>                      The object reference in string form to be converted into an object reference.</p>                                                                                                                                                                                                                                       |
| <b>Return Value</b> | Returns an object reference. This is a proxy object if the stringified object references refers to a remote object.                                                                                                                                                                                                                                      |
| <b>Notes</b>        | CORBA-defined.                                                                                                                                                                                                                                                                                                                                           |
| <b>See Also</b>     | “object_to_string()” on page 222<br>_object_to_string() in<br>“Interface IE.Iona.OrbixWeb.CORBA.ObjectRef” on page 168                                                                                                                                                                                                                                   |

### **string\_to\_object()**

|                    |                                                                                                                                                                                                                                                                                                |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>    | <pre>public org.omg.CORBA.Object string_to_object (     java.lang.String host,     java.lang.String IR_host,     java.lang.String ServerName,     java.lang.String marker,     java.lang.String IR_server,     java.lang.String interfaceName)     throws org.omg.CORBA.SystemException;</pre> |
| <b>Description</b> | <p>Creates an object reference from the parameter strings.</p> <p>The parameter strings are the PROGRESS-specific way of specifying an object.</p>                                                                                                                                             |

### Parameters

|                            |                                                                                                    |
|----------------------------|----------------------------------------------------------------------------------------------------|
| <code>host</code>          | The host name of the target object.                                                                |
| <code>IR_host</code>       | The name of a host running an Interface Repository that stores the target object's IDL definition. |
| <code>serverName</code>    | The name of the target object's server.                                                            |
| <code>marker</code>        | The object's marker name.                                                                          |
| <code>IR_server</code>     | The string "IR" or "IFR".                                                                          |
| <code>interfaceName</code> | The target object's interface.                                                                     |

**Return Value** Returns an (Orbix communications protocol format) object reference constructed from the parameters passed to the method.

**Notes** PROGRESS-specific.

**See Also** "object\_to\_string()" on page 222  
`_object_to_string()` in  
"Interface `IE.Iona.OrbixWeb.CORBA.ObjectRef`" on page 168

### **toString()**

**Synopsis**

```
public java.lang.String toString();
```

**Description** You can use this method to test if the `_CORBA.Orbix` object is an ORB or BOA object.

**Return Value** Returns the string "`IE.Iona.OrbixWeb.CORBA.ORB`".

**Notes** PROGRESS-specific.

**See Also** "object\_to\_string()" on page 222  
`_object_to_string()` in  
"Interface `IE.Iona.OrbixWeb.CORBA.ObjectRef`" on page 168

### **unregisterIOCallback()**

- Synopsis**      `public void unregisterIOCallback()`  
                  throws `org.omg.CORBA.SystemException`;
- Description**    Unregisters the `ioCallback` object, if there is one. Has no effect otherwise.  
For more information on `ioCallbacks` see "Interface `IE.Iona.OrbixWeb.Features.ioCallback`".
- Notes**          PROGRESS-specific.
- See Also**        "Interface `IE.Iona.OrbixWeb.Features.ioCallback`" on page 313

## Class IE.Iona.OrbixWeb.CORBA.OrbCurrent

### Synopsis

The `OrbCurrent` object allows a thread processing a `Request` to get context information about the invocation (such as the name of the person making the invocation and the object being invoked). So, for example, in the processing of a invocation you can do the following:

### Using the Current Object

Use of the Orbix Java `Current` object is not restricted to in-process servers but is used internally by the Activator and may have particular value for in-process servers.

If the operations of the `Current` object, or equivalent operations, are used in out-of-process servers, you should set the Orbix Java configurable property `IT_MULTI_THREADED_SERVER` to `true` before calling `ORB.init()` to ensure thread-safe results. You can call operations for the `Current` object within the server to get information about the current server or server operation.

As noted above, it should normally be called from the operation dispatching thread. It can be called in server-side filters and loaders as well as in the operation itself. A reference to the object is returned by `_OrbixWeb.Current()`, and the following operations are relevant:

- `public static org.omg.CORBA.Principal get_principal():` returns the principal of the client that invoked the current request.  
Equivalent to the ORB operation of the same name.
- `public static String get_principal_string():` as `get_principal()`, but in string form.
- `public static org.omg.CORBA.ServerRequest get_request():` get the current DSI request.
- `public static org.omg.CORBA.Object get_object():` return the target object of the current request.
- `public static int get_protocol():` return the protocol in which the current request was transmitted; for example,  
`IIOP = _CORBA.IT_INTEROPERABLE_OR_KIND.`

- `public static java.lang.Object get_socket():` returns an Orbix Java `SocketConnection` class that has access to the connection the current request arrived on.
- `public static String get_server():` returns the server name (equivalent to `_CORBA.Orbix.myServer()`).

### Synopsis

The `OrbCurrent` object allows a thread processing a `Request` to get context information about the invocation (such as the name of the person making the invocation and the object being invoked upon). So, for example, in the processing of a invocation you can do the following:

```
// get the OrbCurrent Object
IE.Iona.OrbixWeb.CORBA.OrbCurrent curr =
 _OrbixWeb.Current();

// show both ways of getting the Principal
//
// 1) get the Principal Object
org.omg.CORBA.Principal p = curr.get_principal();
String name = new String (p.name());
System.out.println("Principal = " + name);

// 2) get the principal string from the
CurrentObject
System.out.println("Principal = " +
 curr.get_principal_string());

// 3) get the current ServerRequest object
org.omg.CORBA.ServerRequest req =
 curr.get_request();
String op_name = req.op_name();
System.out.println(
 "target method (from request) = " + op_name);

// 4) get the target object for this invocation
System.out.println(
 "target object (from OrbCurrent) = " +
 curr.get_object());

// 5) get the current protocol, either IIOP or
// Orbix Protocol
System.out.println("protocol = " +
```

## Class IE.Iona.OrbixWeb.CORBA.OrbCurrent

---

```
 curr.get_protocol());
// 6) get the socket object from which this
// Request came and get the port number from
// that sock object
Object sock = curr.get_socket();
long port = 0;

// if the sock object is an instance of Socket
// then either using IIOP or Orbix Protocol
if(sock instanceof java.net.Socket){
 java.net.Socket conn = (java.net.Socket)sock;
 port = conn.getLocalPort();
}
// otherwise we are using HTTP tunnelling
else if (sock instanceof java.net.URLConnection){
 System.out.println(
 "protocol ==Http tunneling ");
 java.net.URLConnection conn =
 (java.net.URLConnection)sock;
 port = conn.getLocalPort().getURL().getPort();
}
System.out.println("Port num = " + port);

// 7) get the servername
System.out.println("Server = " +
 curr.get_server());
```

To use any of these methods the `IT_MULTI_THREADED_SERVER`, described in the Orbix Java configuration must be set to true.

### CORBA

```
pseudo interface Current { };
```

### Orbix Java

```
public class OrbCurrent extends org.omg.CORBA.Current
{
 public static org.omg.CORBA.Principal get_principal()
 throws org.omg.CORBA.SystemException;
 public static String get_principal_string()
 throws org.omg.CORBA.SystemException;
 public static org.omg.CORBA.ServerRequest get_request()
 throws org.omg.CORBA.SystemException;
 public static org.omg.CORBA.Object get_object()
 throws org.omg.CORBA.SystemException;
 public static int get_protocol()
```

```
 throws org.omg.CORBA.SystemException;
 public static java.lang.Object get_socket()
 throws org.omg.CORBA.SystemException;
 public static String get_server()
 throws org.omg.CORBA.SystemException;
}
```

### **get\_object()**

#### **Synopsis**

```
public static org.omg.CORBA.Object get_object()
 throws org.omg.CORBA.SystemException;
```

#### **Description**

Get the target invocation "Class org.omg.CORBA.Object" associated with this invocation.

#### **Return Value**

org.omg.CORBA.Object    The target Object for this CORBA method invocation.

#### **Notes**

PROGRESS-specific

#### **See Also**

"Class org.omg.CORBA.Current" on page 39  
"Interface org.omg.CORBA.Object" on page 45

### **get\_principal()**

#### **Synopsis**

```
public static org.omg.CORBA.Principal get_principal()
 throws org.omg.CORBA.SystemException;
```

#### **Description**

This method returns the "Class org.omg.CORBA.Principal" object associated with this invocation. This allows the receiving object to establish who invoked the method.

#### **Return Value**

org.omg.CORBA.Principal    An object representing information about the invoker of a method



**Notes** PROGRESS-specific

**See Also** “Class org.omg.CORBA.Principal” on page 58  
“Interface org.omg.CORBA.Object” on page 45

### get\_principal\_string()

**Synopsis**

```
public static String get_principal_string()
 throws org.omg.CORBA.SystemException;
```

**Description** This method returns the principal string of the invoker of a remote invocation

**Return Value**

String                    The invoker of the remote method.

**Notes** PROGRESS-specific

**See Also** “Class org.omg.CORBA.Principal” on page 58  
“Interface org.omg.CORBA.Object” on page 45

### get\_protocol()

**Synopsis**

```
public static int get_protocol()
 throws org.omg.CORBA.SystemException;
```

**Description** This method returns the protocol type associated with this invocation, it will be one of the following:

```
 _CORBA.IT_INTEROPERABLE_OR_KIND
 _CORBA.IT_ORBIX_OR_KIND
```

**Return Value**

int                      The protocol type for this invocation, it is either IIOP or the Orbix protocol.

**Notes** PROGRESS-specific

**See Also**      “Class org.omg.CORBA.Current” on page 39  
                 “IT\_INTEROPERABLE\_OR\_KIND” on page 345  
                 “IT\_ORBIX\_OR\_KIND” on page 345

### **get\_request()**

**Synopsis**      `public static org.omg.CORBA.ServerRequest get_request()  
                 throws org.omg.CORBA.SystemException;`

**Description**    This method returns the “Class org.omg.CORBA.ServerRequest” object associated with this invocation.

**Return Value**    `org.omg.CORBA.ServerRequest`    The ServerRequest object associated with this invocation.

**Notes**          PROGRESS-specific

**See Also**      “Class org.omg.CORBA.Principal” on page 58  
                 “Class org.omg.CORBA.Current” on page 39

### **get\_server()**

**Synopsis**      `public static String get_server()  
                 throws org.omg.CORBA.SystemException;`

**Description**    Get the server name of this server.

**Return Value**    `String`                    The server name.

**Notes**          PROGRESS-specific.

**See Also**      “Class org.omg.CORBA.Current” on page 39  
                 “impl\_is\_ready()” on page 114

### **get\_socket()**

**Synopsis**

```
public static java.lang.Object get_socket()
 throws org.omg.CORBA.SystemException;
```

**Description**

This method returns the connection object associated with this invocation, it is either a connection of type `java.net.URLConnection` (for HTTP tunneling) or `java.lang.Socket`.

**Return Value**

`java.lang.Object`      The connection object for this invocation.

**Notes**

PROGRESS-specific.

**See Also**

“Class `org.omg.CORBA.Current`” on page 39

# Class IE.Iona.OrbixWeb.CORBA.Principal

**Synopsis** Class `Principal` implements the IDL pseudo-interface `Principal`. This represents information about principals (users). This information may be used to provide authentication and access control.

For more details on principals refer to the *Orbix Programmer's Guide Java Edition*

**CORBA**

```
// Pseudo IDL
```

```
pseudo interface Principal {
 attribute sequence<octet> name;
}
```

**Orbix Java**

```
// Java
```

```
public class Principal extends org.omg.CORBA.Principal {
 // Constructors
 public Principal() throws org.omg.CORBA.SystemException;
 public Principal(byte[] name,boolean doCopy)
 throws org.omg.CORBA.SystemException;
 public Principal(String name)
 throws org.omg.CORBA.SystemException;

 // Data accessor/modifier methods
 public byte[] access_name()
 throws org.omg.CORBA.SystemException;
 public byte[] name() throws org.omg.CORBA.SystemException;
 public void name(byte[] name)
 throws org.omg.CORBA.SystemException;
 public String toString()
 throws org.omg.CORBA.SystemException;
};
```

**Notes**

CORBA-defined.

### **Principal()**

|                    |                                                                       |
|--------------------|-----------------------------------------------------------------------|
| <b>Synopsis</b>    | <code>public Principal() throws org.omg.CORBA.SystemException;</code> |
| <b>Description</b> | Default constructor.                                                  |
| <b>Notes</b>       | PROGRESS-specific.                                                    |

### **Principal()**

|                    |                                                                                                                                                                                                                                                 |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>    | <code>public Principal(byte[] name,boolean doCopy)<br/>throws org.omg.CORBA.SystemException;</code>                                                                                                                                             |
| <b>Description</b> | Create a new <code>Principal</code> object identified by <code>name</code> . The second parameter indicates whether the supplied <code>name</code> should be used by the new object or whether a copy of the <code>name</code> should be taken. |

#### **Parameters**

|                     |                                                                                                                                                        |
|---------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>name</code>   | Create a new <code>Principal</code> using this name.                                                                                                   |
| <code>doCopy</code> | If true take a copy of the <code>name</code> parameter, otherwise, let the new <code>Principal</code> object refer to the <code>name</code> parameter. |

|              |                    |
|--------------|--------------------|
| <b>Notes</b> | PROGRESS-specific. |
|--------------|--------------------|

### **Principal()**

|                    |                                                                                      |
|--------------------|--------------------------------------------------------------------------------------|
| <b>Synopsis</b>    | <code>public Principal(String name)<br/>throws org.omg.CORBA.SystemException;</code> |
| <b>Description</b> | Create a new <code>Principal</code> object identified by <code>name</code> .         |

#### **Parameters**

|                   |                                                   |
|-------------------|---------------------------------------------------|
| <code>name</code> | Use this to identify the <code>Principal</code> . |
|-------------------|---------------------------------------------------|

|              |                    |
|--------------|--------------------|
| <b>Notes</b> | PROGRESS-specific. |
|--------------|--------------------|

|                 |                                           |
|-----------------|-------------------------------------------|
| <b>See Also</b> | Other <code>Principal</code> constructors |
|-----------------|-------------------------------------------|

### **access\_name**

**Synopsis** `public byte[] access_name() throws org.omg.CORBA.SystemException;`

**Description** Accessor method that returns the `Principal` name.

**Return Value**

`byte[]` A reference to the actual `Principal` name.

**Notes** PROGRESS-specific.

### **name()**

**Synopsis** `public byte[] name() throws org.omg.CORBA.SystemException;`

**Description** Accessor method used to retrieve the name of a `Principal`.

**Return Value**

`byte[]` A copy of the `Principal` name.

**Notes** CORBA-defined.

### **name()**

**Synopsis** `public void name(byte[] name)  
throws org.omg.CORBA.SystemException;`

**Description** Modifier method to change the name of a `Principal`.

**Parameters**

`name` New name for `Principal` object.

**Notes** CORBA-defined.

## Class IE.Iona.OrbixWeb.CORBA.Principal

---

### toString()

|                     |                                                                                             |        |                            |
|---------------------|---------------------------------------------------------------------------------------------|--------|----------------------------|
| <b>Synopsis</b>     | <pre>public java.lang.String toString()<br/>    throws org.omg.CORBA.SystemException;</pre> |        |                            |
| <b>Description</b>  | Accessor method that returns the Principal name.                                            |        |                            |
| <b>Return Value</b> | <table><tr><td>String</td><td>The actual Principal name.</td></tr></table>                  | String | The actual Principal name. |
| String              | The actual Principal name.                                                                  |        |                            |
| <b>Notes</b>        | PROGRESS-specific.                                                                          |        |                            |

# Class IE.Iona.OrbixWeb.CORBA.Request

## Synopsis

Class `Request` supports the Dynamic Invocation Interface (DII), whereby an application may issue a request for any interface, even if that interface was unknown at the time the application was compiled.

Orbix Java allows invocations, which are instances of class `Request`, to be constructed by specifying at runtime the target object reference, the operation name and the parameters. Such calls are termed *dynamic* because the IDL interfaces used by a program do not have to be *statically* determined at the time the program is designed and implemented.

Individual `Request` objects can be intercepted by `Filter` objects and `IT_reqTransformer` objects. For information on how to use these see the *Orbix Programmer's Guide Java Edition* and "Class `IE.Iona.OrbixWeb.Features.IT_reqTransformer`" on page 316.

---

**Note:** The PROGRESS-specific `extract()` and `insert()` methods are no longer supported.

---

## CORBA

```
// Pseudo IDL
interface Request {
 readonly attribute Object target;
 readonly attribute Identifier operation;
 readonly attribute NVList arguments;
 readonly attribute NamedValue result;
 readonly attribute Environment env;
 readonly attribute ExceptionList exceptions;
 readonly attribute ContextList contexts;
 attribute Context ctx;
 any add_in_arg();
 any add_named_in_arg(in string name);
 any add_inout_arg();
 any add_named_inout_arg(in string name);
 any add_out_arg();
 any add_named_out_arg(in string name);
 void set_return_type(in TypeCode tc);
 any return_value();
}
```



## Class IE.Iona.OrbixWeb.CORBA.Request

---

```
void invoke();
void send_oneway();
void send_deferred();
void get_response();
boolean poll_response();
};

Orbix Java public class Request extends org.omg.CORBA.Request {

// Constructors
 public Request();
 throws org.omg.CORBA.SystemException;
 public Request(IE.Iona.OrbixWeb.CORBA.ObjectRef target);
 throws org.omg.CORBA.SystemException;
 public Request(IE.Iona.OrbixWeb.CORBA.ObjectRef target,
 java.lang.String operationName);
 throws org.omg.CORBA.SystemException;

 public static Request _nil();
 throws org.omg.CORBA.SystemException;

// Accessor Methods
 public java.lang.String operation();
 throws org.omg.CORBA.SystemException;
 public void setOperation(java.lang.String operationName);
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.Object target();
 throws org.omg.CORBA.SystemException;
 public void setTarget(org.omg.CORBA.Object target);
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.NVList arguments();
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.NamedValue result();
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.Environment env();
 throws org.omg.CORBA.SystemException;
 public void env(org.omg.CORBA.Environment env);
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.ExceptionList exceptions();
 throws org.omg.CORBA.SystemException;
 public void exceptions(org.omg.CORBA.ExceptionList exceptions);
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.ContextList contexts();
```

```
 throws org.omg.CORBA.SystemException;
public void contexts(org.omg.CORBA.ContextList contexts);
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Context ctx();
 throws org.omg.CORBA.SystemException;
public void ctx(org.omg.CORBA.Context c);
 throws org.omg.CORBA.SystemException;

// Object reuse methods
public void reset();
 throws org.omg.CORBA.SystemException;
public void reset(org.omg.CORBA.Object target);
 throws org.omg.CORBA.SystemException;
public void reset(java.lang.String operationName);
 throws org.omg.CORBA.SystemException;
public void reset(org.omg.CORBA.Object target,
 java.lang.String operationName);
 throws org.omg.CORBA.SystemException;

// Argument manipulation methods
public void add_arg(java.lang.String name,
 org.omg.CORBA.Any a, int flag);
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any add_in_arg();
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any add_inout_arg();
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any add_out_arg();
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any add_named_in_arg
 (java.lang.String name);
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any add_named_out_arg
 (java.lang.String name);
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any add_named_inout_arg
 (java.lang.String name);
 throws org.omg.CORBA.SystemException;
public void set_return_type(org.omg.CORBA.TypeCode tc);
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.Any return_value();
 throws org.omg.CORBA.SystemException;
```

## Class IE.Iona.OrbixWeb.CORBA.Request

---

```
// Invocation methods
public void invoke();
 throws org.omg.CORBA.SystemException;
public void send_deferred();
 throws org.omg.CORBA.SystemException;
public void send_oneway();
 throws org.omg.CORBA.SystemException;
public boolean isDynamic();
 throws org.omg.CORBA.SystemException;
public void get_response();
 throws org.omg.CORBA.SystemException;
public boolean poll_response();
 throws org.omg.CORBA.SystemException;
public boolean isException();
 throws org.omg.CORBA.SystemException;
public java.lang.Exception _getException();
 throws org.omg.CORBA.SystemException;
public boolean isOneWay();
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.portable.InputStream
 create_input_stream();
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.portable.OutputStream
 create_output_stream();
 throws org.omg.CORBA.SystemException;
public java.lang.Object getClientConnection();
 throws org.omg.CORBA.SystemException;
public int getMessageLength();
 throws org.omg.CORBA.SystemException;

// ServiceContext methods
public ServiceContext getServiceContext(int id);
 throws org.omg.CORBA.SystemException;
public void addServiceContext(ServiceContext ctx);
 throws org.omg.CORBA.SystemException;
public ServiceContext[] getSCL();
 throws org.omg.CORBA.SystemException;
public setSCL(ServiceContext[] scl);
 throws org.omg.CORBA.SystemException;
public void deleteSCL();
 throws org.omg.CORBA.SystemException;
}
```

**Notes** CORBA-defined.

**See Also** “Class IE.Iona.OrbixWeb.Features.Filter” on page 301  
“Class IE.Iona.OrbixWeb.Features.AuthenticationFilter” on page 297  
“Class IE.Iona.OrbixWeb.Features.ThreadFilter” on page 337  
“Class IE.Iona.OrbixWeb.Features.IT\_reqTransformer” on page 316

### **Request()**

**Synopsis** `public Request();`

**Description** Default constructor. The target object and the operation name for the request should be filled in.

**Notes** PROGRESS-specific.

**See Also** `create_request()` and `_request()` in  
“Interface org.omg.CORBA.Object” on page 45

### **Request()**

**Synopsis** `public Request(IE.Iona.OrbixWeb.CORBA.ObjectRef target);`

**Description** Constructs a `Request` by specifying its target object's reference. You can set the operation name for the request using `Request.setOperation()`.

#### **Parameters**

`target`                    The object which is the target of the request.

**Notes** PROGRESS-specific.

**See Also** `create_request()` and `_request()` in  
“Interface org.omg.CORBA.Object” on page 45  
“setOperation()” on page 266

### Request()

- Synopsis**      `public Request(IE.Iona.OrbixWeb.CORBA.ObjectRef target  
                  java.lang.String operationName);`
- Description**    Constructs a `Request` by specifying its target object's reference and the required operation name.
- Parameters**
- |                            |                                               |
|----------------------------|-----------------------------------------------|
| <code>target</code>        | The object that is the target of the request. |
| <code>operationName</code> | The operation name for the request.           |
- Notes**          PROGRESS-specific.
- See Also**       `create_request()` and `_request()` in  
                  "Interface `org.omg.CORBA.Object`" on page 45

### add\_arg()

- Synopsis**      `public void add_arg(java.lang.String name,  
                          org.omg.CORBA.Any a,  
                          int flag);`
- Description**    Adds the contents of the `Any` (not the `Any` itself) as a parameter to the `Request`. For `out` and `inout` parameters the `Any` itself is updated with the returned value.
- Parameters**
- |                   |                                                                                                |
|-------------------|------------------------------------------------------------------------------------------------|
| <code>name</code> | A programmer description of the argument being passed into the <code>Request</code> .          |
| <code>a</code>    | The value to be added to the <code>Request</code> object.                                      |
| <code>flag</code> | Specifies whether the argument is <code>in</code> , <code>out</code> , or <code>inout</code> . |
- Notes**          PROGRESS-specific.
- See Also**       "Class `org.omg.CORBA.ARG_IN`" on page 99  
                  "Class `org.omg.CORBA.ARG_INOUT`" on page 30  
                  "Class `org.omg.CORBA.ARG_OUT`" on page 31  
                  Other `add_arg` methods

### **add\_in\_arg()**

- Synopsis** `public org.omg.CORBA.Any add_in_arg();`
- Description** Creates an instance of `org.omg.CORBA.Any` as a holder for an `in` parameter for the `Request` object. You insert the `in` parameter value into the returned `Any` object.
- Return Value** Returns the constructed `Any`.
- Notes** CORBA-defined.
- See Also** Other `add_arg` methods

### **add\_inout\_arg()**

- Synopsis** `public org.omg.CORBA.Any add_inout_arg();`
- Description** Creates an instance of `org.omg.CORBA.Any` as a holder for an `inout` parameter for the `Request` object. The client code must insert the `inout` parameter value into the `Any` object. When the request is invoked the server may change the contents of the `Any`. The `Any` is updated when the reply is received. The client can then examine the `Any` for the updated value.
- Return Value** Returns the constructed `Any`.
- Notes** CORBA-defined.
- See Also** Other `add_arg` methods

### **add\_named\_in\_arg()**

- Synopsis** `public org.omg.CORBA.Any add_named_in_arg(java.lang.String name);`
- Description** Creates an instance of `org.omg.CORBA.Any` as a holder for an `in` parameter for the `Request` object. You insert the `in` parameter value into the returned `Any` object.
- Parameters**
- |                   |                                                                                 |
|-------------------|---------------------------------------------------------------------------------|
| <code>name</code> | A programmer description of the argument passed into the <code>Request</code> . |
|-------------------|---------------------------------------------------------------------------------|

**Return Value** Returns the constructed `Any`.

**Notes** CORBA-defined.

**See Also** Other `add_arg` methods

### **add\_named\_inout\_arg()**

**Synopsis**

```
public org.omg.CORBA.Any add_named_inout_arg(java.lang.String name);
```

**Description** Creates an instance of `org.omg.CORBA.Any` as a holder for an `inout` parameter for the `Request` object. The client code must insert the `inout` parameter value into the `Any` object. When the request is invoked the server may change the contents of the `Any`. The `Any` is updated when the reply is received. The client can then examine the `Any` for the updated value.

#### **Parameters**

`name` A programmer description of the argument passed into the `Request`.

**Return Value** Returns the constructed `Any`.

**Notes** CORBA-defined

**See Also** Other `add_arg` methods

### **add\_named\_out\_arg()**

**Synopsis**

```
public org.omg.CORBA.Any add_named_out_arg(java.lang.String name);
```

**Description** Creates an instance of `org.omg.CORBA.Any` as a holder for an `out` parameter for the `Request` object. When the request is invoked the server may change the contents of the `Any`. The `Any` is updated when the reply is received. The client can then examine the `Any` for the returned value.

#### **Parameters**

`name` A programmer description of the argument passed into the `Request`

**Return Value** Returns the constructed `Any`.

**Notes** CORBA-defined.

**See Also** Other `add_arg` methods

### **add\_out\_arg()**

**Synopsis**

```
public org.omg.CORBA.Any add_out_arg();
```

**Description** Creates an instance of `org.omg.CORBA.Any` as a holder for an `out` parameter for the `Request` object. When the request is invoked the server may change the contents of the `Any`. The `Any` will be updated when the reply is received. The client can then examine the `Any` for the returned value.

**Return Value** Returns the constructed `Any`.

**Notes** CORBA-defined.

**See Also** Other `add_arg` methods

### **arguments()**

**Synopsis**

```
public org.omg.CORBA.NVList arguments();
```

**Description** Returns the arguments to the `Request`'s operation in an `NVList`.

**Notes** CORBA-defined.

**See Also** “Class `org.omg.CORBA.NVList`” on page 44

### **contexts()**

**Synopsis**

```
public org.omg.CORBA.ContextList contexts();
```

**Description** Returns the contexts for the `Request`'s operation in a `ContextList`.

**Notes** CORBA-defined.

**See Also** “Class `org.omg.CORBA.ContextList`” on page 37  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248



### contexts()

- Synopsis** `public void contexts(org.omg.CORBA.ContextList contexts);`
- Description** Sets the list of contexts for the Request's operation.
- Notes** PROGRESS-specific.
- See Also** "Class org.omg.CORBA.ContextList" on page 37  
"Class org.omg.CORBA.Request" on page 59  
"Class IE.Iona.OrbixWeb.CORBA.Request" on page 248

### create\_input\_stream()

- Synopsis** `public org.omg.CORBA.portable.InputStream create_input_stream();`
- Description** Returns a new `InputStream` object for accessing data contained within the Request object.
- This method is useful when piggy-backing with filters.
- Notes** PROGRESS-specific.
- See Also** "Class org.omg.CORBA.portable.InputStream" on page 53  
"Class IE.Iona.OrbixWeb.Features.Filter" on page 301  
"create\_output\_stream()" on page 257

### create\_output\_stream()

- Synopsis** `public org.omg.CORBA.portable.OutputStream create_output_stream();`
- Description** Returns a new `OutputStream` object for inputting data contained into the Request object.
- This method is useful when piggy-backing with filters.
- Notes** PROGRESS-specific.
- See Also** "Class org.omg.CORBA.portable.OutputStream" on page 55  
"Class IE.Iona.OrbixWeb.Features.Filter" on page 301  
"create\_input\_stream()" on page 257

### **ctx()**

- Synopsis** `public org.omg.CORBA.Context ctx();`
- Description** Returns the `Context` object for the `Request`.
- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.Context`” on page 35

### **ctx()**

- Synopsis** `public void ctx(org.omg.CORBA.Context c);`
- Description** Inserts the `Context` object `c` into the `Request`.
- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.Context`” on page 35  
“Class `org.omg.CORBA.Request`” on page 59

### **env()**

- Synopsis** `public org.omg.CORBA.Environment env();`
- Description** Returns the `Environment` object for the `Request`. After the `Request` is invoked upon the `Environment` object, contains any `Exception` object thrown during the invocation.
- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.Environment`” on page 41  
“Class `IE.Iona.OrbixWeb.CORBA.Environment`” on page 145

### **env()**

- Synopsis** `public void env(org.omg.CORBA.Environment env);`
- Description** Inserts the `Environment` object `env` into the `Request`.
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.Environment`” on page 41  
“Class `IE.Iona.OrbixWeb.CORBA.Environment`” on page 145  
“Class `org.omg.CORBA.Request`” on page 59

### **exceptions()**

- Synopsis** `public org.omg.CORBA.ExceptionList exceptions();`
- Description** Returns the list of user-defined exceptions that the `Request` object understands. After the `Request` is invoked the `Environment` object, contains any `Exception` object thrown during the invocation.
- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.Environment`” on page 41  
“Class `org.omg.CORBA.ExceptionList`” on page 42  
“Class `IE.Iona.OrbixWeb.CORBA.Environment`” on page 145  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248

### **exceptions()**

- Synopsis** `public void exceptions(org.omg.CORBA.ExceptionList exceptions);`
- Description** Sets the list of `Exception` classes that the `Request` object understands for the current invocation.
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.ExceptionList`” on page 42  
“Class `org.omg.CORBA.Request`” on page 59

### **getClientConnection()**

- Synopsis** `public java.lang.Object getClientConnection();`
- Description** Returns the socket object for the `Request` object's connection. This is either a `java.net.Socket` or `java.net.URLConnection` object depending on the type of connection established.
- Notes** PROGRESS-specific.
- See Also** "Interface `IE.Iona.OrbixWeb.Features.ioCallback`" on page 313

### **getException()**

- Synopsis** `public java.lang.Exception _getException();`
- Description** If an exception has been raised when invoking the `Request` object `_getException` returns the `Exception` object thrown.
- This method is deprecated in favour of using the CORBA-defined `Request.env().exception()`
- Notes** PROGRESS-specific.
- See Also** "Class `org.omg.CORBA.Environment`" on page 41  
"Class `org.omg.CORBA.Request`" on page 59

### **getMessageLength()**

- Synopsis** `public int getMessageLength();`
- Description** Returns the size of the buffer in the `Request` object.
- You can use this function in conjunction with filters to monitor the volume of traffic into your server.
- Notes** PROGRESS-specific.
- See Also** "Class `IE.Iona.OrbixWeb.CORBA.Request`" on page 248

### **get\_response()**

- Synopsis** `public void get_response();`
- Description** Determines whether a request has completed successfully. The call blocks until the `Request` (invoked using `send_deferred()`) has completed.
- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.Request`” on page 59  
“`env()`” on page 259  
“`result()`” on page 264  
“`send_deferred()`” on page 265

### **invoke()**

- Synopsis** `public void invoke();`
- Description** Instructs Orbix Java to invoke the request. The parameters to the request must already be set up. The caller is blocked until the request has been processed by the target object, or until an exception occurs.
- To make a non-blocking request, see  
`IE.Iona.OrbixWeb.CORBA.Request.send_deferred()` and  
`IE.Iona.OrbixWeb.CORBA.Request.send_oneway()`.
- Notes** CORBA-defined.
- See Also** “Class `org.omg.CORBA.Request`” on page 59  
“`env()`” on page 259  
“`result()`” on page 264  
“`send_deferred()`” on page 265  
“`send_oneway()`” on page 265

### **isDynamic()**

- Synopsis** `public boolean isDynamic();`
- Description** Returns `true` or `false` depending on whether or not the `Request` object has been invoked by the DII.
- It only makes sense to use this in conjunction with filter points.
- Notes** PROGRESS-specific.
- See Also** “Class `IE.Iona.OrbixWeb.Features.Filter`” on page 301

### **isException()**

- Synopsis** `public boolean isException();`
- Description** Returns `true` or `false` depending on whether or not the `Request` object contains an exception object.
- This method is deprecated in favour of using the CORBA-defined `org.omg.CORBA.Request.env()`.
- Notes** PROGRESS-specific.
- See Also** `env()` in “Class `org.omg.CORBA.Request`” on page 59  
“`env()`” on page 259

### **\_nil()**

- Synopsis** `public org.omg.CORBA.Request _nil();`
- Description** Returns a `null`.
- Notes** CORBA-defined.

### operation()

- Synopsis**      `public java.lang.String operation();`
- Description**      Returns the request's operation.
- Notes**            CORBA-defined.
- See Also**        “setOperation()” on page 266

### poll\_response()

- Synopsis**      `public boolean poll_response();`
- Description**      Checks to see if a reply has been received for a deferred invocation upon a Request object. If the reply has arrived, `poll_reponse` automatically updates the Request object.
- Notes**            CORBA-defined.
- See Also**        `getResponse()`, `result()`, and `send_deferred()` in  
“Class org.omg.CORBA.Request” on page 59  
“get\_response()” on page 261  
“result()” on page 264  
“send\_deferred()” on page 265

### reset()

- Synopsis**      `public void reset();`  
`public void reset(org.omg.CORBA.object target);`  
`public void reset(java.lang.String operationName);`  
`public void reset(org.omg.CORBA.object target,`  
                  `java.lang.String operationName);`
- Description**      Allows the Request object to be reused. This can be particularly useful if you have a whole batch of requests to be invoked upon the same object or if you have a batch of objects on which you wish to invoke the same operation.
- The previous `target` or `operationName` is reused if you do not use a version of `reset()` that specifies a new `target`, or `operation`, or both.
- Although you can reuse the `targets` and `operationNames`, you must always refresh the arguments being passed to the Request. Arguments cannot be reused.

### Parameters

|                            |                                                                                                                                 |
|----------------------------|---------------------------------------------------------------------------------------------------------------------------------|
| <code>target</code>        | The target object on which the <code>Request</code> is invoked. If this is not specified, the previous target object is reused. |
| <code>operationName</code> | The operation to be invoked upon the target object. If this is not specified, the previous operation is reused.                 |

**Notes** PROGRESS-specific.

**See Also** “Request()” on page 252  
“setTarget()” on page 267  
“setOperation()” on page 266

### **result()**

**Synopsis** `public org.omg.CORBA.NamedValue result();`

**Description** Returns the `Request`'s result as a `NamedValue` object. It only makes sense to call this method after a `Request` has been invoked and has returned.

**Notes** CORBA-defined.

**See Also** “Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248

### **return\_value()**

**Synopsis** `public org.omg.CORBA.Any return_value();`

**Description** Returns the `Request`'s result as an `Any`. It only makes sense to call this method after a `Request` has been invoked and has returned.

This method is preferred over `IE.Iona.OrbixWeb.CORBA.result()`.

**Notes** CORBA-defined.



### `send_deferred()`

**Synopsis**

```
public void send_deferred();
```

**Description**

Instructs Orbix Java to invoke the request in a non-blocking fashion. The parameters to the request must already be set up. As you, the caller, are not blocked you may continue to do work in parallel with the target object's processing of the call.

The caller can use the method `org.omg.CORBA.Request.poll_response()` to determine whether the operation completed.

You should use the method `org.omg.CORBA.Request.get_response()` to determine the outcome of the request.

To make a blocking request, refer to the `invoke()` method in “Class `org.omg.CORBA.Request`” on page 59.

To send multiple deferred requests, refer to the `multiple_requests_deferred` method in “Class `org.omg.CORBA.ORB`” on page 46.

**Notes**

CORBA-defined.

**See Also**

`getResponse()`, `invoke()`, `poll_response()`, and `send_oneway()` in “Class `org.omg.CORBA.Request`” on page 59  
“`get_response()`” on page 261  
“`invoke()`” on page 261  
“`poll_response()`” on page 263  
“`send_oneway()`” on page 265

### `send_oneway()`

**Synopsis**

```
public void send_oneway();
```

**Description**

Instructs Orbix Java to invoke a `oneway` request.

You can use this method even if the operation has not been defined to be `oneway` in its IDL definition. The caller should not expect any `in` or `inout` parameters to be updated.

The parameters to the request must already be set up before making the call. The caller is not blocked, and can continue to work in parallel with the target object's processing of the call.

To make a blocking request, see `CORBA.Request.invoke()`.

**Notes** PROGRESS-specific.

**See Also** `getResponse()`, `invoke()`, `poll_response()`, and `send_deferred()` in “Class `org.omg.CORBA.Request`” on page 59  
“`get_response()`” on page 261  
“`invoke()`” on page 261  
“`poll_response()`” on page 263  
“`send_deferred()`” on page 265

### **setOperation()**

**Synopsis** `public void setOperation(java.lang.String operationName);`

**Description** Sets the operation for the `Request` object.

**Notes** PROGRESS-specific.

**See Also** `create_request()`, `request()`, and `operation()` in “Class `org.omg.CORBA.Request`” on page 59  
“`operation()`” on page 263

### **set\_return\_type()**

**Synopsis** `public void set_return_type(org.omg.CORBA.TypeCode tc);`

**Description** Sets the `TypeCode` for the return type of the `Request` object.

**Notes** CORBA-defined.

**See Also** `result()` and `return_value()` in “Class `org.omg.CORBA.Request`” on page 59  
“`result()`” on page 264  
“`return_value()`” on page 264

### setTarget()

- Synopsis** `public void setTarget(org.omg.CORBA.object target);`
- Description** Sets the target CORBA object for the Request.
- Notes** PROGRESS-specific.
- See Also** `create_request()` and `target()` in “Class org.omg.CORBA.Request” on page 59  
`request()` in “Interface org.omg.CORBA.Object” on page 45.  
“reset()” on page 263

### target()

- Synopsis** `public org.omg.CORBA.Object target();`
- Description** Returns the target CORBA object for the Request.
- Notes** CORBA-defined
- See Also** `_create_request()` in “Interface org.omg.CORBA.Object” on page 45  
`_request()` in “Interface org.omg.CORBA.Object” on page 45  
`target()` in “Class org.omg.CORBA.Request” on page 59  
“reset()” on page 263

# Class **IE.Iona.OrbixWeb.CORBA.singletonORB**

## **Synopsis**

The IDL to Java mapping distinguishes between a fully-functional ORB and a singleton ORB with restricted functionality. Earlier versions of Orbix Java do not make this distinction. In this version however, there are important differences between these ORB types, compliant with the revised mapping. The type of ORB that `ORB.init()` returns depends on whether the call has parameters.

## **Singleton ORB**

An `ORB.init()` call with no parameters returns an instance of a singleton ORB. There is only one instance of the singleton ORB in a virtual machine. The singleton ORB's restricted functionality is mainly for security reasons in applets. You can call the following operations on the singleton ORB:

- `create_list()`
- `create_named_value()`
- `create_exception_list()`
- `create_context_list()`
- `get_default_context()`
- `create_environment()`
- `create_xxx_tc()`  
(where xxx is a defined `Typecode` type)
- `get_primitive_tc()`
- `create_any()`
- `create_output_stream()`

An attempt to call any other ORB operations on the singleton ORB results in a system exception.

## **Fully Functional ORB**

Any of the forms of `ORB.init()` with parameters returns a new, fully functional ORB. In earlier versions of Orbix Java, each call in the same VM returns the same ORB (`_CORBA.Orbix`). In this version each call returns a different new ORB. This adds considerable flexibility to some applications, as each new ORB

is completely independent from any other. For example, in its configuration, connections, listener ports and server object tables. Multiple ORBs also facilitate applet separation.

### CORBA

```
// Pseudo IDL

pseudo interface ORB {

// Creation methods
 NVList create_list(in long count);
 NamedValue create_named_value(in String name,
 in Any value,
 in Flags flags);
 ExceptionList create_exception_list();
 ContextList create_context_list();
 Context get_default_context();
 Environment create_environment();
 Any create_any();
 OutputStream create_output_stream();
 // Typecode creation
 TypeCode create_struct_tc
 (in RepositoryId id,
 in Identifier name,
 in StructMemberSeq members);
 TypeCode create_union_tc
 (in RepositoryId id,
 in Identifier name,
 in TypeCode discriminator_type,
 in UnionMemberSeq members);
 TypeCode create_enum_tc
 (in RepositoryId id,
 in Identifier name,
 in EnumMemberSeq members);
 TypeCode create_alias_tc
 (in RepositoryId id,
 in Identifier name,
 in TypeCode original_type);
 TypeCode create_exception_tc
 (in RepositoryId id,
 in Identifier name,
 in StructMemberSeq members);
 TypeCode create_interface_tc
 (in RepositoryId id,
```

```
 in Identifier name);
TypeCode create_string_tc
 (in unsigned long bound);
TypeCode create_wstring_tc
 (in unsigned long bound);
TypeCode create_sequence_tc
 (in unsigned long bound,
 in TypeCode element_type);
TypeCode create_recursive_sequence_tc
 (in unsigned long bound,
 in unsigned long offset);
TypeCode create_array_tc
 (in unsigned long length,
 in TypeCode element_type);
TypeCode get_primitive_tc(in TCKind tcKind);
```

### Orbix Java

```
public class ORB extends org.omg.CORBA.ORB {
 public org.omg.CORBA.Any create_any()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.ContextList create_context_list()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.Environment create_environment()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.ExceptionList create_exception_list()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.NVLList create_list(int count)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.NamedValue create_named_value(
 String name,
 org.omg.CORBA.Any value,
 int flags)
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.portable.OutputStream create_output_stream()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.Context get_default_context()
 throws org.omg.CORBA.SystemException;
 public org.omg.CORBA.TypeCode get_primitive_tc(
 org.omg.CORBA.TCKind tcKind)
 throws org.omg.CORBA.SystemException;
```

**Notes** CORBA-defined.  
**See Also** “Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184

### **create\_any()**

**Synopsis**

```
public org.omg.CORBA.Any create_any()
 throws org.omg.CORBA.SystemException;
```

  
**Description** Creates a new empty “Class IE.Iona.OrbixWeb.CORBA.Any”.  
**Return Value**  

```
org.omg.CORBA.Any
```

 The new Any.

**Notes** CORBA-defined  
**See Also** “Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184  
“Class IE.Iona.OrbixWeb.CORBA.Any” on page 81

### **create\_context\_list()**

**Synopsis**

```
public org.omg.CORBA.ContextList create_context_list()
 throws org.omg.CORBA.SystemException;
```

  
**Description** When making an invocation using the DII on an IDL operation that has a Context specified, you must pass a ContextList parameter to the `_create_request()` method in “Interface org.omg.CORBA.Object” on page 45. This method allows you to create an empty “Class org.omg.CORBA.ContextList”.  
**Return Value**  

```
contextList
```

 An empty contextList object.

**Notes** CORBA-defined.  
**See Also** “Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184  
“Class org.omg.CORBA.ORB” on page 46  
“Class org.omg.CORBA.ContextList” on page 37  
“Class IE.Iona.OrbixWeb.CORBA.ContextList” on page 139

“Class IE.Iona.OrbixWeb.CORBA.Request” on page 248

“Class org.omg.CORBA.Context” on page 35

`_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### **create\_environment()**

#### **Synopsis**

```
public org.omg.CORBA.Environment create_environment()
 throws org.omg.CORBA.SystemException;
```

#### **Description**

The “Class org.omg.CORBA.Environment” object is used with the DII to allow exception information to be returned from an operation invocation. This method creates a new empty `Environment` object that you can use as a parameter to the `_create_request()` method in “Interface org.omg.CORBA.Object” on page 45.

#### **Return Value**

`Environment`            A new empty `Environment` object.

#### **Notes**

CORBA-defined.

#### **See Also**

“Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184

“Class org.omg.CORBA.ORB” on page 46

“Class org.omg.CORBA.ContextList” on page 37

“Class IE.Iona.OrbixWeb.CORBA.Request” on page 248

“Class IE.Iona.OrbixWeb.CORBA.Environment” on page 145

“Class org.omg.CORBA.Environment” on page 41

`_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### **create\_exception\_list()**

#### **Synopsis**

```
public org.omg.CORBA.ExceptionList create_exception_list()
 throws org.omg.CORBA.SystemException;
```

#### **Description**

A “Class org.omg.CORBA.ExceptionList” is used by the DII to describe the exceptions that can be raised by IDL operations. This method creates an empty `ExceptionList` to be inserted into the `Request`.



### Return Value

`ExceptionList`      An empty `ExceptionList`.

**Notes**      CORBA-defined.

**See Also**      “Class `org.omg.CORBA.ExceptionList`” on page 42  
“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184  
“Class `org.omg.CORBA.ORB`” on page 46  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248  
“Class `IE.Iona.OrbixWeb.CORBA.Environment`” on page 145  
“Class `org.omg.CORBA.Environment`” on page 41  
`_create_request()` method in “Interface `org.omg.CORBA.Object`” on page 45

### **create\_list()**

**Synopsis**

```
public org.omg.CORBA.NVList create_list(int count)
 throws org.omg.CORBA.SystemException;
```

**Description**      Creates an empty “Class `org.omg.CORBA.NVList`” for use as a parameter type or for use as a way to describe the parameters to an operation invocation when using the `_create_request()` method in “Interface `org.omg.CORBA.Object`” on page 45.

`add_item()` is the only way to add an item to an `NVList`. `get_length()` returns number of times `add_item()` was called. The `NVList` always starts with element number 0.

### Parameters

`count`      The size of the `NVList` to create.

### Return Value

`NVList`      The empty `NVList` returned by this method.

**Notes**      CORBA-defined.

**See Also**      “Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184  
“Class `org.omg.CORBA.ORB`” on page 46  
“Class `org.omg.CORBA.NVList`” on page 44

“Class IE.Iona.OrbixWeb.CORBA.NVList” page 158

“Class IE.Iona.OrbixWeb.CORBA.Request” on page 248

`_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### **create\_named\_value()**

#### **Synopsis**

```
public org.omg.CORBA.NamedValue create_named_value(
 String name,
 org.omg.CORBA.Any value,
 int flags)
 throws org.omg.CORBA.SystemException;
```

#### **Description**

Create an empty “Class org.omg.CORBA.NamedValue”. This can be inserted into a “Class IE.Iona.OrbixWeb.CORBA.NVList” when using the DII as one of the parameters to the operation invocation.

#### **Parameters**

|       |                                                          |
|-------|----------------------------------------------------------|
| name  | The name of the NamedValue.                              |
| value | An Any to be inserted into the value of the NamedValue.  |
| flags | Indicates whether this is an IN, OUT or INOUT parameter. |

#### **Return Value**

|            |                                                 |
|------------|-------------------------------------------------|
| NamedValue | The NamedValue constructed by this method call. |
|------------|-------------------------------------------------|

#### **Notes**

CORBA-defined.

#### **See Also**

“Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184

“Class org.omg.CORBA.ORB” on page 46

“Class org.omg.CORBA.NVList” on page 44

“Class IE.Iona.OrbixWeb.CORBA.NVList” page 158

“Class IE.Iona.OrbixWeb.CORBA.NamedValue” on page 152

“Class org.omg.CORBA.NamedValue” on page 43

`_create_request()` method in “Interface org.omg.CORBA.Object” on page 45

### create\_output\_stream()

**Synopsis**

```
public org.omg.CORBA.portable.OutputStream create_output_stream()
 throws org.omg.CORBA.SystemException;
```

**Description**

The `Input/OutputStream` classes provide methods for the reading and writing of all of the mapped IDL types to and from streams. Their implementations are used inside the ORB to marshal parameters and to insert and extract complex data types into and from `Anys` and `Requests`.

The streaming APIs are found in the “Class `org.omg.CORBA.portable.Streamable`” package.

The ORB object is used as a factory to create an output stream. An input stream may be created from an output stream.

**Return Value**

`OutputStream`                      A new `OutputStream` object.

**Notes**

CORBA-defined.

**See Also**

“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184  
“Class `org.omg.CORBA.portable.Streamable`” on page 57  
“Class `org.omg.CORBA.portable.InputStream`” on page 53  
“Class `org.omg.CORBA.portable.OutputStream`” on page 55  
“Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248

### get\_default\_context()

**Synopsis**

```
public org.omg.CORBA.Context get_default_context()
 throws org.omg.CORBA.SystemException;
```

**Description**

This operation returns a reference to the default process “Class `org.omg.CORBA.Context`” object. You can then use this for the `Context` parameter to an invocation.

**Return Value**

`context`                              The default `Context` object for this process.

**Notes**

CORBA-defined.

**See Also**      “Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184  
                  “Class org.omg.CORBA.ORB” on page 46  
                  “Class org.omg.CORBA.Context” on page 35  
                  “Class IE.Iona.OrbixWeb.CORBA.Context” on page 130

### **create\_tc()**

**Synopsis**

```
public org.omg.CORBA.TypeCode create_alias_tc(
 String id,
 String name,
 org.omg.CORBA.TypeCode original_type)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_array_tc(
 int length,
 org.omg.CORBA.TypeCode element_type)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_enum_tc(String id,
 String name,
 String[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_exception_tc(
 String id,
 String name,
 org.omg.CORBA.StructMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_interface_tc(String id,
 String name)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_recursive_sequence_tc(
 int bound,
 int offset)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_sequence_tc(int bound,
 ,int offset)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_string_tc(int bound)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_struct_tc(
 String id,
 String name,
 org.omg.CORBA.StructMember[] members)
```

```
throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_union_tc(
 String id,
 String name,
 org.omg.CORBA.TypeCode disc_type,
 org.omg.CORBA.UnionMember[] members)
 throws org.omg.CORBA.SystemException;
public org.omg.CORBA.TypeCode create_wstring_tc(int bound)
 throws org.omg.CORBA.SystemException;
```

### Description

Creates a new `TypeCode` for a specified IDL type. Refer to the Interface Repository section of the CORBA specification.

Normally the `TypeCodes` describing IDL types are generated automatically in the Helper classes or are accessible from the Interface Repository.

In some situations, such as bridges between ORBs, `TypeCodes` need to be constructed outside of any Interface Repository. You can do this using the `create_<type>_tc()` methods on the ORB pseudo-object.

Refer to “Class `org.omg.CORBA.TypeCode`” on page 71 for details of parameters.

For example:

For an array `TypeCode` the methods available are `length()`, which returns the size of this dimension of the array, and `content_type()`, which returns the `TypeCode` for the contents of the array.

---

**Note:** For a multi-dimensional array, is also be an array `TypeCode`.

---

The parameters for `create_array_tc()` correspond to the values that represent the length of the array and the `TypeCode` of the elements contained in the array. For example, to create a `TypeCode` for a 2 dimensional array of longs, use the following code:

```
import IE.Iona.OrbixWeb._CORBA;
import org.omg.CORBA.TypeCode;
import org.omg.CORBA.ORB;

// Create a TypeCode for an array defined as follows in IDL.
// typedef long LongArray[4][5];
```

```
TypeCode tempTC=
 ORB.init().create_array_tc(5,
 _CORBA._tc_long);
TypeCode tc =
 ORB.init().create_array_tc(4,
 tempTC);
```

### Parameters

|      |                                                                                                                                                                                                                                                                                                                     |
|------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| id   | The RepositoryId String for the object described in the CORBA specification is a string of the form "IDL:/<ident1>/<ident2>/.../<identn>:<version number>".<br><br>For example for the grid interface the RepositoryId is "IDL:grid:1.0". If the Helper classes are available, the id() method returns this string. |
| name | The name of the IDL type.                                                                                                                                                                                                                                                                                           |

### Return Value

TypeCode                      The TypeCode generated.

**Notes**                      CORBA-defined.

**See Also**                    "Class IE.Iona.OrbixWeb.CORBA.ORB" on page 184  
"Class org.omg.CORBA.ORB" on page 46

## Class IE.Iona.OrbixWeb.CORBA.TypeCode

### Synopsis

The Java class `TypeCode` implements the IDL pseudo interface `TypeCode`. `TypeCode` is used to describe arbitrary complex IDL type structures at runtime. A `TypeCode` consists of a *kind* and a sequence of *parameters* (a parameter is of type `CORBA.Any`). The kind classifies the `TypeCode`: for example, whether it is an IDL basic type, a struct, a sequence, and so on. `TypeCode` constant values are defined in the Orbix Java class `TCKind`. The parameters give the details of the type definition. For example, the IDL type `sequence<long, 20>` has the kind `TCKind.tk_sequence` and has parameters `long` and `20`.

The parameters of each `TypeCode` are:

| KIND                             | PARAMETER LIST |
|----------------------------------|----------------|
| <code>TCKind.tk_null</code>      | NONE           |
| <code>TCKind.tk_void</code>      | NONE           |
| <code>TCKind.tk_short</code>     | NONE           |
| <code>TCKind.tk_long</code>      | NONE           |
| <code>TCKind.tk_ushort</code>    | NONE           |
| <code>TCKind.tk_ulong</code>     | NONE           |
| <code>TCKind.tk_float</code>     | NONE           |
| <code>TCKind.tk_double</code>    | NONE           |
| <code>TCKind.tk_boolean</code>   | NONE           |
| <code>TCKind.tk_char</code>      | NONE           |
| <code>TCKind.tk_octet</code>     | NONE           |
| <code>TCKind.tk_any</code>       | NONE           |
| <code>TCKind.tk_TypeCode</code>  | NONE           |
| <code>TCKind.tk_Principal</code> | NONE           |

| KIND                 | PARAMETER LIST                                                                                       |
|----------------------|------------------------------------------------------------------------------------------------------|
| TCKind.tk_objref     | { interface-id }                                                                                     |
| TCKind.tk_struct     | { struct-name,<br>member-name, TypeCode,<br>...<repeat pairs>... }                                   |
| TCKind.tk_union      | { union-name, switch-TypeCode,<br>label-value, member-name,<br>TypeCode,<br>...<repeat triples>... } |
| TCKind.tk_enum       | { enum-name, enum-id,<br>...<repeat enum-id>... }                                                    |
| TCKind.tk_string     | { maxlen-integer }                                                                                   |
| TCKind.tk_sequence   | { TypeCode, maxlen-integer }                                                                         |
| TCKind.tk_array      | { TypeCode, length-integer }                                                                         |
| TCKind.tk_alias      | { alias-name, TypeCode }                                                                             |
| TCKind.tk_except     | { except-name,<br>member_name, TypeCode,<br>...<repeat pairs>... }                                   |
| TCKind.tk_longlong   | NONE                                                                                                 |
| TCKind.tk_ulonglong  | NONE                                                                                                 |
| TCKind.tk_longdouble | NONE                                                                                                 |
| TCKind.tk_wchar      | NONE                                                                                                 |
| TCKind.tk_wstring    | { maxlen_integer }                                                                                   |
| TCKind.tk_fixed      | { digits, scale }                                                                                    |

A TypeCode of kind TCKind.tk\_objref has a single parameter giving the interface name.



A `TypeCode` of kind `TCKind.tk_struct` has one parameter giving the `struct` name, and has two parameters for each member of the `struct`: the first giving the member's name and the second giving its `TypeCode`. A `struct` with  $N$  members has  $2N+1$  parameters.

A `TypeCode` of kind `TCKind.tk_union` has parameters giving the union name, the `TypeCode` of the switch (discriminator) of the union, and three parameters for each member of the union: the first giving the label value, the second giving the member name, and the third giving the member's `TypeCode`. If the union has a default member, the triple for this has a label-value of 0 and the `TypeCode` of the corresponding any returned by `member_label()` is the `TypeCode` for an octet, which is not a valid switch type for a union. Thus this 0 can be distinguished from a normal 0 switch value.

A `TypeCode` of kind `TCKind.tk_enum` has one parameter giving the `enum` name, and one parameter for each enumerate constant. Enumerate constants are represented as strings.

A `TypeCode` of kind `TCKind.tk_string` has one parameter—an integer giving the maximum length of the string. A 0 length indicates an unbounded string.

A `TypeCode` of kind `TCKind.tk_sequence` has two parameters: a `TypeCode` for the element types, and a `long` for the length. A 0 length indicates an unbounded sequence.

A `TypeCode` of kind `TCKind.tk_array` has two parameters. For single-dimensional arrays the first parameter is the `TypeCode` for the array and the second parameter is the length of the array. For multi-dimensional arrays a recursive approach is taken. The `TypeCode` is of kind `TCKind.tk_array` and the second parameter is the length of the first dimension of the array. The first `TypeCode` parameter can then be queried for its contents (either an array of basic or constructed types or another array of arrays). This process is repeated until the `TypeCode` parameter is a different type than `TCKind.tk_array`.

A `TypeCode` of kind `TCKind.tk_alias` has two parameters, the first specifying the name of the alias and the second giving the `TypeCode` of the type being aliased.

A `TypeCode` of kind `TCKind.tk_except` has one parameter giving the exception name, and has two parameters for each member of the exception: the first giving the member's name and the second giving its `TypeCode`. Exceptions with no members are allowed.

A `TypeCode` of kind `TCKind.tk_fixed` has two parameters, the first giving the precision of the fixed-point number in decimal digits and the second giving the position of the decimal point (scale).

An IDL operation with a parameter of type `TypeCode` translates into a Java method with a parameter of type `TypeCode`.

A `TypeCode` object reference constant declaration can be generated by the IDL compiler from named type definitions that appear in an IDL file—that is, from the following types:

```
interface
typedef
struct
union
enum
alias
except
```

A number of `TypeCode` object reference constants are always available to allow the user to access `TypeCodes` for standard types. These are defined in the `CORBA` class. Using `ORB.get_primitive_tc` gives similar results.

```
CORBA._tc_null CORBA._tc_void
CORBA._tc_short CORBA._tc_long
CORBA._tc_ushort CORBA._tc_ulong
CORBA._tc_float CORBA._tc_double
CORBA._tc_boolean CORBA._tc_char
CORBA._tc_wchar CORBA._tc_wstring
CORBA._tc_longlong CORBA._tc_ulonglong
CORBA._tc_octet CORBA._tc_any
CORBA._tc_TypeCode CORBA._tc_Principal
CORBA._tc_Object CORBA._tc_string
CORBA._tc_NamedValue
```

### **CORBA**

```
enum TCKind { tk_null, tk_void, tk_short, tk_long, tk_ushort,
tk_ulong, tk_float, tk_double, tk_boolean, tk_char, tk_octet,
tk_any, tk_TypeCode, tk_Principal, tk_objref, tk_struct, tk_union,
```

## Class IE.Iona.OrbixWeb.CORBA.TypeCode

---

```
tk_enum, tk_string, tk_sequence, tk_array, tk_alias, tk_except,
tk_longlong, tk_ulonglong, tk_longdouble, tk_wchar, tk_wstring,
tk_fixed };

pseudo interface TypeCode {
 exception Bounds {};
 exception BadKind {};

 // for all TypeCode kinds
 boolean equal(in TypeCode tc);
 TCKind kind();

 // for objref, struct, union, enum, alias, and except
 RepositoryID id() raises (BadKind);
 RepositoryId name() raises (BadKind);

 // for struct, union, enum, and except
 unsigned long member_count() raises (BadKind);
 Identifier member_name(in unsigned long index) raises (BadKind,
Bounds);

 // for struct, union, and except
 TypeCode member_type(in unsigned long index) raises (BadKind,
Bounds);

 // for union
 any member_label(in unsigned long index) raises (BadKind,
Bounds);
 TypeCode discriminator_type() raises (BadKind);
 long default_index() raises (BadKind);

 // for string, sequence, and array
 unsigned long length() raises (BadKind);
 TypeCode content_type() raises (BadKind);
}

Orbix Java public class TypeCode extends org.omg.CORBA.TypeCode {

 // Constructors
 public TypeCode(TCKind tcKind, String id, String name,
 java.lang.Object[] members, int length,
 org.omg.CORBA.TypeCode content_type)
 throws org.omg.CORBA.SystemException;
```

```
public TypeCode(TCKind tcKind)
 throws org.omg.CORBA.SystemException;

// Get the TCKind code
public TCKind kind() throws org.omg.CORBA.SystemException;

public boolean equals(java.lang.Object _obj)
 throws org.omg.CORBA.SystemException;

// OMG equality operation
public boolean equal(org.omg.CORBA.TypeCode _obj)
 throws org.omg.CORBA.SystemException;

// Compare two TypeCodes
public static boolean compare(org.omg.CORBA.TypeCode tc1,
 org.omg.CORBA.TypeCode tc2)
 throws org.omg.CORBA.SystemException;

// Repository id for TypeCode
public String id()
 throws BadKind, org.omg.CORBA.SystemException;
public String name()
 throws BadKind, org.omg.CORBA.SystemException;

// Number of members in struct, union etc.
public int member_count()
 throws BadKind, org.omg.CORBA.SystemException;

// struct, union etc. member type
public org.omg.CORBA.TypeCode member_type(int index)
 throws BadKind, Bounds, org.omg.CORBA.SystemException;

// struct, union etc. member name
public String member_name(int index)
 throws BadKind, Bounds, org.omg.CORBA.SystemException;
public org.omg.CORBA.Any member_label(int index)
 throws BadKind, Bounds, org.omg.CORBA.SystemException;

public org.omg.CORBA.TypeCode discriminator_type()
 throws BadKind, org.omg.CORBA.SystemException;

public int default_index()
 throws BadKind, org.omg.CORBA.SystemException;
```

## Class IE.Iona.OrbixWeb.CORBA.TypeCode

---

```
public int length()
 throws BadKind, org.omg.CORBA.SystemException;

// Get contents typecode
public org.omg.CORBA.TypeCode content_type()
 throws BadKind, org.omg.CORBA.SystemException;

public OrbixTypeCode orbixTypeCode()
 throws org.omg.CORBA.SystemException;

public String toString()
 throws org.omg.CORBA.SystemException;
};
```

**Notes** CORBA-defined.

**See Also** “Class org.omg.CORBA.TCKind” on page 67  
“Class org.omg.CORBA.TypeCodePackage.BadKind” on page 74  
“Class org.omg.CORBA.TypeCodePackage.Bounds” on page 75

### TypeCode()

**Synopsis**

```
public TypeCode(TCKind tcKind, String id, String name,
 java.lang.Object[] members, int length,
 org.omg.CORBA.TypeCode content_type)
 throws org.omg.CORBA.SystemException;
```

**Description** Construct a `TypeCode` from structural type information. Typecodes are created using ORB operations by the user.

### Parameters

|                      |                                                                                                                                                            |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>tcKind</code>  | The “kind” of the <code>TypeCode</code> . Can use the object reference constants to represent the standard types; for example, <code>CORBA._tc_char</code> |
| <code>id</code>      | Repository ID for a type in the Interface Repository.                                                                                                      |
| <code>name</code>    | IDL name.                                                                                                                                                  |
| <code>members</code> | Members of complex types; for example, union, struct, except, and so on.                                                                                   |

|              |                                                                 |
|--------------|-----------------------------------------------------------------|
| length       | Number of elements for arrays and sequences, length of a string |
| content_type | Base type for elements of sequences and arrays                  |

**Notes** PROGRESS-specific.

**See Also** Other `TypeCode` constructors  
“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184

### **TypeCode()**

**Synopsis**

```
public TypeCode(TCKind tcKind)
 throws org.omg.CORBA.SystemException;
```

**Description** Construct a `TypeCode` from a given typecode kind. Typecodes are created by the user, using `ORB` operations.

#### **Parameters**

|        |                                                                                                                                                                               |
|--------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| tcKind | Create a <code>TypeCode</code> of type <code>tcKind</code> ; for example, <code>CORBA._tc_Object</code> for a <code>TypeCode</code> which represents an <code>Object</code> . |
|--------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Notes** PROGRESS-specific.

**See Also** Other `TypeCode` constructors  
“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184

### **kind()**

**Synopsis**

```
public TCKind kind() throws org.omg.CORBA.SystemException;
```

**Description** Return the kind of `TypeCode` as defined in “Class `org.omg.CORBA.TCKind`” on page 67. Typecodes are created by the user, using `ORB` operations.

**Notes** CORBA-defined.

**See Also** Other `TypeCode` constructors  
“Class `IE.Iona.OrbixWeb.CORBA.ORB`” on page 184

### equals()

|                      |                                                                                                                                                                                                                                                 |                      |                                                                                                                                                                                   |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>      | <pre>public boolean equals(java.lang.Object _obj)     throws org.omg.CORBA.SystemException;</pre>                                                                                                                                               |                      |                                                                                                                                                                                   |
| <b>Description</b>   | Compares the current <code>TypeCode</code> object with <code>_obj</code> . Two <code>TypeCodes</code> are equal when the IDL definitions from which they are compiled denote equal types.                                                       |                      |                                                                                                                                                                                   |
| <b>Parameters</b>    | <table><tr><td><code>obj</code></td><td>Must be an instance of <code>org.omg.CORBA.TypeCode</code></td></tr></table>                                                                                                                            | <code>obj</code>     | Must be an instance of <code>org.omg.CORBA.TypeCode</code>                                                                                                                        |
| <code>obj</code>     | Must be an instance of <code>org.omg.CORBA.TypeCode</code>                                                                                                                                                                                      |                      |                                                                                                                                                                                   |
| <b>Return Value</b>  | <table><tr><td><code>boolean</code></td><td>Returns <code>true</code> if the <code>TypeCodes</code> are equal; returns <code>false</code> if they are unequal, or if <code>_obj</code> is not a <code>TypeCode</code> object.</td></tr></table> | <code>boolean</code> | Returns <code>true</code> if the <code>TypeCodes</code> are equal; returns <code>false</code> if they are unequal, or if <code>_obj</code> is not a <code>TypeCode</code> object. |
| <code>boolean</code> | Returns <code>true</code> if the <code>TypeCodes</code> are equal; returns <code>false</code> if they are unequal, or if <code>_obj</code> is not a <code>TypeCode</code> object.                                                               |                      |                                                                                                                                                                                   |
| <b>Notes</b>         | PROGRESS-specific.                                                                                                                                                                                                                              |                      |                                                                                                                                                                                   |
| <b>See Also</b>      | “equal()” on page 287<br>“compare()” on page 288                                                                                                                                                                                                |                      |                                                                                                                                                                                   |

### equal()

|                      |                                                                                                                                                                                  |                      |                                                                                                                    |
|----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------|--------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>      | <pre>public boolean equal(org.omg.CORBA.TypeCode _obj)     throws org.omg.CORBA.SystemException;</pre>                                                                           |                      |                                                                                                                    |
| <b>Description</b>   | OMG-defined method for checking equality of <code>TypeCodes</code> .                                                                                                             |                      |                                                                                                                    |
| <b>Parameters</b>    | <table><tr><td><code>obj</code></td><td>Check equality of current <code>TypeCode</code> against <code>obj</code>.</td></tr></table>                                              | <code>obj</code>     | Check equality of current <code>TypeCode</code> against <code>obj</code> .                                         |
| <code>obj</code>     | Check equality of current <code>TypeCode</code> against <code>obj</code> .                                                                                                       |                      |                                                                                                                    |
| <b>Return Value</b>  | <table><tr><td><code>boolean</code></td><td>Returns <code>true</code> if the <code>TypeCodes</code> are equal; returns <code>false</code> if they are unequal.</td></tr></table> | <code>boolean</code> | Returns <code>true</code> if the <code>TypeCodes</code> are equal; returns <code>false</code> if they are unequal. |
| <code>boolean</code> | Returns <code>true</code> if the <code>TypeCodes</code> are equal; returns <code>false</code> if they are unequal.                                                               |                      |                                                                                                                    |

**Notes** CORBA-defined.

**See Also** “equal()” on page 287  
“compare()” on page 288

### **compare()**

**Synopsis**

```
public static boolean compare(org.omg.CORBA.TypeCode tc1,
 org.omg.CORBA.TypeCode tc2)
 throws org.omg.CORBA.SystemException;
```

**Description** Returns true if the `TypeCode` specified in parameter `tc1` holds the same value as the `TypeCode` specified in `tc2`.

#### **Parameters**

|                  |                                                      |
|------------------|------------------------------------------------------|
| <code>tc1</code> | First <code>TypeCode</code> instance to be compared. |
| <code>tc2</code> | Second <code>TypeCode</code> to be compared.         |

#### **Return Value**

|                      |                                                                                             |
|----------------------|---------------------------------------------------------------------------------------------|
| <code>boolean</code> | Returns true if the <code>TypeCodes</code> are equal;<br>returns false if they are unequal. |
|----------------------|---------------------------------------------------------------------------------------------|

**Notes** PROGRESS-specific.

**See Also** “equal()” on page 287  
“compare()” on page 288



### id()

**Synopsis**      `public String id() throws BadKind, org.omg.CORBA.SystemException;`

**Description**      Returns the Interface Repository identifier for the `TypeCode`.

**Return Value**

String                      Interface Repository identifier.

**Notes**              CORBA-defined.

### name()

**Synopsis**      `public String name()  
                  throws BadKind, org.omg.CORBA.SystemException;`

**Description**      Returns an identifying name for object references, structs, enums, unions, aliases and exceptions.

**Return Value**

String                      Name of `TypeCode` as specified in IDL.

**Notes**              CORBA-defined.

### member\_count()

**Synopsis**      `public int member_count()  
                  throws BadKind, org.omg.CORBA.SystemException;`

**Description**      Returns the number of constituent members for `struct`, `union`, `enum` and `except` `TypeCodes`. Throws `BadKind` exception if called on a `TypeCode` other than these.

**Return Value**

int                          Number of members in `struct`, `union`,  
                                  except of `enum`.

**Notes**              CORBA-defined.

### **member\_type()**

**Synopsis**

```
public org.omg.CORBA.TypeCode member_type(int index)
 throws BadKind, Bounds, org.omg.CORBA.SystemException;
```

**Description**

Returns the `TypeCode` describing the member identified by `index`. Valid only for `struct` and `union` and except `TypeCodes`. Calling this on any other type results in a `BadKind` exception.

**Parameters**

|                    |                                                                                                                                    |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------|
| <code>index</code> | Identifies the member within the <code>struct</code> or <code>union</code> for which the <code>TypeCode</code> is to be retrieved. |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------|

**Return Value**

|                       |                                                                                                                  |
|-----------------------|------------------------------------------------------------------------------------------------------------------|
| <code>TypeCode</code> | <code>TypeCode</code> that describes the member at the specified position within the <code>struct/union</code> . |
|-----------------------|------------------------------------------------------------------------------------------------------------------|

**Notes**

CORBA-defined.

### **member\_name()**

**Synopsis**

```
public String member_name(int index)
 throws BadKind, Bounds, org.omg.CORBA.SystemException;
```

**Description**

Returns the name of the member identified by `index` in a `struct`, `union`, `except` or `enum`.

**Parameters**

|                    |                                                                               |
|--------------------|-------------------------------------------------------------------------------|
| <code>index</code> | Identifies the member within <code>struct/union</code> or <code>enum</code> . |
|--------------------|-------------------------------------------------------------------------------|

**Return Value**

|                     |                         |
|---------------------|-------------------------|
| <code>String</code> | Name of indexed member. |
|---------------------|-------------------------|

**Notes**

CORBA-defined.

### **member\_label()**

**Synopsis**

```
public org.omg.CORBA.Any member_label(int index)
 throws BadKind, Bounds, org.omg.CORBA.SystemException;
```

**Description**

Returns the label of the union member identified by `index`.

**Parameters**

|                    |                                                                                                                                  |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------|
| <code>index</code> | Identifies member in the union. A <code>Bounds</code> exception is thrown if <code>index</code> does not correspond to a member. |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------|

**Return Value**

|                  |                                                                                                                                                                                                                                                                         |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>Any</code> | The type of the label value is designated by the union discriminator <code>TypeCode</code> . The default member is identified with the 0 octet. The <code>Any</code> can be used to distinguish between the default member label and labels for the legal switch types. |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Notes**

CORBA-defined.

### **discriminator\_type()**

**Synopsis**

```
public org.omg.CORBA.TypeCode discriminator_type()
 throws BadKind, org.omg.CORBA.SystemException;
```

**Description**

Returns the type of all non-default member labels in a union.

**Return Value**

|                       |                                           |
|-----------------------|-------------------------------------------|
| <code>TypeCode</code> | The type of the discriminator in a union. |
|-----------------------|-------------------------------------------|

**Notes**

CORBA-defined.

### **default\_index()**

**Synopsis**

```
public int default_index()
 throws BadKind, org.omg.CORBA.SystemException;
```

**Description**

Returns the index of the default member of a union or -1 if no default member has been defined. Raises a `BadKind` exception if called on anything other than a union.

**Return Value**

int                                      Index of the default union member or -1 if not defined.

**Notes**

CORBA-defined.

### **length()**

**Synopsis**

```
public int length()
 throws BadKind, org.omg.CORBA.SystemException;
```

**Description**

Can be invoked on `string`, `wstring`, `array` and `sequence` `TypeCodes`. For `string`, `wstring` and `sequence`, it returns the bound or 0 for an unbounded `string`, `wstring` or `sequence`. For arrays it returns the number of elements in the array. Invoking on all other types causes the `BadKind` exception to be thrown.

**Return Value**

int                                      For strings, wstrings and sequences returns the bounds or 0 if unbounded. For arrays returns number of elements in the array.

**Notes**

CORBA-defined.

### **content\_type()**

**Synopsis**

```
public org.omg.CORBA.TypeCode content_type()
 throws BadKind, org.omg.CORBA.SystemException;
```

**Description**

Can be invoked on sequence, array and alias TypeCodes. All others result in BadKind being thrown. For sequence and array it returns the type of the elements, for alias it returns the original type being aliased.

**Return Value**

|          |                                                                                       |
|----------|---------------------------------------------------------------------------------------|
| TypeCode | Type of elements for sequence and array TypeCodes, original type for alias TypeCodes. |
|----------|---------------------------------------------------------------------------------------|

**Notes**

CORBA-defined.

### **orbixTypeCode()**

**Synopsis**

```
public OrbixTypeCode orbixTypeCode()
 throws org.omg.CORBA.SystemException;
```

**Description**

Return PROGRESS-specific type for TypeCode identification.

**Return Value**

|               |                                                |
|---------------|------------------------------------------------|
| OrbixTypeCode | PROGRESS-specific identification for TypeCode. |
|---------------|------------------------------------------------|

**Notes**

PROGRESS-specific.

### **toString()**

**Synopsis**

```
public java.lang.String toString()
 throws org.omg.CORBA.SystemException;
```

**Description**

Return a stringified version of the `TypeCode` in the following format:

“`TypeCode : kind = <kind> id = <id> name = <name>`”.

**Return Value**

`String`

A stringified version of the `TypeCode`

**Notes**

PROGRESS-specific

Part III

Package

IE.Iona.OrbixWeb.Feature

S



## Class

# IE.Iona.OrbixWeb.Features.AuthenticationFilter

**Synopsis** `AuthenticationFilter` is a derived class of class `Filter`. It is used to pass authentication information between processes.

There are two important differences between an `AuthenticationFilter` and a normal `Filter`.

First, there can only ever be one instance of the `AuthenticationFilter`.

Second, this instance of the `AuthenticationFilter` is placed in the `Filter` chain before normal filters, but after `ThreadFilter` instances. This allows you to authenticate the request before passing the request to any application code.

The usual way to use an `AuthenticationFilter` is to declare a derived class of `AuthenticationFilter` and then provide implementations of the filter points `outRequestPreMarshal()` and `inRequestPreMarshal()`. These implementations add or remove authentication information respectively. You then create an instance of the derived class in both the client and the server.

### Orbix Java

```
// Java

package IE.Iona.OrbixWeb.Features;

public class AuthenticationFilter extends
 IE.Iona.OrbixWeb.Features.Filter {
 protected AuthenticationFilter()
 throws SystemException;
 protected AuthenticationFilter(org.omg.CORBA.ORB orb)
 throws SystemException;
}
```

**Notes** PROGRESS-specific.

**See Also** “Class `IE.Iona.OrbixWeb.Features.Filter`” on page 301

### **AuthenticationFilter()**

- Synopsis**      `protected AuthenticationFilter();`
- Description**    You cannot create direct instances of `AuthenticationFilter`. The constructor is protected to enforce this.
- Notes**          PROGRESS-specific.

### **AuthenticationFilter()**

- Synopsis**      `protected AuthenticationFilter(org.omg.CORBA.ORB orb);`
- Description**    Direct instances of `AuthenticationFilter` cannot be created. The constructor is protected to enforce this.
- The `orb` parameter provides support for multiple ORBs. This allows the newly-created `AuthenticationFilter` to be associated with a specific ORB instance.
- Notes**          PROGRESS-specific.

## Class IE.Iona.OrbixWeb.Features.Config

**Synopsis** Class `Config` provides methods for accessing and setting Orbix Java configuration variables using Java code.

---

**Note:** The `Config` class is deprecated because configuration is now on a per-ORB basis. To get and set configuration variables using Orbix Java APIs, you should use the methods provided by class `IE.Iona.OrbixWeb.Features.OrbConfig`.

---

**Orbix Java**

```
// Java

package IE.Iona.OrbixWeb.Features;

public class Config {

 // Constructor
 public Config();

 // Methods
 public static String getConfigItem(String);

 public static synchronized void setConfigItem(String, String);
}
```

**Notes** PROGRESS-specific.

**See Also** “Class `IE.Iona.OrbixWeb.Features.OrbConfig`” on page 330

### **Config()**

**Synopsis** `public Config();`

**Description** The default constructor.

**Notes** PROGRESS-specific.

### **getConfigItem()**

**Synopsis**

```
public String getConfigItem(String name)
```

**Description**

Get a configuration item in `String` form. Refer to the *Orbix Administrator's Guide Java Edition* for a complete list of Orbix Java configuration items.

**Parameters**

|      |                                                                                                                         |
|------|-------------------------------------------------------------------------------------------------------------------------|
| name | The configuration item name in <code>String</code> form; for example:<br><pre>getConfigItem("IT_DEFAULT_TIMEOUT")</pre> |
|------|-------------------------------------------------------------------------------------------------------------------------|

**Notes**

PROGRESS-specific.

### **setConfigItem()**

**Synopsis**

```
public synchronized void setConfigItem(String name, String value)
```

**Description**

Sets a configuration item in `String` form. Refer to the *Orbix Administrator's Guide Java Edition* for a complete list of Orbix Java configuration items.

**Parameters**

|       |                                                                                                                                       |
|-------|---------------------------------------------------------------------------------------------------------------------------------------|
| name  | The configuration item name in <code>String</code> form.                                                                              |
| value | The configuration item value in <code>String</code> form; for example:<br><pre>setConfigItem("IT_DEFAULT_TIMEOUT",<br/>"80000")</pre> |

**Notes**

PROGRESS-specific.

## Class IE.Iona.OrbixWeb.Features.Filter

**Synopsis** Class `Filter` is a conceptually abstract class describing the interface to a per-process filter.

If you wish to implement a per-process filter you may define a derived class of `Filter` and redefine some or all of the eight monitoring method and two failure points as described in the *Orbix Programmer's Guide Java Edition* .

For a list of the available `SystemExceptions` that can be raised see the “System Exceptions” on page 455.

### Orbix Java

```
// Java

package IE.Iona.OrbixWeb.Features;

public class Filter {
 // Constructor
 protected Filter();
 protected Filter(boolean installme);
 protected Filter(org.omg.CORBA.ORB orb, boolean installme)

 // Methods
 public void _delete();

 // Client-side filter points
 public boolean outRequestPreMarshal(Request r)
 throws org.omg.CORBA.SystemException;
 public boolean outRequestPostMarshal(Request r)
 throws org.omg.CORBA.SystemException;
 public boolean inReplyPreMarshal(Request r)
 throws org.omg.CORBA.SystemException;
 public boolean inReplyPostMarshal(Request r)
 throws org.omg.CORBA.SystemException;

 // Server-side filter points
 public boolean inRequestPreMarshal(Request r)
 throws org.omg.CORBA.SystemException;
 public boolean inRequestPostMarshal(Request r)
 throws org.omg.CORBA.SystemException;
 public boolean outReplyPreMarshal(Request r)
```

```
throws org.omg.CORBA.SystemException;
public boolean outReplyPostMarshal(Request r)
 throws org.omg.CORBA.SystemException;

// Failure filter points
public void outReplyFailure(Request r, Exception ex)
 throws org.omg.CORBA.SystemException;
public void inReplyFailure(Request r, Exception ex)
 throws org.omg.CORBA.SystemException;
}
```

**Note** PROGRESS-specific.

**See Also** “Class org.omg.CORBA.Request” on page 59  
“Class org.omg.CORBA.SystemException” on page 66  
“Class org.omg.CORBA.UserException” on page 77  
“Class IE.Iona.OrbixWeb.Features.AuthenticationFilter” on page 297  
“Class IE.Iona.OrbixWeb.Features.Filter” on page 301

### **Filter()**

**Synopsis** `protected Filter();`

**Description** The default constructor adds the newly-created filter object into the per-process filter chain. Direct instances of `Filter` cannot be created, and the constructor is protected to enforce this. The derived classes of `Filter` normally have public constructors.

**Notes** PROGRESS-specific.

### **Filter()**

**Synopsis** `protected Filter(boolean installMe);`

**Description** If the value of `installMe` is `true`, this constructor adds the newly-created filter object into the per-process filter chain.

If the value of `installME` is `false`, the newly created filter object is not added to the per-process filter chain. This flexibility is useful for implementing master-slave architectures.

Direct instances of `Filter` cannot be created; the constructor is protected to enforce this. The derived classes of `Filter` may have public constructors overriding this constructor.

**Notes** PROGRESS-specific.

### **Filter()**

**Synopsis** `protected Filter(org.omg.CORBA.ORB orb, boolean installMe);`

**Description** Direct instances of `Filter` cannot be create; the constructor is protected to enforce this. The derived classes of `Filter` may have public constructors that overriding this constructor.

### **Parameters**

|                        |                                                                                                                                                                                                                                                                                                                                                                                    |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>orb</code>       | The <code>orb</code> parameter provides support for multiple ORBs. This allows the newly-created filter to be associated with a specific ORB instance.                                                                                                                                                                                                                             |
| <code>installMe</code> | If the value of <code>installMe</code> is <code>true</code> , this constructor adds the newly-created filter object into the per-process filter chain.<br><br>If the value of <code>installMe</code> is <code>false</code> , the newly created filter object is not added to the per-process filter chain. This flexibility is useful for implementing master-slave architectures. |

**Notes** PROGRESS-specific.

### **\_delete()**

**Synopsis** `public void _delete();`

**Description** Removes any references to the `Filter` object from the Orbix Java runtime by removing the object from the process filter chain. You must call this method when your client or server is about to exit or when you have finished using the `Filter` object in question so that it can be garbage collected.

**Notes** PROGRESS-specific.

**See Also**      “finalize()” on page 111  
                 “finalize()” on page 205  
                 “unregisterIOCallback()” on page 236

### **inReplyFailure()**

**Synopsis**      `public void inReplyFailure(Request r, java.lang.Exception ex);`

**Description**      Defines the action to perform if the target object raises an exception or if any preceding marshalling filter point (‘out request’, ‘in request’, ‘out reply’ or ‘in reply’) raises an exception or uses its return value to indicate that the call should not be processed any further.

If not redefined in a derived class, this filter point carries out no actions.

#### **Parameters**

|                 |                                                                                                                                          |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------|
| <code>r</code>  | This is the Request object for the current invocation.                                                                                   |
| <code>ex</code> | This is the exception object that has just been thrown by the implementation object, by a preceding filter point, or by the ORB runtime. |

**Notes**      PROGRESS-specific.

### **inReplyPostMarshal()**

**Synopsis**      `public boolean inReplyPostMarshal(Request r);`

**Description**      Defines the action to perform after any operation on any object in another address space. In particular, after the operation response has arrived at the caller’s address space, and after the operation’s return parameters and return value have been removed from the reply packet.

If not redefined in a derived class, the following implementation is inherited:

```
// Java
{ return true; } // Continue the call.
```



### Parameters

`r` This is the `Request` for the current invocation.

### Return Value

`true` Continue with the request as normal. The reply is sent to the next filter on the chain, or, if this is the last filter, it is sent to the calling object.

`false` Do not continue with the call. Raise a `FILTER_SUPPRESS` exception and do not run the remaining filters.

### Exceptions

If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

### Notes

PROGRESS-specific.

### **inReplyPreMarshal()**

#### Synopsis

```
public boolean inReplyPreMarshal(Request r)
```

#### Description

Defines the action to perform after any operation on any object in another address space. Specifically, after the operation response has arrived at the caller's address space, and before the operation's return parameters and return value have are removed from the reply packet.

If not redefined in a derived class, the following implementation is inherited:

```
// Java
{ return true; } // Continue the call.
```

#### Parameters

`r` This is the `Request` object for the current invocation.

### Return Value

|                    |                                                                                                                                                           |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>true</code>  | Continue with the request as normal. The reply is sent to the next filter on the chain, or, if this is the last filter, it is sent to the calling object. |
| <code>false</code> | Do not continue with the call. Raise a <code>FILTER_SUPPRESS</code> exception and do not run the remaining filters.                                       |

**Exceptions** If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

**Notes** PROGRESS-specific.

### **inRequestPostMarshal()**

**Synopsis** `public boolean inRequestPostMarshal(Request r);`

**Description** Defines the action to perform before any incoming operation on any object in the address space. Specifically, before the operation has been sent to the target object, and after the operation's parameters have been removed from the request packet.

If not redefined in a derived class, the following implementation is inherited:

```
// Java
{ return true; } // Continue the call.
```

### Parameters

|                |                                                                     |
|----------------|---------------------------------------------------------------------|
| <code>r</code> | This is the <code>Request</code> object for the current invocation. |
|----------------|---------------------------------------------------------------------|

### Return Value

|                    |                                                                                                                                                                                                               |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>true</code>  | Continue with the request as normal. The operation call is sent to the next filter on the chain, or, if this is the last filter, it is sent to the per-object filters, if any, and then to the target object. |
| <code>false</code> | Do not continue with the call. Raise a <code>FILTER_SUPPRESS</code> exception; do not run the remaining filters and do not pass the call onto the target object.                                              |

### Exceptions

If you redefine this method in a derived class, you may raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

### Notes

PROGRESS-specific.

### **inRequestPreMarshal()**

#### Synopsis

```
public boolean inRequestPreMarshal(Request r);
```

#### Description

Defines the action to perform before incoming requests: before any incoming operation on any object in the address space. Specifically, before the operation has been sent to the target object, and before the operation's parameters have been removed from the request packet.

If not redefined in a derived class, the following implementation is inherited:

```
 // Java
{ return true; } // Continue the call.
```

#### Parameters

|                |                                                                     |
|----------------|---------------------------------------------------------------------|
| <code>r</code> | This is the <code>Request</code> object for the current invocation. |
|----------------|---------------------------------------------------------------------|

### Return Value

|                    |                                                                                                                                                                                                               |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>true</code>  | Continue with the request as normal. The operation call is sent to the next filter on the chain, or, if this is the last filter, it is sent to the per-object filters, if any, and then to the target object. |
| <code>false</code> | Do not continue with the call. Raise a <code>FILTER_SUPPRESS</code> exception; do not run the remaining filters and do not pass the call onto the target object.                                              |

**Exceptions** If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

**Notes** PROGRESS-specific.

**See Also** “Class `IE.Iona.OrbixWeb.Features.ThreadFilter`” on page 337  
“`inRequestPreMarshal()`” on page 307

### **outReplyFailure()**

**Synopsis** `public void outReplyFailure(Request r, java.lang.Exception ex);`

**Description** Defines the action to perform if the target object raises an exception, or if any preceding marshalling filter point on the server's side ('in request' or 'out reply') raises an exception or uses its return value to indicate that the call should not be processed any further.

If not redefined in a derived class, this filter point performs no actions.

### Parameters

|                 |                                                                                                                                         |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| <code>r</code>  | This is the <code>Request</code> object for the current invocation.                                                                     |
| <code>ex</code> | This is the exception object that has just been thrown by the implementation object, by a preceding filter point or by the ORB runtime. |

**Notes**            PROGRESS-specific.

### **outReplyPostMarshal()**

**Synopsis**            `public boolean outReplyPostMarshal (Request r);`

**Description**       Defines the action to perform before outgoing replies: after any incoming operation on any CORBA object in the address space. Specifically, after the operation call is processed, and after the operation's return parameters and return value are added to the reply packet.

If not redefined in a derived class, the following implementation is inherited:

```
 // Java
 { return true; } // Continue the call.
```

### **Parameters**

`r`                    This is the `Request` object for the current invocation.

### **Return Value**

`true`                Continue with the request as normal. The reply is sent to the next filter on the chain, or, if this is the last filter, it is sent to the calling object's address space (where it is handled by 'in reply' filters).

`false`               Do not continue with the call. Raise a `FILTER_SUPPRESS` exception and do not run the remaining filters.

**Exceptions**        If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

**Notes**            PROGRESS-specific.

### outReplyPreMarshal()

**Synopsis**      `public boolean outReplyPreMarshal(Request r);`

**Description**      Defines the action to perform before outgoing replies: after any incoming operation on any CORBA object in the address space. Specifically, after the operation call has been processed, and before the operation's return parameters and return value have been added to the reply packet.

If not redefined in a derived class, the following implementation is inherited:

```
// Java
{ return true; } // Continue the call.
```

### Parameters

`r`                      This is the `Request` object for the current invocation.

### Return Value

`true`                      Continue with the request as normal. The reply is sent to the next filter on the chain, or, if this is the last filter, it is sent to the calling object's address space (where it is handled by 'in reply' filters).

`false`                      Do not continue with the call. Raise a `FILTER_SUPPRESS` exception and do not run the remaining filters.

**Exceptions**      If you redefine this method in a derived class, you may raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

**Notes**              PROGRESS-specific.

## outRequestPostMarshal()

### Synopsis

```
public boolean outRequestPostMarshal(Request r);
```

### Description

Defines the action to perform before outgoing requests; before any operation from this address space to any object in another address space. Specifically, before the invocation has been transmitted and after the operation's parameters have been added to the request packet.

If not redefined in a derived class, the following implementation is inherited:

```
// Java
{ return true; } // Continue the call.
```

### Parameters

`r` This is the `Request` object for the current invocation.

### Return Value

`true` Continue with the request as normal. The operation call is sent to the next filter on the chain, or, if this is the last filter it is transmitted to the address space of the target object (where it is first handled by any per-process filters and then per-object filters).

`false` Do not continue with the call. Raise a `FILTER_SUPPRESS` exception. Do not run the remaining filters and do not transmit the operation call out of this address space.

### Exceptions

If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

### Notes

PROGRESS-specific.

### outRequestPreMarshal()

**Synopsis**      `public boolean outRequestPreMarshal(Request r);`

**Description**      Defines the action to perform before outgoing requests; before any operation from this address space to any object in another address space. In particular, before the invocation has been transmitted and after the operation's parameters have been added to the request packet.

If not redefined in a derived class, the following implementation is inherited:

```
// Java
{ return true; } // Continue the call.
```

### Parameters

`r`                      This is the `Request` object for the current invocation.

### Return Value

`true`                      Continue with the request as normal. The operation call is sent to the next filter on the chain, or, if this is the last filter, it is transmitted to the address space of the target object (where it is first handled by any per-process filters and then per-object filters).

`false`                      Do not continue with the call. Raise a `FILTER_SUPPRESS` exception. Do not run the remaining filters and do not transmit the operation call out of this address space.

**Exceptions**      If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

You can also return `false`. If you do this, Orbix Java raises a `FILTER_SUPPRESS` exception and the call is not continued.

**Notes**              PROGRESS-specific.



## Interface `IE.Iona.OrbixWeb.Features.ioCallback`

### Synopsis

An application may wish to be informed when a new connection is established, or when an existing connecton is closed. A connection is opened when a client first communicates with the server; it is closed when the client terminates or the communications layer reports a break in service between the server and the client.

To implement an input/output callback you must write an application `ioCallback` class implementing the `IE.Iona.OrbixWeb.Features.ioCallback` Java interface.

You then pass an instance of the application callback object to the ORB object using:

```
IE.Iona.OrbixWeb.CORBA.ORB.registerIOCallback
(IE.Iona.OrbixWeb.CORBA.ioCallback)
```

for example:

```
_CORBA.Orbix.registerIOCallback(new myioCallbackObj());
```

To unregister a callback object use

```
IE.Iona.OrbixWeb.CORBA.ORB.unregisterIOCallback();
```

`OpenCallBack()` is called whenever a connection is created, and `CloseCallBack()` is be called when a connection is closed.

Your code should not depend on the calls being made in a particular thread because the thread in which these calls are made is variable. For example, if you are binding to a server, the `OpenCallBack()` is made in the thread which is making the bind. If a connection is abruptly closed, the `CloseCallBack()` is made in the reader thread. If a client thread calls `closeConnection()`, `CloseCallBack()` is called in that thread.

You can register only one `ioCallback` object at a time. When an object is registered it replaces the object that is currently registered there.

You should unregister the `ioCallback` object when you are finished with it to ensure that your objects are swiftly garbage collected.

By default there is no `ioCallback` object registered.

**Orbix Java**

```
public interface ioCallback {
 public void OpenCallBack(String serverName, Object conn)
 throws SystemException;
 public void CloseCallBack(String serverName, Object conn)
 throws SystemException;
}
```

**Notes**

PROGRESS-specific.

**See Also**

“registerIOCallback()” on page 225  
“unregisterIOCallback()” on page 236

### CloseCallBack()

**Synopsis**

```
public void CloseCallBack(String serverName, Object conn);
```

**Description**

This method will get called when any connection to the process in which your `ioCallback` is registered is closed or broken.

**Parameters**

|                         |                                                                                                                                                                                                                                                 |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>serverName</code> | The name of the server, to which your connection has just been broken. If you were connected to a client process from the server, this contains a unique number (a port or process ID) to identify the client that you were communicating with. |
| <code>conn</code>       | This is the socket connection object for the connection that has just been broken. It is either of type <code>java.net.Socket</code> or <code>java.net.URLConnection</code> depending on the kind of connection that existed.                   |

**Notes**

PROGRESS-specific.

**See Also**

“OpenCallBack()” on page 315

### **OpenCallBack()**

**Synopsis**

```
public void OpenCallBack(String serverName, Object conn);
```

**Description**

This method is called when a connection is established between the process in which your `ioCallback` is registered and some other process.

**Parameters**

|                         |                                                                                                                                                                                                                                                      |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>serverName</code> | The name of the server, with which a connection has just been established. If you are connecting with a client process from the server, this contains a unique number (a port or process ID) to identify the client that was communicating with you. |
| <code>conn</code>       | This is the socket connection object for the connection that has just been established.<br><br>It is either of type <code>java.net.Socket</code> or <code>java.net.URLConnection</code> depending on the kind of connection that existed.            |

**Notes**

PROGRESS-specific.

**See Also**

“CloseCallBack()” on page 314

## Class `IE.Iona.OrbixWeb.Features.IT_reqTransformer`

### Synopsis

Class `IE.Iona.OrbixWeb.Features.IT_reqTransformer` is a conceptually abstract class describing the interface for transformer objects that allow an `org.omg.CORBA.Request` data buffer to be modified before an operation invocation is transmitted to a server, and before a reply is returned to a client.

If you wish to implement specific `Request` transformation behaviour you can define a derived class of `IE.Iona.OrbixWeb.Features.IT_reqTransformer` and redefine the `transform` and `transform_error` methods as described in the *Orbix Programmer's Guide Java Edition*.

`Request` transformers are registered with the Orbix Java runtime using “`setMyReqTransformer()`” on page 231 or “`setReqTransformer()`” on page 232.

### Orbix Java

```
// Java

package IE.Iona.OrbixWeb.Features;

import IE.Iona.OrbixWeb.CORBA.octetSeqHolder;

public class IT_reqTransformer {
 public boolean transform(octetSeqHolder data,
 String host,
 boolean is_send,
 org.omg.CORBA.Request req)

 public String transform_error()
}

```

### See Also

“`setMyReqTransformer()`” on page 231  
“`setReqTransformer()`” on page 232  
“`getMyReqTransformer()`” on page 210

## Class `IE.Iona.OrbixWeb.Features.IT_reqTransformer`

---

### **transform()**

#### **Synopsis**

```
public boolean transform(octetSeqHolder data,
 String host,
 boolean is_send,
 org.omg.CORBA.Request req)
```

#### **Description**

Defines the transformation to be performed on `org.omg.CORBA.Request`. This function is automatically invoked on the registered transformer object immediately prior to transmitting data in an `org.omg.CORBA.Request` (and after filtering) and directly subsequent (before any filtering) to receiving data in an `org.omg.CORBA.Request`.

A derived class of `IE.Iona.OrbixWeb.Features.IT_reqTransformer` should override this function to implement a transformation.

An implementation of this function may raise an `org.omg.CORBA.COMM_FAILURE` system exception to indicate that an error has occurred during the transformation. The `reason` member of the exception contains the text returned by `IE.Iona.OrbixWeb.Features.IT_reqTransformer.transform_error()`.

#### **Parameters**

|                      |                                                                                                                                                                                                                                                                                                               |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>data</code>    | The raw binary data buffer to be transformed.                                                                                                                                                                                                                                                                 |
| <code>host</code>    | If sending a request, this is the host on which the server process resides.<br><br>If receiving a request, this is an empty string.                                                                                                                                                                           |
| <code>is_send</code> | A flag identifying whether a request is being sent from an address space or received into an address space.<br><br>A value of <code>true</code> indicates that the request is being sent.<br><br>A value of <code>false</code> indicates that the request is being received.                                  |
| <code>req</code>     | If sending a request, this is the request object that is normally sent. You can use this <code>Request</code> object, for example, to obtain information such as what host, server, and interface the outgoing <code>data</code> is being sent to.<br><br>If receiving a request, this is <code>null</code> . |

### Return Value

|                    |                                                                                                                                                                                                              |
|--------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>true</code>  | Transformation was successful.                                                                                                                                                                               |
| <code>false</code> | Transformation failed. This automatically raises an <code>org.omg.CORBA.COMM_FAILURE</code> system exception, with the <code>reason</code> string set to the text provided by <code>transform_error()</code> |

**Notes**           PROGRESS-specific.

**See Also**       “`transform_error()`” on page 318  
                  “Class `IE.Iona.OrbixWeb.Features.Filter`” on page 301

### **transform\_error()**

**Synopsis**       `public String transform_error()`

**Description**   Returns a string describing every error that has occurred in the `transform()` function. A derived class may override this function to return a text string specific to the transformation implemented by the class. The Orbix Java runtime automatically calls this method to get the error string whenever the `transform()` method returns `false` (that is, raises a `COMM_FAILURE` exception).

**Return Value**   The string returned by this function is used in the `reason` element of an `org.omg.CORBA.COMM_FAILURE` exception thrown by `IE.Iona.OrbixWeb.Features.IT_reqTransformer.transform()`.

**Notes**           PROGRESS-specific.

**See Also**       “`transform()`” on page 317

# Class IE.Iona.OrbixWeb.Features.LoaderClass

## Synopsis

When an operation invocation arrives at a process, Orbix Java searches for the target object in the object table for the process. By default, if the object is not found, Orbix Java returns an `INV_OBJREF` exception to the caller. However, by installing one or more loader objects in a process, you can choose to intervene and be informed about the failure to find the object.

A `LoaderClass` object can handle such an object fault by reconstructing the required object from a persistent store, such as a flat file, an RDBMS, or an ODBMS.

Orbix Java can then retry the invocation on the newly-created object. This occurs transparently to the caller.

Loaders are defined by defining a derived class of `IE.Iona.OrbixWeb.Features.LoaderClass` and are installed by creating an instance of the new class.

## Orbix Java

```
// Java

package IE.Iona.OrbixWeb.Features;

public class LoaderClass {
 // Constructors.
 public LoaderClass();
 public LoaderClass(boolean registerMe);
 public LoaderClass(org.omg.CORBA.ORB orb, boolean registerMe);

 // Methods.
 public org.omg.CORBA.Object load (String interfaceName,
 String marker, boolean local)
 throws SystemException;
 public void save (org.omg.CORBA.Object obj, int reason)
 throws SystemException;
 public void record
 (org.omg.CORBA.Object obj, StringHolder marker)
 throws SystemException;
```

```
 public boolean rename (org.omg.CORBA.Object obj,
 StringHolder marker)
 throws SystemException;
 }
```

**Notes** PROGRESS-specific.

### **LoaderClass()**

**Synopsis** `public LoaderClass ();`

**Description** The `LoaderClass` constructor has protected access. You cannot create a direct instance of class `LoaderClass`.

**Notes** PROGRESS-specific.

**See Also** Other class constructors.

### **LoaderClass()**

**Synopsis** `public LoaderClass (boolean registerMe);`

**Description** The `LoaderClass` constructor has protected access. You cannot create a direct instance of class `LoaderClass`.

#### **Parameters**

|                         |                                                                                                                                                                                    |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>registerMe</code> | The value of this parameter must be <code>true</code> if the <code>load()</code> method of the new loader is to be called by Orbix Java, rather than explicitly by the programmer. |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

**Notes** PROGRESS-specific.

**See Also** Other class constructors.



### **LoaderClass()**

|                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                      |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |
|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>         | <pre>public LoaderClass(org.omg.CORBA.ORB orb, boolean registerMe);</pre>                                                                                                                                                                                                                                                                                                                                                                            |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |
| <b>Description</b>      | The <code>LoaderClass</code> constructor has protected access. You cannot create a direct instance of class <code>LoaderClass</code> .                                                                                                                                                                                                                                                                                                               |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |
| <b>Parameters</b>       | <table><tr><td><code>orb</code></td><td>The <code>orb</code> parameter provides support for multiple ORBs. This allows the newly-created loader to be associated with a specific ORB instance.</td></tr><tr><td><code>registerMe</code></td><td>The value of this parameter must be <code>true</code> if the <code>load()</code> method of the new loader is to be called by Orbix Java, rather than explicitly by the programmer.</td></tr></table> | <code>orb</code> | The <code>orb</code> parameter provides support for multiple ORBs. This allows the newly-created loader to be associated with a specific ORB instance. | <code>registerMe</code> | The value of this parameter must be <code>true</code> if the <code>load()</code> method of the new loader is to be called by Orbix Java, rather than explicitly by the programmer. |
| <code>orb</code>        | The <code>orb</code> parameter provides support for multiple ORBs. This allows the newly-created loader to be associated with a specific ORB instance.                                                                                                                                                                                                                                                                                               |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |
| <code>registerMe</code> | The value of this parameter must be <code>true</code> if the <code>load()</code> method of the new loader is to be called by Orbix Java, rather than explicitly by the programmer.                                                                                                                                                                                                                                                                   |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |
| <b>Notes</b>            | PROGRESS-specific.                                                                                                                                                                                                                                                                                                                                                                                                                                   |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |
| <b>See Also</b>         | Other class constructors.                                                                                                                                                                                                                                                                                                                                                                                                                            |                  |                                                                                                                                                        |                         |                                                                                                                                                                                    |

### **load()**

|                    |                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Synopsis</b>    | <pre>public org.omg.CORBA.Object<br/>    load (String interfaceName, String marker, boolean local)<br/>    throws SystemException;</pre>                                                                                                                                                                                                                                                                                              |
| <b>Description</b> | <p>When an object fault occurs, the <code>load()</code> method is called on each loader in turn until one of them successfully returns the address of the object, or until they have all returned <code>null</code>.</p> <p>The responsibility of the <code>load()</code> method is to determine if the required object is to be loaded by the current loader, and, if so, create the object and assign the correct marker to it.</p> |

### Parameters

|                            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>interfaceName</code> | <p>The interface name of the missing object is determined as follows:</p> <ul style="list-style-type: none"><li>• If an object fault occurs during the call:<br/><pre>// Java<br/>g = GridHelper._bind( &lt;parameters&gt; );</pre>the interface name in <code>load()</code> is “Grid”.</li><li>• If the first parameter to <code>bind()</code> is a full object reference string, Orbix Java returns an exception if the reference's interface field is not <code>Grid</code> or a derived interface of <code>Grid</code>.</li><li>• If an object fault occurs during the call:<br/><pre>// Java<br/>g = org.omg.CORBA.ORB.string_to_object<br/>( &lt;full object reference string&gt; );</pre>the interface name in <code>load()</code> is that extracted from the full object reference string.</li><li>• If a loader is called because of a reference entering an address space (as an <code>in</code>, <code>out</code> or <code>inout</code> parameter, a return value, or as the target object of an operation call), then the interface name in <code>load()</code> is the interface name extracted from the object reference.</li></ul> <p>The switches passed to the IDL compiler affect how the interface name is seen by <code>load()</code>. See the method “<code>_interfaceMarker()</code>” on page 176.</p> |
| <code>marker</code>        | <p>The marker of the required object.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

`local` Set to `true` if the object fault occurred because of a collocated call to `bind()` or `org.omg.CORBA.ORB.string_to_object()` by the process itself.

Set to `false` if the object fault occurred because of an object fault on the target object of an incoming operation invocation, or on an `in`, `out` or `inout` parameter or return value

**Return Value** Returns the object reference, if the object is made available, or `null` otherwise.

**Notes** PROGRESS-specific.

**See Also** “Class `org.omg.CORBA.ORB`” on page 46  
“`save()`” on page 325  
“`_interfaceMarker()`” on page 176

### **record()**

**Synopsis**

```
public void record (org.omg.CORBA.Object obj,
 StringHolder marker);
```

**Description** When you name an object by passing a marker name to the TIE or `ImplBase` constructor, Orbix Java calls `record()` on the object’s loader.

A derived class may redefine `record()` to override your choice of name.

The default loader inherits its implementation of `record()` from `LoaderClass`. This implementation does not change the chosen name. It may, however, raise an exception if the name is in use (that is, an object with the same interface name and marker name already exists in the server process) and the object consequently cannot be registered.

If no marker name is suggested, the default `record()` method chooses a name that is a string of decimal digits, different to any generated before in the current process.

You can also name an object using the method “`_marker()`” on page 179. In this case, Orbix Java calls `rename()` rather than `record()` on the object’s loader.

### Parameters

|                     |                                        |
|---------------------|----------------------------------------|
| <code>obj</code>    | The object currently being registered. |
| <code>marker</code> | The name of the object marker.         |

**Notes**      PROGRESS-specific.

**See Also**    “`rename()`” on page 324  
              “`_marker()`” on page 179

### **rename()**

#### **Synopsis**

```
public boolean rename (org.omg.CORBA.Object obj,
 StringHolder marker);
```

#### **Description**

When you name an object by calling `_marker()` in class `IE.Iona.OrbixWeb.CORBA.BaseObject`, Orbix Java calls `rename()` on the object's loader.

A derived class may redefine `rename()` to override the programmer's choice of name.

The default loader inherits its implementation of `rename()` from `LoaderClass`. This implementation does not change the chosen name. It may, however, raise an exception if the name is in use (that is, an object with the same interface name and marker name already exists in the server process).

Note that an object may also be named by passing a marker name to the TIE or `ImplBase` constructor. In this case, Orbix Java calls `record()` on the object's loader.

#### **Parameters**

|                     |                                                 |
|---------------------|-------------------------------------------------|
| <code>obj</code>    | The object that is currently being renamed.     |
| <code>marker</code> | The new name to be used for the objects marker. |

**Return Value**    Returns `true` if the object is successfully renamed. Returns `null` otherwise.

## Class `IE.Iona.OrbixWeb.Features.LoaderClass`

---

**Notes**            `PROGRESS`-specific.

**See Also**        “`record()`” on page 323  
                  “`_marker()`” on page 179

### **save()**

#### **Synopsis**

```
public void save (org.omg.CORBA.Object obj, int reason)
```

#### **Description**

Immediately before process termination, you may invoke the method `IE.Iona.OrbixWeb.CORBA.ORB.finalize()` on the `_CORBA.Orbix` object. Orbix Java then iterates through all of the objects in its object table and calls `save()` on the loader associated with each object. A loader may save the object to persistent storage (either by calling a method on the object, or by accessing the object’s data).

The associated loader’s `save()` method is also called when an object is destroyed using `org.omg.CORBA.ORB.disconnect()`.

You can call `save()` explicitly for an object by calling its

`IE.Iona.OrbixWeb.CORBA.ObjectRef._save()` method.

`IE.Iona.OrbixWeb.CORBA.ObjectRef._save()` calls the `save()` method on the object’s loader. The `_save()` method must be called in the same address space as the target object: calling it in a client process (that is, on a proxy) has effect.

#### **Parameters**

|                     |                                                                                                                                                                                                                                                                                                                                                                                         |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>obj</code>    | The object on who’s loader <code>save()</code> is asked to store.                                                                                                                                                                                                                                                                                                                       |
| <code>reason</code> | The reason that <code>save()</code> has been called. This may be:<br><br><code>_CORBA.processTermination</code> : The process is about to exit.<br><code>_CORBA.explicitCall</code> : The object’s <code>_save()</code> method has been called.<br><br><code>_CORBA.objectDeletion</code> : A call to <code>org.omg.CORBA.ORB.disconnect()</code> has been made with <code>obj</code> . |

**Notes**            PROGRESS-specific.

**See Also**        “\_save()” on page 182  
                  “load()” on page 321  
                  “Class org.omg.CORBA.ORB” on page 46  
                  “processTermination” on page 348  
                  “explicit\_call” on page 344  
                  “objectDeletion” on page 346

# Class IE.Iona.OrbixWeb.Features.locatorClass

**Synopsis** Class `IE.Iona.OrbixWeb.Features.locatorClass` is a base class defining the interface to a location server. Orbix Java uses the installed locator to find a target object in the distributed system when `bind()` is called with a null host name.

The default locator, provided by Orbix Java, searches for the target object of a `bind()` call. For details on the `bind()` method, refer to the *Orbix Programmer's Guide Java Edition* .

You can override the default locator by defining and implementing a derived class of `locatorClass` as described in the *Orbix Programmer's Guide Java Edition* .

**Orbix Java** `// Java`

```
package IE.Iona.OrbixWeb.Features;

public class locatorClass {

 protected locatorClass();

 public String[] lookUp (String serviceName, int MaxHops,
 Context ctx);
}
```

**See Also** *Orbix Programmer's Guide Java Edition*

## **locatorClass()**

**Synopsis** `protected locatorClass()`

**Description** Default constructor.

**Notes** PROGRESS-specific. This class is `protected`, so you cannot create an instance of this class directly.

### lookup()

#### Synopsis

```
public String[] lookup (String serviceName, int maxHops,
 Context ctx);
```

#### Description

Searches for a server. It is called on the locator pointed to by `ORB.locator()`, when `bind()` is called with a null host name. Any parameters to `bind()` are passed to `lookup()`.

#### Parameters

|                          |                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>serviceName</code> | The name of the server being sought                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <code>maxHops</code>     | <p>In the default locator, this is interpreted as the maximum number of machines to search for the required server.</p> <p>An interpretation similar to this one should be retained in a user-defined locator if it is to be used without changing client code that explicitly calls <code>lookup()</code>.</p>                                                                                                                                                    |
| <code>ctx</code>         | <p>This allows a client to pass extra information to the locator; for example, constraints on how to search for the server. You can use the context parameter to define properties to be used when deciding between a set of servers with the same name.</p> <p>The <code>Context</code> passed to <code>lookup()</code> originates in the <code>Context</code> value passed to a <code>bind()</code> call.</p> <p>The default locator ignores this parameter.</p> |



## Class `IE.Iona.OrbixWeb.Features.locatorClass`

---

### Return Value

`String[]` The default locator returns a list of names of hosts on which the server is registered in the Implementation Repository. The default implementation of the locator randomizes the sequence before returning it. It also adds the `localhost` to the end of the array. This is a basic technique in load balancing to avoid swamping any one server. A user-defined `locatorClass` should keep a similar interpretation. An empty array is returned if no host names can be found for the specified server.

There is a different rule for applets. Refer to the chapter “Locating Servers at Runtime” in the *Orbix Java Edition Programmer’s Guide* for details.

**Notes**           PROGRESS-specific.

**See Also**       “Locating Servers at Runtime” in the *Orbix Programmer’s Guide Java Edition* .

## Class IE.Iona.OrbixWeb.Features.OrbConfig

**Synopsis** Class `OrbConfig` provides methods for accessing and setting Orbix Java configuration variables. The `OrbConfig` class replaces class `IE.Iona.OrbixWeb.Features.Config`. The `Config` class is deprecated because of Orbix Java's support for multiple ORBs. Configuration is now on a per-ORB basis.

Refer to the *Orbix Programmer's Guide Java Edition* for full details of Orbix Java configuration variables.

**Orbix Java**

```
// Java

public class OrbConfig {

 // Constructor
 public OrbConfig(ORB);

 // Methods
 public String defaultConfigFile();
 public Hashtable getConfigFile();
 public String getConfigItem(String);
 public synchronized Properties getConfiguration();
 public synchronized void setConfigItem(String, String);
 public synchronized void setConfiguration(Properties);
 public synchronized void setConfiguration (String name);
 public synchronized void zeroConfiguration();
}
```

**Notes** PROGRESS-specific.

**See Also** “Class `IE.Iona.OrbixWeb.Features.Config`” on page 299  
“`config()`” on page 195

### **OrbConfig()**

**Synopsis** `public OrbConfig(Orb orb);`

**Description** The default `OrbConfig` constructor.

**Parameters**

|                  |                                                                                                               |
|------------------|---------------------------------------------------------------------------------------------------------------|
| <code>orb</code> | Enables configuration to be associated with a specific ORB instance. This provides support for multiple ORBs. |
|------------------|---------------------------------------------------------------------------------------------------------------|

**Notes** PROGRESS-specific.

### **defaultConfigFile()**

**Synopsis** `public String defaultConfigFile();`

**Description** Returns a `String` containing the default `orbixweb3.cfg` configuration file. This method is provided for emergency use—if you accidentally delete your configuration file. Calling this API creates a new configuration file containing the default values.

**Notes** PROGRESS-specific.

### **getConfigFile()**

**Synopsis** `public Hashtable getConfigFile();`

**Description** Gets the current settings in the Orbix Java configuration files. This includes the contents of `iona.cfg`, `common.cfg`, `orbixweb3.cfg`, and `orbixnames3.cfg`. This method also supports `orbix.cfg` and `orbixweb.properties` files, for backwards compatibility.

**Notes** PROGRESS-specific.

### **getConfigItem()**

- Synopsis** `public String getConfigItem(String name);`
- Description** Gets the value of the specified configuration parameter in `String` form. Refer to the *Orbix Administrator's Guide Java Edition* for a complete list of Orbix Java configuration parameters.
- Parameters**
- |      |                                                                       |
|------|-----------------------------------------------------------------------|
| name | The configuration item name in <code>String</code> form; for example: |
|------|-----------------------------------------------------------------------|
- ```
getConfigItem("IT_DEFAULT_TIMEOUT");
```
- Notes** PROGRESS-specific.

getConfiguration()

- Synopsis** `public synchronized Properties getConfiguration();`
- Description** Returns the configuration parameters programmatically set by the user.
- Notes** PROGRESS-specific.
- See Also** “setConfiguration()” on page 332

setConfiguration()

- Synopsis** `public synchronized void setConfiguration(Properties props);`
- Description** Sets configuration parameters from the specified `java.util.Properties` object.
- Notes** PROGRESS-specific.
- See Also** “setConfiguration()” on page 332

setConfiguration()

- Synopsis** `public synchronized void setConfiguration (String name);`
- Description** Sets configuration from a specified configuration file. The file you specify must be included on the classpath.
- Notes** PROGRESS-specific.
- See Also** “setConfiguration()” on page 332

setConfigItem()

- Synopsis** `public synchronized void setConfigItem(String name, String value)`
- Description** Sets a configuration item in `String` form. Refer to the *Orbix Administrator's Guide Java Edition* for a complete list of Orbix Java configuration items.
- Parameters**
- | | |
|--------------------|--|
| <code>name</code> | The configuration item name in <code>String</code> form. |
| <code>value</code> | The configuration item value in <code>String</code> form; for example:
<code>setConfigItem("IT_DEFAULT_TIMEOUT", "80000");</code> |
- Notes** PROGRESS-specific.

zeroConfiguration()

- Synopsis** `public synchronized void zeroConfiguration();`
- Description** Resets any configuration settings, returning to compiled-in defaults. This method also resets any configuration that has been loaded from configuration files or URLs.
- Notes** PROGRESS-specific.
- See also** “setConfiguration()” on page 332
“setConfigItem()” on page 333

Class IE.Iona.OrbixWeb.Features.ProxyFactory

Synopsis ProxyFactory is the base class for Orbix Java proxy factory classes. Orbix Java allows smart proxies to be implemented for IDL interfaces. When implementing a smart proxy, you must declare a derived class of the default proxy factory class for an IDL type and override the proxy factory `New()` method. To state which IDL interface type your ProxyFactory is to be used for, pass the interface ID to the constructor for the base class.

Orbix Java

```
// Java

package IE.Iona.OrbixWeb.Features;

public class ProxyFactory {
    // Ctor
    protected ProxyFactory(String id);
    protected ProxyFactory(org.omg.CORBA.ORB orb, String name);
    // Method
    public org.omg.CORBA.Object
        New(org.omg.CORBA.portable.Delegate d);
}
```

ProxyFactory()

Synopsis `protected ProxyFactory(String id);`

Description This constructor registers this object with the system as providing the specified interface ID. The name can be retrieved at runtime from the `static` method `<interfaceName>Helper.id()`. This constructor should be called from the constructor of the smart proxy being created using `super(<InterfaceName>Helper.id())`.

Class IE.Iona.OrbixWeb.Features.ProxyFactory

Parameters

`id` The ID of the IDL interface implemented by this object.

Notes PROGRESS-specific.

ProxyFactory()

Synopsis

```
protected ProxyFactory(org.omg.CORBA.ORB orb, String name);
```

Description

This constructor registers this object with the system as providing the specified interface name. The name can be retrieved at runtime from the static method `<interfaceName>Helper.id()`. This constructor should be called from the constructor of the Smart Proxy being created using `super (<InterfaceName>Helper.id())`.

Parameters

`orb` The `orb` parameter provides support for multiple ORBs. This allows the smart proxy to be associated with a specific ORB instance.

`name` The name of the IDL interface implemented by this object

Notes PROGRESS-specific.

New()

Synopsis

```
public org.omg.CORBA.Object New(org.omg.CORBA.portable.Delegate d)
```

Description

This method should be overridden in a derived smart proxy class. The derived method is invoked by Orbix Java each time a new smart proxy is created. Orbix Java passes it the delegate of the real object for which the proxy is required in the `d` parameter.

Parameters

d The delegate of the real object for which the proxy is required

Return Value Returns the new proxy object reference.

Notes PROGRESS-specific.

See Also “Interface org.omg.CORBA.Object” on page 45

Class IE.Iona.OrbixWeb.Features.ThreadFilter

Synopsis

The conceptually abstract class `ThreadFilter` is special kind of filter that you can use to implement custom threading and queuing policies.

To take advantage of a `ThreadFilter`'s special functionality you should define a derived class of `ThreadFilter` and redefine the `inRequestPreMarshal()` method. When a request enters this filter point, you can take over responsibility for dispatching the request. You can then pass the request into a custom event queue serviced by one or more threads, or you can create a thread directly and pass it the `Request` object to be dispatched.

The class `ThreadFilter` inherits from the class `Filter`. Although the `ThreadFilter` does not redefine any of the `Filter` class' method signatures, it does change the behaviour of `inRequestPreMarshal` (see below) and the default constructor. Redefining any of the other `Filter` operations has no special effect. A separate chain of `ThreadFilters` is maintained by the Orbix Java run-time.

To take advantage of the special abilities of the `ThreadFilter` you must either use its default constructor, or pass an ORB instance to the constructor to add the filter to that ORB's `ThreadFilter` chain.

See the "thread1", "thread2" and "thread3" demos for sample code.

Orbix Java

```
// Java

package IE.Iona.OrbixWeb.Features;

public class ThreadFilter extends Filter {
    protected ThreadFilter();
    protected ThreadFilter(org.omg.CORBA.ORB orb)
}

```

Notes PROGRESS-specific.

See Also “Class org.omg.CORBA.Request” on page 59
“Class org.omg.CORBA.SystemException” on page 66
“continueThreadDispatch()” on page 106
“Class IE.Iona.OrbixWeb.Features.Filter” on page 301
“Class IE.Iona.OrbixWeb.Features.AuthenticationFilter” on page 297

ThreadFilter()

Synopsis `protected ThreadFilter();`

Description The default constructor adds the newly-created `ThreadFilter` object onto the `ThreadFilter` chain. Direct instances of `ThreadFilter` cannot be created, and the constructor is protected to enforce this. The derived classes of `ThreadFilter` normally have public constructors.

Notes PROGRESS-specific.

ThreadFilter()

Synopsis `protected ThreadFilter(org.omg.CORBA.ORB orb);`

Description The `orb` parameter provides support for multiple ORBs. This allows the newly created `ThreadFilter` to be associated with a specific ORB instance. This constructor adds the newly-created `ThreadFilter` object onto the ORB's `ThreadFilter` chain.

Direct instances of `ThreadFilter` cannot be created, and the constructor is protected to enforce this. The derived classes of `ThreadFilter` normally have public constructors.

Notes PROGRESS-specific.

`inRequestPreMarshal()`

Synopsis

```
public boolean inRequestPreMarshal(Request r);
```

Description

Defines the action to perform for incoming requests: before any incoming operation on any object in the address space. In particular, before the operation has been sent to the target object and before the operation's parameters have been removed from the request packet.

The special behaviour for `ThreadFilters` is tied up with the return value.

If `true` is returned, the responsibility for processing the request object stays with the Orbix Java runtime and the request gets immediately dispatched.

If `false` is returned, (unlike a normal filter where a `FILTER_SUPPRESS` exception is thrown) it is your responsibility to decide when to process the request.

You can pass the current request object to a different thread or put the request into a custom request queue.

Once the application comes to a stage where it wishes to process the request, it should call the method

`IE.Iona.OrbixWeb.CORBA.BOA.continueThreadDispatch()`. The thread that calls `continueThreadDispatch` blocks on the call until the request has been fully processed and then the call returns.

If not redefined the default implementation is as follows:

```
// Java
{ return true; } // Continue the call.
```

Parameters

`r` This is the `Request` object for the current invocation.

Return Value

`true` Continue with the request as normal. The operation call is sent to the next filter on the chain, or, if this is the last filter, it is sent to the per-object filters, if any, and then to the target object.

`false` Remove responsibility for dispatching this `Request` from the runtime. The runtime goes back to the internal queue and starts processing the next request to arrive. It is up to you to ensure that the request gets dispatched at some later time, whether in the current or in a different thread.

Exceptions

If you redefine this method in a derived class, you can raise a `SystemException` to indicate that the call is not to be continued.

If you wish to raise a `FILTER_SUPPRESS` exception, you should create and throw it as a normal `SystemException`.

Notes

PROGRESS-specific.

See Also

“Class `org.omg.CORBA.SystemException`” on page 66
“`continueThreadDispatch()`” on page 106

Part IV

Package IE.Iona.OrbixWeb

Class IE.Iona.OrbixWeb._CORBA

Synopsis The `_CORBA` class implements constants and operations defined at the highest level of scope within the IDL `CORBA` module, and includes a number of other definitions specific to Orbix Java. This class includes a set of `TypeCode` constant definitions (including `_tc_null`, `_tc_short`, and `_tc_long`) that are described in detail in “Class IE.Iona.OrbixWeb.CORBA.TypeCode” on page 279.

Orbix Java // Java

```
package IE.Iona.OrbixWeb;
public class _CORBA {

    public static final TypeCode _tc_null;
    public static final TypeCode _tc_void;
    public static final TypeCode _tc_short;
    public static final TypeCode _tc_long;
    public static final TypeCode _tc_ushort;
    public static final TypeCode _tc_ulong;
    public static final TypeCode _tc_float;
    public static final TypeCode _tc_double;
    public static final TypeCode _tc_boolean;
    public static final TypeCode _tc_char;
    public static final TypeCode _tc_octet;
    public static final TypeCode _tc_any;
    public static final TypeCode _tc_TypeCode;
    public static final TypeCode _tc_Principal;
    public static final TypeCode _tc_Object;
    public static final TypeCode _tc_struct;
    public static final TypeCode _tc_union;
    public static final TypeCode _tc_enum;
    public static final TypeCode _tc_string;
    public static final TypeCode _tc_NamedValue;
    public static final TypeCode _tc_wchar;
    public static final TypeCode _tc_wstring;
    public static final TypeCode _tc_longlong;
    public static final TypeCode _tc_ulonglong;
    public static final TypeCode _tc_fixed;
```

```
//Locator and maximum number of hops
    public static IE.Iona.OrbixWeb.Features.locatorClass locator;

//Loader constants
    public static final int processTermination;
    public static final int objectDeletion;
    public static final int explicitCall;

//Object type constants
    public static final int IT_INTEROPERABLE_OR_KIND;
    public static final int IT_ORBIX_OR_KIND;

//Timeout constant
    public static final int IT_INFINITE_TIMEOUT;

    public static IE.Iona.OrbixWeb.CORBA.ORB Orbix;

    public static final String _ORBIX_VERSION;
    public static final int _MAX_LOCATOR_HOPS;

};
```

explicit_call

Synopsis

```
public static final int explicit_call;
```

Description

You can pass this value to the method `IE.Iona.OrbixWeb.CORBA.Features.LoaderClass.save()` to indicate that `save()` has been called directly from an application using the `save()` method.

Notes

PROGRESS-specific.

See Also

“objectDeletion” on page 346
“processTermination” on page 348
“save()” on page 325

IT_INFINITE_TIMEOUT

- Synopsis** `public static final int IT_INFINITE_TIMEOUT`
- Description** A value you can pass as a timeout parameter to an Orbix Java event processing call to indicate that the call should never return.
- Notes** PROGRESS-specific.
- See Also** “Interface IE.Iona.OrbixWeb.CORBA.BOA” on page 98

IT_INTEROPERABLE_OR_KIND

- Synopsis** `public static final int IT_INTEROPERABLE_OR_KIND;`
- Description** This value should be passed as the `kind` parameter to `IE.Iona.OrbixWeb.CORBA.BaseObject._object_to_string()` to convert an object reference to a stringified Interoperable Object Reference (IOR).
- Notes** PROGRESS-specific.

IT_ORBIX_OR_KIND

- Synopsis** `public static final int IT_ORBIX_OR_KIND;`
- Description** You should pass this value as the `kind` parameter to `IE.Iona.OrbixWeb.CORBA.BaseObject._object_to_string()` to convert an object reference to a stringified Orbix object reference.
- Notes** PROGRESS-specific.

_ORBIX_VERSION

- Synopsis** `public static final String _ORBIX_VERSION;`
- Description** A string containing a description of this version of Orbix, for example, “OrbixWeb 3.2”.
- Notes** PROGRESS-specific.

_MAX_LOCATOR_HOPS

- Synopsis** `public static final int _MAX_LOCATOR_HOPS;`
- Description** This specifies the maximum value that `_LOCATOR_HOPS` can be set to. The value of `MAX_LOCATOR_HOPS` is 10.
- Notes** `PROGRESS`-specific.
- See Also** “Class `IE.Iona.OrbixWeb.Features.locatorClass`” on page 327

objectDeletion

- Synopsis** `public static final int objectDeletion;`
- Description** You can pass this value to the method `IE.Iona.OrbixWeb.Features.LoaderClass.save()` to indicate that `save()` is called as the result of `IE.Iona.OrbixWeb.CORBA.BOA.dispose()` invocation on an object reference.
- Notes** `PROGRESS`-specific.
- See Also** “Class `IE.Iona.OrbixWeb.Features.locatorClass`” on page 327

Orbix

Synopsis

```
public static IE.Iona.OrbixWeb.CORBA.ORB Orbix
```

Description

This variable is a convenience for Orbix Java programmers. Its use is deprecated, you should use the `ORB.init()` method instead.

It is an instance of an ORB object of type `IE.Iona.OrbixWeb.CORBA.ORB` (in a pure client) or of type `IE.Iona.OrbixWeb.CORBA.BOA` (in a server). This is the same object as that returned by `ORB.init()` except that its type has already been narrowed to the Orbix Java correct implementation class.

Before you use `_CORBA.Orbix` you must call `ORB.init()` at least once in order to create the ORB object in the first place.

Multiple ORB Support

`_CORBA.Orbix` refers to the *default ORB*, the first full ORB created. If that ORB is destroyed, `_CORBA.Orbix` becomes `null` until another ORB is created.

Only server objects connected to the default ORB can be persistent and contacted via `orbxid`; for example, by clients calling `bind()`. Server objects connected to other ORBs in the virtual machine listen on other ports unknown to `orbixd` and should be regarded as transient objects.

Features such as filters smart proxies and loaders are associated with particular ORB instances. By default, this is the default ORB. The Orbix Java API allows any of these to be associated with a selected ORB instance.

Notes

PROGRESS-specific.

See Also

`init()` in “Class IE.Iona.OrbixWeb.CORBA.ORB” on page 184
“Class IE.Iona.OrbixWeb.Features.Filter” on page 301
“Class IE.Iona.OrbixWeb.Features.AuthenticationFilter” on page 297
“Class IE.Iona.OrbixWeb.Features.LoaderClass” on page 319
“Class IE.Iona.OrbixWeb.Features.ProxyFactory” on page 334

processTermination

Synopsis	<code>public static final int processTermination;</code>
Description	You can pass this value to the method <code>IE.Iona.OrbixWeb.Features.LoaderClass.save()</code> to indicate that <code>save()</code> has been called due to the termination of the current process. This can be, for example, due to a server timing out.
Notes	PROGRESS-specific.
See Also	“Class <code>IE.Iona.OrbixWeb.Features.locatorClass</code> ” on page 327

Class IE.Iona.OrbixWeb._OrbixWeb

Synopsis The methods in the `_OrbixWeb` class return an Orbix Java implementation class for a supplied OMG abstract base class. The `_OrbixWeb` class provides a consistent interface to allow you to access the value-added features and methods of the Orbix Java implementations of the CORBA abstract base classes. Typically, this involves casting from an abstract class in the `org.omg.CORBA` package to an implementation class in the `IE.Iona.OrbixWeb` package. The system exception `BAD_PARAM` is thrown if the supplied object cannot be converted to the desired return type, for example, if there are multiple ORBs in the same virtual machine.

Orbix Java

```
// Java

package IE.Iona.OrbixWeb;
public class _OrbixWeb {
    public static IE.Iona.OrbixWeb.CORBA.InputCoder
        MarshalBuffer(org.omg.CORBA.portable.InputStream stream)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static IE.Iona.OrbixWeb.CORBA.OutputCoder
        MarshalBuffer(org.omg.CORBA.portable.OutputStream stream)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static IE.Iona.OrbixWeb.CORBA.ORB
        ORB(org.omg.CORBA.ORB orb)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static IE.Iona.OrbixWeb.CORBA.BOA
        BOA(org.omg.CORBA.ORB orb)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static IE.Iona.OrbixWeb.CORBA.Any
        Any(org.omg.CORBA.Any a)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static final IE.Iona.OrbixWeb.OrbixProt.OrbixTypeCode
        TypeCode(org.omg.CORBA.TypeCode t)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static final IE.Iona.OrbixWeb.CORBA.NamedValue
        NamedValue(org.omg.CORBA.NamedValue nv)
            throws org.omg.CORBA.BAD_PARAM, SystemException;
    public static final IE.Iona.OrbixWeb.CORBA.NVList
        NVList(org.omg.CORBA.NVList nvl)
```

```
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.Context
    Context(org.omg.CORBA.Context c)
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.ContextList
    ContextList(org.omg.CORBA.ContextList cl)
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.ObjectRef
    Object(org.omg.CORBA.Object o)
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.Principal
    Principal(org.omg.CORBA.Principal p)
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.Request
    Request(org.omg.CORBA.Request r)
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.DSIServerRequest
    ServerRequest(org.omg.CORBA.ServerRequest r)
        throws org.omg.CORBA.BAD_PARAM, SystemException;
public static final IE.Iona.OrbixWeb.CORBA.OrbCurrent
    Current()
        throws org.omg.CORBA.BAD_PARAM, SystemException;
```

Any()

Synopsis

```
public static IE.Iona.OrbixWeb.CORBA.Any
    Any(org.omg.CORBA.Any a);
```

Description

Converts a reference of type `org.omg.CORBA.Any` to a reference of type `IE.Iona.OrbixWeb.CORBA.Any`.

Parameters

a The Any to be converted.

Return Value

Returns an Any of type `IE.Iona.OrbixWeb.CORBA.Any`

Notes

PROGRESS-specific.

See Also

“Class `IE.Iona.OrbixWeb.CORBA.Any`” on page 81

Context()

- Synopsis** `public static final IE.Iona.OrbixWeb.CORBA.Context
Context(org.omg.CORBA.Context c)`
- Description** Converts a reference of type `org.omg.CORBA.Context` to a reference of type `IE.Iona.OrbixWeb.CORBA.Context`.
- Parameters**
- `c` The `Context` to be converted.
- Return Value** Returns a `Context` of type `IE.Iona.OrbixWeb.CORBA.Context`
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.Context`” on page 35
“Class `IE.Iona.OrbixWeb.CORBA.Context`” on page 130

ContextList()

- Synopsis** `public static final IE.Iona.OrbixWeb.CORBA.ContextList
ContextList(org.omg.CORBA.ContextList c)`
- Description** Converts a reference of type `org.omg.CORBA.ContextList` to a reference of type `IE.Iona.OrbixWeb.CORBA.ContextList`.
- Parameters**
- `c` The `ContextList` to be converted.
- Return Value** Returns a `Context` of type `IE.Iona.OrbixWeb.CORBA.ContextList`
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.ContextList`” on page 37
“Class `IE.Iona.OrbixWeb.CORBA.ContextList`” on page 139

Current()

Synopsis

```
public static final IE.Iona.OrbixWeb.CORBA.OrbCurrent Current()
```

Description

The current object contains information about the request currently being processed. This method can be validly called during the execution of the request itself as well as in filters and loaders. These operations include the following:

```
// Return the principal of the client.
public static org.omg.CORBA.Principal get_principal()
// Return the DSI server request.
public static org.omg.CORBA.ServerRequest get_request()
// Return the target of the request.
public static org.omg.CORBA.Object get_object()
// Return the protocol (IIOP or Orbix) in which the
// request was transmitted.
public static int get_protocol()
// Return the connection object on which the request arrived
// in the server.
public static java.lang.Object get_socket()
```

To ensure thread safety, if you expect the server to concurrently execute requests. You should set the configurable item `IT_MULTI_THREADED_SERVER` to `true` to ensure that these operations return the information associated with the current thread rather than another active thread.

Return Value

OrbCurrent The returned current object.

Notes

PROGRESS-specific.

See Also

“get_current()” on page 112
“Class IE.Iona.OrbixWeb.CORBA.OrbCurrent” on page 237
“Class org.omg.CORBA.Current” on page 39

NamedValue()

- Synopsis** `public static final IE.Iona.OrbixWeb.CORBA.NamedValue
NamedValue(org.omg.CORBA.NamedValue nv);`
- Description** Converts a reference of type `org.omg.CORBA.NamedValue` to a reference of type `IE.Iona.OrbixWeb.CORBA.NamedValue`.
- Parameters**
- `nv` The `NamedValue` to be converted.
- Return Value** Returns a `NamedValue` of type `IE.Iona.OrbixWeb.CORBA.NamedValue`
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.NamedValue`” on page 43
“Class `IE.Iona.OrbixWeb.CORBA.NamedValue`” on page 152

NVList()

- Synopsis** `public static final IE.Iona.OrbixWeb.CORBA.NVList
NVList(org.omg.CORBA.NVList nvl)`
- Description** Converts a reference of type `org.omg.CORBA.NVList` to a reference of type `IE.Iona.OrbixWeb.CORBA.NVList`.
- Parameters**
- `nvl` The `NVList` to be converted.
- Return Value** Returns an `NVList` of type `IE.Iona.OrbixWeb.CORBA.NVList`
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.NVList`” on page 44
“Class `IE.Iona.OrbixWeb.CORBA.NVList`” page 158

Object()

Synopsis	<pre>public static final IE.Iona.OrbixWeb.CORBA.ObjectRef Object(org.omg.CORBA.Object o)</pre>
Description	Converts a reference of type <code>org.omg.CORBA.Object</code> to a reference of type <code>IE.Iona.OrbixWeb.CORBA.ObjectRef</code> . This allows the use of extra Orbix Java specific methods with object references.
Parameters	<ul style="list-style-type: none">o The <code>org.omg.CORBA.Object</code> to be converted.
Return Value	Returns an <code>Object</code> of type <code>IE.Iona.OrbixWeb.CORBA.ObjectRef</code>
Notes	PROGRESS-specific.
See Also	“Interface <code>org.omg.CORBA.Object</code> ” on page 45 “Interface <code>IE.Iona.OrbixWeb.CORBA.ObjectRef</code> ” on page 168

Principal()

Synopsis	<pre>public static final IE.Iona.OrbixWeb.CORBA.Principal Principal(org.omg.CORBA.Principal p)</pre>
Description	Converts a reference of type <code>org.omg.CORBA.Principal</code> to a reference of type <code>IE.Iona.OrbixWeb.CORBA.Principal</code> .
Parameters	<ul style="list-style-type: none">p The <code>Principal</code> to be converted.
Return Value	Returns a <code>Principal</code> of type <code>IE.Iona.OrbixWeb.CORBA.Principal</code>
Notes	PROGRESS-specific.
See Also	“Class <code>org.omg.CORBA.Principal</code> ” on page 58 “Class <code>IE.Iona.OrbixWeb.CORBA.Principal</code> ” on page 244

Request()

- Synopsis** `public static final IE.Iona.OrbixWeb.CORBA.Request
Request(org.omg.CORBA.Request r)`
- Description** Converts a reference of type `org.omg.CORBA.Request` to a reference of type `IE.Iona.OrbixWeb.CORBA.Request`.
- Parameters**
- `r` The `Request` to be converted.
- Return Value** Returns a `Request` of type `IE.Iona.OrbixWeb.CORBA.Request`
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.Request`” on page 59
 “Class `IE.Iona.OrbixWeb.CORBA.Request`” on page 248

ServerRequest()

- Synopsis** `public static final IE.Iona.OrbixWeb.CORBA.DSIServerRequest
ServerRequest(org.omg.CORBA.ServerRequest sr)`
- Description** Converts a reference of type `org.omg.CORBA.ServerRequest` to a reference of type `IE.Iona.OrbixWeb.CORBA.DSIServerRequest`.
- Parameters**
- `sr` The `ServerRequest` to be converted.
- Return Value** Returns a `ServerRequest` of type `IE.Iona.OrbixWeb.CORBA.DSIServerRequest`
- Notes** PROGRESS-specific.
- See Also** “Class `org.omg.CORBA.ServerRequest`” on page 61

TypeCode()

Synopsis

```
public static final IE.Iona.OrbixWeb.OrbixProt.OrbixTypeCode  
    TypeCode(org.omg.CORBA.TypeCode t)
```

Description

Converts a reference of type `org.omg.CORBA.TypeCode` to a reference of type `IE.Iona.OrbixWeb.OrbixProt.OrbixTypeCode`.

Parameters

`t` The `TypeCode` to be converted.

Return Value

Returns a `Typecode` of type `IE.Iona.OrbixWeb.OrbixProt.OrbixTypeCode`.

Notes


PROGRESS-specific. This function is only for use with the Orbix protocol as the returned object is optimized for this protocol and has Orbix-specific additions, or for debug purposes as the returned class contains a `toString()` operation for outputting the `Typecode` in Orbix format. Normally the runtime is the only user of this class. There is no equivalent method for the IIOP protocol as the class `IE.Iona.OrbixWeb.CORBA.TypeCode` directly implements the `org.omg.CORBA.TypeCode` abstract base class only.

See Also

“Class `IE.Iona.OrbixWeb.CORBA.TypeCode`” on page 279

Part V

IDL Interface to the Interface Repository



Common CORBA Data Types

CORBA::DefinitionKind

Synopsis

```
enum DefinitionKind {  
    dk_none, dk_all,  
    dk_Attribute, dk_Constant, dk_Exception, dk_Interface,  
    dk_Module, dk_Operation, dk_Typedef,  
    dk_Alias, dk_Struct, dk_Union, dk_Enum,  
    dk_Primitive, dk_String, dk_Sequence, dk_Array,  
    dk_Repository  
};
```

Description

Each Interface Repository (IFR) object has an attribute (`def_kind`) of type `DefinitionKind` that records the kind of the IFR object. For example, the `def_kind` attribute of an `InterfaceDef` object is `dk_interface`. The enumeration constants `dk_none` and `dk_all` have special meanings when searching for an object in a repository.

Notes

CORBA-defined.

CORBA::Identifier

Synopsis

```
typedef string Identifier;
```

Description

A simple name that identifies modules, interfaces, constants, typedefs, exceptions, attributes, and operations. An identifier is not necessarily unique within the entire Interface Repository; it is unique only within a particular `Repository`, `ModuleDef`, `InterfaceDef`, or `OperationDef`.

Notes

CORBA-defined.

CORBA::RepositoryId

Synopsis	<code>typedef string RepositoryId;</code>
Description	A string that uniquely identifies a module, interface, constant, typedef, exception, attribute, or operation.
Notes	CORBA-defined.

CORBA::ScopedName

Synopsis	<code>typedef string ScopedName;</code>
Description	<p>A <code>ScopedName</code> gives an entity's name relative to a scope. A <code>ScopedName</code> that begins with “:.” is an <i>absolute scoped name</i>; one that uniquely identifies an entity within a repository. An example is:</p> <pre> ::Account::makeWithdrawal.</pre> <p>A <code>ScopedName</code> that does not begin with “:.” is a relative scoped name; one that identifies an entity relative to some other entity. An example is:</p> <pre> makeWithdrawal</pre> <p>This is within the entity with the absolute scoped name <code>::Account</code>.</p>
Notes	CORBA-defined.

CORBA::AliasDef

Synopsis The interface `AliasDef` describes an IDL typedef that aliases another definition. It is used to represent an IDL typedef.

CORBA

```
// IDL
// In module CORBA.

interface AliasDef : TypedefDef {
    attribute IDLType original_type_def;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“Container::create_alias()” on page 378

AliasDef::describe()

Synopsis Description `describe()`;

Description Inherited from `Contained`, the `describe()` operation returns a structure of type `Contained::Description`:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The `DefinitionKind` for the `kind` member is `dk_Alias`. The `value` member is an any whose `TypeCode` is `_tc_AliasDescription` and whose `value` is a structure of type `TypeDescription`:

```
// IDL
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

See Also “TypedefDef::describe()” on page 416

AliasDef:original_type_def

Synopsis attribute IDLType original_type_def;

Description Identifies the type being aliased.

Modifying the `original_type_def` attribute automatically updates the `type` attribute (the `type` attribute is inherited from `TypedefDef` which in turn inherits it from `IDLType`). Both attributes contain the same information.

Notes CORBA-defined.

See Also “IDLType::type” on page 391

CORBA::ArrayDef

Synopsis The interface `ArrayDef` represents a one-dimensional array. A multi-dimensional array is represented by an `ArrayDef` with an element type that is another array definition. The final element type represents the type of element contained in the array. You can create an instance of interface `ArrayDef` using `CORBA::Repository::create_array()`.

CORBA

```
// IDL
// In module CORBA

interface ArrayDef : IDLType {
    attribute unsigned long length;
    readonly attribute TypeCode element_type;
    attribute IDLType element_type_def;
};
```

Notes CORBA-defined.

See Also “CORBA::IDLType” on page 390
“ArrayDef::element_type_def” on page 364
“Repository::create_array()” on page 408

ArrayDef::element_type

Synopsis `readonly attribute TypeCode element_type;`

Description Identifies the type of the element contained in the array. This contains the same information as the attribute `element_type_def`.

Notes CORBA-defined.

See Also “ArrayDef::element_type_def” on page 364

ArrayDef::element_type_def

- Synopsis** `attribute IDLType element_type_def;`
- Description** Describes the type of the element contained within the array. This contains the same information as the attribute `element_type`.
- You can change the type of elements contained in the array by changing this attribute. Changing this attribute also changes the `element_type` attribute.
- Notes** CORBA-defined.

ArrayDef::length

- Synopsis** `attribute unsigned long length;`
- Description** Specifies the number of elements in the array.
- Notes** CORBA-defined.

CORBA::AttributeDef

Synopsis Interface AttributeDef describes an IDL attribute.

CORBA

```
// IDL
// In module CORBA.
enum AttributeMode { ATTR_NORMAL, ATTR_READONLY };

interface AttributeDef : Contained {
    readonly attribute TypeCode type;
    attribute IDLType type_def;
    attribute AttributeMode mode;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“InterfaceDef::create_attribute()” on page 393

AttributeDef::describe()

Synopsis Description describe();

Description Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Attribute. The value member is an any whose TypeCode is _tc_AttributeDescription.

The value is a structure of type AttributeDescription:

```
// IDL
// In module CORBA.
struct AttributeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
```

```
VersionSpec version;  
TypeCode type;  
AttributeMode mode;  
};
```

See Also “Contained::describe()” on page 372

AttributeDef::mode

Synopsis `attribute AttributeMode mode;`

Description Specifies whether the attribute is read/write (`ATTR_NORMAL`) or readonly (`ATTR_READONLY`).

Notes CORBA-defined.

AttributeDef::type

Synopsis `readonly attribute TypeCode type;`

Description Identifies the type of this attribute. The same information is contained in the `type_def` attribute.

Notes CORBA-defined.

See Also “AttributeDef::type_def” on page 366
“CORBA::TypedefDef” on page 416

AttributeDef::type_def

Synopsis `attribute IDLType type_def;`

Description Describes the type for this attribute. The same information is contained in the `type` attribute. Changing the `type_def` attribute automatically changes the `type` attribute.

Notes CORBA-defined.

See Also “AttributeDef::type_def” on page 366
“CORBA::TypedefDef” on page 416

CORBA::ConstantDef

Synopsis Interface ConstantdefinedDef describes an IDL constant. The name of the constant is inherited from Contained.

CORBA

```
// IDL
// in module CORBA.

interface ConstantDef : Contained {
    readonly attribute TypeCode type;
    attribute IDLType type_def;
    attribute any value;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“Container::create_constant()” on page 378

ConstantDef::describe()

Synopsis Description describe();

Description Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Constant.

The value member is an any whose `TypeCode` is `_tc_ConstantDescription` and whose value is a structure of type `ConstantDescription`:

```
// IDL
struct ConstantDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    any value;
};
```

Notes CORBA-defined.

See Also “`Contained::describe()`” on page 372

ConstantDef::type

Synopsis `readonly attribute TypeCode type;`

Description Identifies the type of this constant. The type must be a `TypeCode` for one of the simple types (such as `long`, `short`, `float`, `char`, `string`, `double`, `boolean`, `unsigned long`, and `unsigned short`). The same information is contained in the `type_def` attribute.

Notes CORBA-defined.

See Also “`ConstantDef::type_def`” on page 368

ConstantDef::type_def

Synopsis `attribute IDLType type_def;`

Description Identifies the type of the constant. The same information is contained in the `type` attribute.

You can change the type of a constant by changing its `type_def` attribute. This also changes its `type` attribute.

Notes CORBA-defined.

See Also “`ConstantDef::type`” on page 368

ConstantDef::value

- Synopsis** attribute any value;
- Description** Contains the value for this constant. When changing the `value` attribute, the `TypeCode` of the `any` must be the same as the `type` attribute.
- Notes** CORBA-defined.

CORBA::Contained

Synopsis Interface `Contained` is an abstract interface that describes Interface Repository objects that can be contained in a module, interface, or repository. It is a base interface for the following interfaces:

```
ModuleDef
InterfaceDef
ConstantDef
TypedefDef
ExceptionDef
AttributeDef
OperationDef
StructDef
EnumDef
UnionDef
AliasDef
```

CORBA

```
// IDL
// In module CORBA.

typedef string VersionSpec;

interface Contained : IObject {
    attribute RepositoryId id;
    attribute Identifier name;
    attribute VersionSpec version;

    readonly attribute Container defined_in;
    readonly attribute ScopedName absolute_name;
    readonly attribute Repository containing_repository;

    struct Description {
        DefinitionKind kind;
        any value;
    };
};
```

```
Description describe();  
void move (  
    in Container new_container,  
    in Identifier new_name,  
    in VersionSpec new_version);  
};
```

Notes CORBA-defined.

See Also “CORBA::Container” on page 375
“CORBA::IObject” on page 397

Contained::absolute_name()

Synopsis `readonly attribute ScopedName absolute_name;`

Description Gives the absolute scoped name of an object.

Notes CORBA-defined.

Contained::containing_repository()

Synopsis `readonly attribute Repository containing_repository;`

Description Gives the `Repository` within which the object is contained.

Notes CORBA-defined.

Contained::defined_in

Synopsis `attribute Container defined_in;`

Description Specifies the `Repository ID` for the Interface Repository object in which the object is contained.

An IFR object is said to be contained by the IFR object in which it is defined. For example, an `InterfaceDef` object is contained by the `ModuleDef` in which it is defined.

Contained also applies to objects of type `AttributeDef` or `OperationDef`. These objects may also be said to be contained in an `InterfaceDef` object if they are inherited into that interface. Note that inheritance of operations and attributes across the boundaries of different modules is also allowed.

Notes CORBA-defined.

See Also “`Container::contents()`” on page 377

Contained::describe()

Synopsis `Description describe();`

Description Returns a structure of type `Contained::Description`:

```
// IDL
struct Description {
    DefinitionKind kind
    any value;
};
```

This is a generic form of description used as a wrapper for another structure stored in the `value` field. Depending on the type of the `Contained` object, the `value` field contains a corresponding description structure:

```
ConstantDescription
ExceptionDescription
AttributeDescription
OperationDescription
ModuleDescription
InterfaceDescription
TypeDescription
```

The last of these, `TypeDescription` is used for objects of type `StructDef`, `UnionDef`, `EnumDef`, and `AliasDef` (it is associated with interface `TypedefDef` from which these four listed interfaces inherit).

The `kind` field contains the same value as the `def_kind` attribute that `Contained` inherits from `IRObject`.

Notes CORBA-defined.

See Also “`Container::describe_contents()`” on page 383

Contained::id

- Synopsis** `attribute RepositoryId id;`
- Description** A `RepositoryId` provides an alternative method of naming an object which is independent of the `ScopedName`. To be CORBA-compliant, you should follow the naming conventions specified for CORBA `RepositoryIds`. Changing the `id` attribute changes the global identity of the contained object. It is an error to change the `id` to a value that currently exists in the contained object's `Repository`.
- Notes** CORBA-defined.

Contained::move ()

- Synopsis** `void move(in Container new_container,
 in Identifier new_name, in VersionSpec new_version);`
- Description** Removes this object from its container, and adds it to the container specified by `new_container`. The new container must:
- ◆ Be in the same repository.
 - ◆ Be capable of containing an object of this type.
 - ◆ Not contain an object of the same name (unless multiple versions are supported).
- The `name` attribute of the object being moved is changed to that specified by the `new_name` parameter. The `version` attribute is changed to that specified by the `new_version` parameter.
- Notes** CORBA-defined.
- See Also** “CORBA::Container” on page 375

Contained::name

Synopsis attribute Identifier name;

Description The name of the object within its scope. For example, in the following definition:

```
// IDL
interface Example {
    void op();
};
```

the names are `Example` and `op`. A name must be unique within its scope but is not necessarily unique within an Interface Repository. You can change the `name` attribute, however, it is an error to change it to a value that is currently in use within the object's Container.

Notes CORBA-defined.

See Also “Contained::id” on page 373

Contained::version

Synopsis attribute VersionSpec version;

Description The version number for this object. Each interface object is identified by a version that distinguishes it from other objects of the same name.

Notes CORBA-defined.

CORBA::Container

Synopsis Interface `Container` describes objects that can contain other objects. Such objects are:

- `Repository`
- `ModuleDef`
- `InterfaceDef`

CORBA

```
// IDL
// In module CORBA.

typedef sequence <Contained> ContainerSeq;

interface Container : IRObject {

    Contained lookup(in ScopedName search_name);

    ContainedSeq contents(
        in DefinitionKind limit_type,
        in boolean exclude_inherited);

    ContainedSeq lookup_name(
        in Identifier search_name,
        in long levels_to_search,
        in DefinitionKind limit_type,
        in boolean exclude_inherited);

    struct Description {
        Contained contained_object;
        DefinitionKind kind;
        any value;
    };

    typedef sequence<Description> DescriptionSeq;
```

```
DescriptionSeq describe_contents(  
    in DefinitionKind limit_type,  
    in boolean exclude_inherited,  
    in long max_returned_objs);  
  
ModuleDef create_module(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version  
);  
  
ConstantDef create_constant(  
    in RepositoryId id,  
  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType type,  
    in any value);  
  
StructDef create_struct(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in StructMemberSeq members);  
  
UnionDef create_union(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType discriminator_type,  
    in UnionMemberSeq members);  
  
EnumDef create_enum(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in EnumMemberSeq members);  
  
AliasDef create_alias(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType original_type);
```



```
InterfaceDef create_interface(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in InterfaceDefSeq base_interfaces);  
  
ExceptionDef create_exception(  
    in RepositoryId id;  
    in Identifier name,  
    in VersionSpec version,  
    in StructMemberSeq members);  
};
```

Notes CORBA-defined.

See Also “CORBA::IObject” on page 397

Container::contents()

Synopsis ContainedSeq contents(in DefinitionKind limit_type,
in boolean exclude_inherited);

Description Returns a sequence of Contained objects that are directly contained in (defined in or inherited into) the target object. You can use this operation to navigate through the hierarchy of definitions—starting, for example, at a Repository.

Parameters

limit_type	If set to dk_all, all of the contained Interface Repository objects are returned. If set to the DefinitionKind for a specific interface type, it returns only interfaces of that type. For example, if set to dk_Operation, it returns contained operations only.
exclude_inherited	Applies only to interfaces. If set to TRUE, inherited objects are not returned. If set to FALSE, objects are returned even if they are inherited.

Notes CORBA-defined.

See Also “Container::describe_contents()” on page 383

Container::create_alias()

Synopsis

```
UnionDef create_alias(in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType original_type);
```

Description

Creates a new `AliasDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `AliasDef` object is defined.

Parameters

<code>id</code>	The <code>RepositoryId</code> for the new <code>AliasDef</code> object. An error is returned if an <code>Interface Repository</code> object with the same <code>id</code> already exists within the object's <code>Repository</code> .
<code>name</code>	The name for the new <code>AliasDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new <code>AliasDef</code> .
<code>original_type</code>	The original type that is being aliased.

Notes

CORBA-defined.

See Also

“CORBA::AliasDef” on page 361

Container::create_constant()

Synopsis

```
ConstantDef create_constant(in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType type,  
    in any value);
```

Description

Creates a `ConstantDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `ConstantDef` object is defined.

Parameters

id	The RepositoryId of the new ConstantDef object. It is an error to specify an id that already exists within the object's Repository.
name	The name of the new ConstantDef object. It is an error to specify a name that already exists within the object's Container when multiple versions are not supported.
version	The version number of the new ConstantDef object.
type	The type of the defined constant. This must be one of the simple types (long, short, ulong, ushort, float, double, char, string, boolean).
value	The value of the defined constant.

Notes CORBA-defined.

See Also "CORBA::ConstantDef" on page 367

Container::create_enum()**Synopsis**

```
EnumDef create_enum(in RepositoryId id,  
                   in Identifier name,  
                   in VersionSpec version,  
                   in EnumMemberSeq members);
```

Description

Creates a new EnumDef object within the target Container. The defined_in attribute is set to Container. The containing_repository attribute is set to the Repository in which the new EnumDef object is defined.

Parameters

id	The RepositoryId of the new EnumDef object. It is an error to specify an id that already exists within the Repository.
name	The name of the EnumDef object. It is an error to specify a name that already exists within the object's Container when multiple versions are not supported.
version	The version number of the new EnumDef object.
members	A sequence of EnumMember structures that describe each member of the new EnumDef object.

Notes CORBA-defined.
See Also “CORBA::EnumDef” on page 386

Container::create_exception()

Synopsis

```
ExceptionDef create_exception(in RepositoryId id,  
                             in Identifier name,  
                             in VersionSpec version,  
                             in StructMemberSeq members);
```

Description Creates a new `ExceptionDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `ExceptionDef` object is defined. The `type` attribute of the `StructMember` structures is ignored and should be set to `_tc_void`.

Parameters

`id` The `RepositoryId` of the new `ExceptionDef` object. It is an error to specify an `id` that already exists within the object's `Repository`.

`name` The name of the new `ExceptionDef` object. It is an error to specify a name that already exists within the object's `Container` when multiple versions are not supported.

`version` A version number for the new `ExceptionDef` object.

`members` A sequence of `StructMember` structures that describe each member of the new `ExceptionDef` object.

Notes CORBA-defined.
See Also “CORBA::ExceptionDef” on page 388

Container::create_interface()

Synopsis

```
InterfaceDef create_interface(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in InterfaceDefSeq base_interfaces);
```

Description Creates a new empty `InterfaceDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `InterfaceDef` object is defined.

Parameters

<code>id</code>	The <code>RepositoryId</code> of the new <code>InterfaceDef</code> object. It is an error to specify an <code>id</code> that already exists within the object's <code>Repository</code> .
<code>name</code>	The name of the new <code>InterfaceDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new <code>InterfaceDef</code> object.
<code>base_interfaces</code>	A sequence of <code>InterfaceDef</code> objects from which the new interface inherits.

Notes CORBA-defined.

See Also “CORBA::InterfaceDef” on page 392

Container::create_module()**Synopsis**

```
ModuleDef create_module(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version);
```

Description Creates an empty `ModuleDef` object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the `Repository` in which the newly-created `ModuleDef` object is defined.

Parameters

<code>id</code>	The <code>RepositoryId</code> of the new <code>ModuleDef</code> object. It is an error to specify an <code>id</code> that already exists within the object's <code>Repository</code> .
<code>name</code>	The name of the new <code>ModuleDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.

`version` A version for the `ModuleDef` object to be created.

Notes CORBA-defined.

Container::create_struct()

Synopsis

```
StructDef create_struct(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in StructMemberSeq members);
```

Description

Creates a new `StructDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `StructDef` object is defined. The `type` attribute of the `StructMember` structures is ignored and should be set to `_tc_void`.

Parameters

`id` The `RepositoryId` of the new `StructDef` object. It is an error to specify an `id` that already exists within the object's `Repository`.

`name` The name of the new `StructDef` object. It is an error to specify a name that already exists within the object's `Container` when multiple versions are not supported.

`version` A version for the new `StructDef` object.

`members` A sequence of `StructMember` structures that describe each member of the new `StructDef` object.

Notes CORBA-defined.

See Also "CORBA::StructDef" on page 413

Container::create_union()

Synopsis

```
UnionDef create_union(  
    in RepositoryId id,  
    in Identifier name,
```

```

    in VersionSpec version,
    in IDLType discriminator_type,
    in UnionMemberSeq members);

```

Description Creates a new `UnionDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `UnionDef` object is defined. The `type` attribute of the `UnionMember` structures is ignored and should be set to `_tc_void`.

Parameters

<code>id</code>	The <code>RepositoryId</code> of the new <code>UnionDef</code> object. It is an error to specify an <code>id</code> that already exists within the object's <code>Repository</code> .
<code>name</code>	The name of the new <code>UnionDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new <code>UnionDef</code> object.
<code>discriminator_type</code>	The type of the Union discriminator.
<code>members</code>	A sequence of <code>UnionMember</code> structures that describe each member of the new <code>UnionDef</code> object.

Notes CORBA-defined.

See Also “CORBA::UnionDef” on page 418

Container::describe_contents()

Synopsis

```

DescriptionSeq describe_contents(
    in DefinitionKind limit_type,
    in boolean exclude_inherited,
    in long max_returned_objs);

```

Description A combination of the operation `Contained::describe()` and the operation `Container::contents()`, the `describe_contents()` operation returns a sequence of structures of type `Container::Description`:

```

// IDL
struct Description {
    Contained contained_object;

```

```
        DefinitionKind kind;  
        any value;  
    };
```

Each of these structures gives the object reference of a contained object, together with its `kind` and `value`.

Notes CORBA-defined.

See Also “Container::contents()” on page 377
“Contained::describe()” on page 372

Container::lookup()

Synopsis `Contained lookup(in ScopedName search_name);`

Description Locates an object name within the target container. The objects can be directly or indirectly defined in or inherited into the target container.

Parameters

`search_name` The name of the object to search for relative to the target container. If a relative name is given, the object is looked up relative to the target container. If `search_name` is an absolute scoped name (prefixed by ‘:.’), the object is located relative to the containing `Repository`.

Notes CORBA-defined.

See Also “Container::lookup_name()” on page 385

Container::lookup_name()**Synopsis**

```
ContainedSeq lookup_name(  
    in Identifier search_name,  
    in long levels_to_search,  
    in DefinitionKind limit_type,  
    in boolean exclude_inherited);
```

Description

Locates an object or objects by name within the target container. The named objects can be directly or indirectly defined in or inherited into the target container.

Parameters

<code>search_name</code>	The simple name of the object to search for. The use of the wildcard character "*" is also allowed (Orbix specific).
<code>levels_to_search</code>	Defines whether the search is confined to the current object or should include all Interface Repository objects contained by the object. If set to -1, the current object and all contained Interface Repository objects are searched. If set to 1, only the current object is searched.
<code>limit_type</code>	If this is set to <code>dk_all</code> , all the contained Interface Repository objects are returned. If set to the <code>DefinitionKind</code> for a particular Interface Repository kind, it returns only objects of that kind. For example, if set to <code>dk_Operation</code> , it returns contained operations only.
<code>exclude_inherited</code>	Applies only to interfaces. If set to <code>TRUE</code> , inherited objects are not returned. If set to <code>FALSE</code> , objects are returned even if they are inherited.

Return Value

Returns a sequence of contained objects; more than one object, having the same simple name can exist within a nested scope structure.

Notes

CORBA-defined.

CORBA::EnumDef

Synopsis Interface EnumDef describes an IDL enumeration definition.

CORBA

```
// IDL
// In module CORBA.

typedef sequence <Identifier> EnumMemberSeq;

interface EnumDef : TypedefDef {
    attribute EnumMemberSeq members;
};
```

Notes CORBA-defined.

See Also “CORBA::TypedefDef” on page 416

EnumDef::describe()

Synopsis Description describe();

Description Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Enum. The value member is an any whose TypeCode is _tc_TypeDescription and whose value is a structure of type TypeDescription:

```
// IDL
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

The `type` field of the `struct` gives the `TypeCode` of the defined `Enum`.

See Also “`TypedefDef::describe()`” on page 416

EnumDef::members

Synopsis `attribute EnumMemberSeq members;`

Description Contains the enumeration’s list of identifiers (its enumerated constants).

You can change the set of enumerated constants by changing this attribute.

Notes CORBA-defined.

CORBA::ExceptionDef

Synopsis Interface ExceptionDef describes an IDL exception. It inherits from interface Contained.

CORBA

```
// IDL
// In module CORBA.
struct StructMember {
    Identifier name;
    TypeCode type;
    IDLType type_def;
};
typedef sequence <StructMember> StructMemberSeq;

interface ExceptionDef : Contained {
    readonly attribute TypeCode type;
    attribute StructMemberSeq members;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370

ExceptionDef::describe()

Synopsis Description describe();

Description Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Exception. The value member is an any whose TypeCode is _tc_ExceptionDescription and whose value is a structure of type ExceptionDescription:

```
// IDL
struct ExceptionDescription {
```

```
Identifier name;  
RepositoryId id;  
RepositoryId defined_in;  
VersionSpec version;  
TypeCode type;  
};
```

The `type` field of the struct gives the `TypeCode` of the defined exception.

Notes CORBA-defined.

See Also “`Contained::describe()`” on page 372

ExceptionDef::members

Synopsis attribute `StructMemberSeq` `members`;

Description In a sequence of `StructMember` structures, the `members` attribute describes the exception’s members.

You can modify the `members` attribute to change the structure’s members. You should set only the `name` and `type_def` fields of each `StructMember`. The `type` field should be set to `_tc_void`, and it is set automatically to the `TypeCode` of the `type_def` field.

Notes CORBA-defined.

See Also “`CORBA::StructDef`” on page 413
“`ExceptionDef::type`” on page 389

ExceptionDef::type

Synopsis readonly attribute `TypeCode` `type`;

Description The type of the exception (from which the definition of the exception can be understood). The `TypeCode` kind for an exception is `tk_except`.

Notes CORBA-defined.

See Also “`ExceptionDef::members`” on page 389

CORBA::IDLType

Synopsis The abstract interface `IDLType` describes Interface Repository objects that represent interfaces, type definitions, structures, unions, enumerations, aliases (that is, IDL typedef), primitives, bounded strings, sequences, and array types. Thus, it is a base interface for the following interfaces:

- `ArrayDef`
- `InterfaceDef`
- `PrimitiveDef`
- `StringDef`
- `SequenceDef`
- `TypedefDef`
- `AliasDef`
- `StructDef`
- `UnionDef`
- `EnumDef`

CORBA

```
// IDL
// In module CORBA.
interface IDLType : IRObject {
    readonly attribute TypeCode type;
};
```

Notes CORBA-defined.

See Also “CORBA::IRObject” on page 397

IDLType::type

Synopsis	readonly attribute TypeCode type;
Description	Encodes the type information of an Interface Repository object. Most type information can also be extracted using operations and attributes defined on derived types of IDLType.
Notes	CORBA-defined.

CORBA::InterfaceDef

Synopsis

Interface `InterfaceDef` describes an IDL interface definition. It may contain lists of constants, typedefs, exceptions, operations, and attributes and inherits from the interfaces `Container`, `Contained` and `IDLType`.

The `_get_interface()` function on an object reference returns a reference to the `InterfaceDef` object that defines the CORBA object's interface.

CORBA

```
// IDL
// In module CORBA.

interface InterfaceDef;

typedef sequence <InterfaceDef> InterfaceDefSeq;
typedef sequence <RepositoryId> RepositoryIdSeq;
typedef sequence <OperationDescription> OpDescriptionSeq;
typedef sequence <AttributeDescription> AttrDescriptionSeq;

interface InterfaceDef : Container, Contained, IDLType {
    attribute InterfaceDefSeq base_interfaces;

    boolean is_a (in RepositoryId interface_id);

    struct FullInterfaceDescription {
        Identifier name;
        RepositoryId id;
        RepositoryId defined_in;
        VersonSpec version;
        OpDescriptionSeq operations;
        AttrDescriptionSeq attributes;
        RepositoryIdSeq base_interfaces;
        TypeCode type;
    };

    FullInterfaceDescription describe_interface();

    AttributeDef create_attribute (
        in RepositoryId id,
        in Identifier name,
```



```
        in VersionSpec version,  
        in IDLType type,  
        in AttributeMode mode);  
OperationDef create_operation (  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType result,  
    in OperationMode mode,  
    in ParDescriptionSeq params,  
    in ExceptionDefSeq exceptions,  
    in ContextIdSeq contexts);  
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“CORBA::Container” on page 375

InterfaceDef::base_interfaces

Synopsis attribute InterfaceDefSeq base_interfaces;

Description In a sequence of InterfaceDefs, the `base_interfaces` attribute lists the interfaces from which this interface inherits.

You can change the inheritance specification of an `InterfaceDef` object by changing its `base_interfaces` attribute. It is an error if the name of any definition contained in the interface conflicts with the name of a definition in any of the base interfaces.

Notes CORBA-defined.

InterfaceDef::create_attribute()

Synopsis AttributeDef create_attribute(
 in RepositoryId id,
 in Identifier name,
 in VersionSpec version,
 in IDLType type,
 in AttributeMode mode);

Description Creates a new `AttributeDef` within the target `InterfaceDef`. The `defined_in` attribute of the new `AttributeDef` is set to the target `InterfaceDef`.

Parameters

<code>id</code>	The <code>RepositoryId</code> of the new attribute. It is an error to specify an <code>id</code> that already exists within the target object's <code>Repository</code> .
<code>name</code>	The name of the attribute. It is an error to specify a name that already exists within this <code>InterfaceDef</code> .
<code>version</code>	A version for this attribute.
<code>type</code>	The <code>IDLType</code> for this attribute.
<code>mode</code>	Specifies whether the attribute is read-only (<code>ATTR_READONLY</code>) or read/write (<code>ATTR_NORMAL</code>).

Notes CORBA-defined.

See Also “CORBA::AttributeDef” on page 365

InterfaceDef::create_operation()

Synopsis

```
OperationDef create_operation(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType result,  
    in OperationMode mode,  
    in ParDescriptionSeq params,  
    in ExceptionDefSeq exceptions,  
    in ContextIdSeq contexts);
```

Description Creates a new `OperationDef` within the target `InterfaceDef`. The `defined_in` attribute of the new `OperationDef` is set to the target `InterfaceDef`.

Parameters

<code>id</code>	The <code>RepositoryId</code> of the new attribute. It is an error to specify an <code>id</code> that already exists within the target object's <code>Repository</code> .
<code>name</code>	The name of the attribute. It is an error to specify a name that already exists within this <code>InterfaceDef</code> .

version	A version number for this operation.
result	The return type for this operation.
mode	Specifies whether this operation is normal (OP_NORMAL) or oneway (OP_ONEWAY).
params	A sequence of ParameterDescription structures which describe the parameters to this operation.
exceptions	A sequence of ExceptionDef objects that describe the exceptions this operation can raise.
contexts	A sequence of context identifiers for this operation.

Notes CORBA-defined.

See Also “CORBA::OperationDef” on page 402
“CORBA::ExceptionDef” on page 388

InterfaceDef::describe()

Synopsis

```
Description describe();
```

Description

Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Interface. The value member is an any whose TypeCode is _tc_InterfaceDescription and whose value is a structure of type InterfaceDescription:

```
// IDL
struct InterfaceDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    RepositoryIdSeq base_interfaces;
};
```

Notes CORBA-defined.

See Also “Contained::describe()” on page 372

InterfaceDef::describe_interface ()

Synopsis FullInterfaceDescription describe_interface();

Description Returns a description of the interface, including its operations, attributes, and base interfaces in a structure of type FullInterfaceDescription:

```
struct FullInterfaceDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersonSpec version;
    OpDescriptionSeq operations;
    AttrDescriptionSeq attributes;
    RepositoryIdSeq base_interfaces;
    TypeCode type;
};
```

You can determine details of exceptions and contexts via the returned sequence of OperationDescription structures.

Notes CORBA-defined.

See Also “OperationDef::describe()” on page 403
“AttributeDef::describe()” on page 365

InterfaceDef::is_a ()

Synopsis boolean is_a(in RepositoryId interface_id);

Description Returns TRUE if the interface is either identical to or inherits, directly or indirectly, from the InterfaceDef object whose RepositoryId is passed in the parameter interface_id. Otherwise it returns FALSE.

Notes CORBA-defined.

CORBA::IObject

Synopsis The interface `IObject` provides a base interface from which all Interface Repository interfaces are derived.

CORBA

```
// IDL
// In module CORBA.

interface IObject {
    readonly attribute DefinitionKind def_kind;
    void destroy ();
};
```

Notes CORBA-defined.

IObject::def_kind

Synopsis `readonly attribute DefinitionKind def_kind`

Description Identifies the kind of an Interface Repository (IFR) object. For example, an `OperationDef` object, describing an IDL operation, has the kind `dk_Operation`.

Notes CORBA-defined.

IObject::destroy()

Synopsis `void destroy();`

Description Deletes an IFR object. This also deletes any objects contained within the target object. It is an error to invoke the `destroy()` operation on a `Repository` or on a `PrimitiveDef` object.

Notes CORBA-defined.

CORBA::IT_InterfaceDef

Synopsis The interface `IT_InterfaceDef` adds one extra function to the standard `InterfaceDef` object.

CORBA

```
// IDL
// In module CORBA.

interface IT_InterfaceDef : InterfaceDef {
    InterfaceDefSeq derived_interfaces();
};
```

Notes Orbix-specific.

See Also “CORBA::InterfaceDef” on page 392

IT_InterfaceDef::derived_interfaces()

Synopsis `InterfaceDefSeq derived_interfaces();`

Description Returns a list of all the interfaces that are derived from the given interface. They are returned as a sequence of `InterfaceDef` objects.

Notes Orbix-specific.

See Also “InterfaceDef::base_interfaces” on page 393

CORBA::IT_Repository

Synopsis The interface `IT_Repository` provides transactional access to the Interface Repository. These operations can be used to help ensure that the repository is left in a consistent state. In the present implementation only one transaction may be active at a time.

Note: This transactional access is a feature of the Interface Repository and should not be confused with transactions in OrbixOTS.

CORBA

```
// IDL
// In module CORBA.

interface IT_Repository : Repository {
    unsigned long start();
    void commit(in unsigned long transaction_id);
    void rollBack(in unsigned long transaction_id);
    typedef sequence <unsigned long> transactions;
    transactions active_transactions();
};
```

Notes Orbix-specific.

See Also “CORBA::Container” on page 375
“CORBA::Repository” on page 407

IT_Repository::start()

Synopsis `unsigned long start();`

Description Starts a new transaction.

Return Value Returns a transaction identifier for the transaction started or 0 if the transaction could not be started.

Notes Orbix-specific.

IT_Repository::commit()

Synopsis `void commit(in unsigned long transaction_id);`

Description Commits a transaction.

Parameters

`transaction_id` The identifier for the transaction.

Notes Orbix-specific.

See Also “IT_Repository::start()” on page 399

IT_Repository::rollBack()

Synopsis `void rollBack(in unsigned long transaction_id);`

Description Rolls back all changes made during the transaction to the previous commit point.

Parameters

`transaction_id` The identifier for the transaction to be rolled back.

Notes Orbix-specific.

See Also “IT_Repository::commit()” on page 400

IT_Repository::active_transactions()

Synopsis `transactions active_transactions();`

Description Returns a sequence of active `transaction_ids`. If no transaction is active, an empty sequence is returned.

Notes Orbix-specific.

CORBA::ModuleDef

Synopsis The interface `ModuleDef` describes an IDL module. It inherits from the interfaces `Container` and `Contained`.

CORBA

```
// IDL
// In module CORBA.
interface ModuleDef : Container, Contained {
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“CORBA::Container” on page 375

ModuleDef::describe()

Synopsis Description `describe()`;

Description Inherited from `Contained`, the `describe()` operation returns a structure of type `Contained::Description`:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The `DefinitionKind` for the `kind` member is `dk_Module`. The `value` member is an any whose `TypeCode` is `_tc_ModuleDescription` and whose value is a structure of type `ModuleDescription`:

```
struct ModuleDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
};
```

Notes CORBA-defined.

See Also “Contained::describe()” on page 372

CORBA::OperationDef

Synopsis Interface `OperationDef` describes an IDL operation that is defined in an IDL interface.

One use of `OperationDef` is to construct an `NVList` for a specific operation for use in the Dynamic Invocation Interface. See `CORBA::ORB::create_operation_list()` for details.

CORBA

```
// IDL
// In module CORBA.

enum OperationMode { OP_NORMAL, OP_ONEWAY };

enum ParameterMode { PARAM_IN, PARAM_OUT, PARAM_INOUT };

struct ParameterDescription {
    Identifier name;
    TypeCode type;
    IDLType type_def;
    ParameterMode mode;
};

typedef sequence <ParameterDescription> ParDescriptionSeq;

typedef Identifier ContextIdentifier;
typedef sequence <ContextIdentifier> ContextIdSeq;

typedef sequence <ExceptionDescription> ExcDescriptionSeq;

interface OperationDef : Contained {
    readonly attribute TypeCode result;
    attribute IDLType result_def;
    attribute ParDescriptionSeq params;
    attribute OperationMode mode;
    attribute ContextIdSeq contexts;
    attribute ExceptionDefSeq exceptions;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“CORBA::ExceptionDef” on page 388

OperationDef::contexts

Synopsis `attribute ContextIdSeq contexts;`
Description The list of context identifiers specified in the context clause of the operation.
Notes CORBA-defined.

OperationDef::exceptions

Synopsis `attribute ExceptionDefSeq`
Description The list of exceptions that the operation can raise.
Notes CORBA-defined.
See Also “CORBA::ExceptionDef” on page 388

OperationDef::describe()

Synopsis `Description describe();`
Description Inherited from `Contained`, the `describe()` operation returns a structure of type `Contained::Description`:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The `DefinitionKind` for the `kind` member is `dk_Operation`. The value member is an any whose `TypeCode` is `_tc_OperationDescription` and whose value is a structure of type `OperationDescription`:

```
struct OperationDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
```

```
        TypeCode result;
        OperationMode mode;
        ContextIdSeq contexts;
        ParDescriptionSeq parameters;
        ExcDescriptionSeq exceptions;
    };
```

Notes CORBA-defined.

See Also “Contained::describe()” on page 372
“CORBA::ExceptionDef” on page 388

OperationDef::mode

Synopsis attribute OperationMode mode;

Description Specifies whether the operation is normal (OP_NORMAL) or oneway (OP_ONEWAY). You can set the mode attribute set to OP_ONEWAY only if the result is `_tc_void` and all parameters have a mode of PARAM_IN.

Notes CORBA-defined.

OperationDef::params

Synopsis attribute ParDescriptionSeq params;

Description Specifies the parameters for this operation. It is a sequence of structures of type ParameterDescription:

```
    struct ParameterDescription {
        Identifier name;
        TypeCode type;
        IDLType type_def;
        ParameterMode mode;
    };
```

The `name` member provides the name for the parameter. The `type` member identifies the `TypeCode` for the parameter. The `type_def` member identifies the definition of the type for the parameter. The `mode` specifies whether the parameter is an in (PARAM_IN), an out (PARAM_OUT) or an inout (PARAM_INOUT) parameter. The order of the `ParameterDescriptions` is significant.

Notes CORBA-defined.
See Also “IDLType::type” on page 391

OperationDef::result

Synopsis `readonly attribute TypeCode result;`
Description The return type of this operation. The attribute `result_def` contains the same information.
Notes CORBA-defined.
See Also “OperationDef::result_def” on page 405

OperationDef::result_def

Synopsis `attribute IDLType result_def;`
Description Describes the return type for this operation. The attribute `result` contains the same information.
Setting the `result_def` attribute also updates the `result` attribute.
Notes CORBA-defined.
See Also “IDLType::type” on page 391
“OperationDef::result” on page 405

CORBA::PrimitiveDef

Synopsis Interface `PrimitiveDef` represents a primitive type such as short or long. `PrimitiveDef` objects are anonymous (unnamed) and owned by the Repository. You cannot create objects of type `PrimitiveDef`. When needed, you can obtain a reference to a `PrimitiveDef` through a call to the operation `CORBA::Repository::get_primitive()`.

```
// IDL
// In module CORBA.

enum PrimitiveKind {
    pk_null, pk_void, pk_short, pk_long, pk_ushort, pk_ulong,
    pk_float, pk_double, pk_boolean, pk_char, pk_octet,
    pk_any, pk_TypeCode, pk_Principal, pk_string, pk_objref
};

interface PrimitiveDef : IDLType {
    readonly attribute PrimitiveKind kind;
};
```

Notes CORBA-defined.

See Also “IDLType::type” on page 391

PrimitiveDef::kind

Synopsis `readonly attribute PrimitiveKind kind;`

Description Identifies which of the primitive types is represented by this `PrimitiveDef`. A `PrimitiveDef` with a kind of type `pk_string` represents an unbounded string, a bounded string is represented by the interface `StringDef`. A `PrimitiveDef` with a kind of type `pk_objref` represents the IDL type `Object`.

Notes CORBA-defined.

See Also “IDLType::type” on page 391
“CORBA::StringDef” on page 415

CORBA::Repository

Synopsis The Interface Repository itself is a container for IDL type definitions. Its interface is described by the `Repository` interface. It can be used to look up any definition, by either name or identity, that is defined in the global name space or within an interface or module.

```
CORBA // IDL
// In module CORBA.

interface Repository : Container {
    Contained lookup_id(
        in RepositoryId search_id);

    PrimitiveDef get_primitive (in PrimitiveKind kind);

    StringDef create_string (in unsigned long bound);

    SequenceDef create_sequence (
        in unsigned long bound,
        in IDLType element_type);

    ArrayDef create_array (
        in unsigned long length,
        in IDLType element_type);
};
```

Notes CORBA-defined.

See Also “CORBA::Container” on page 375

Repository::create_array()

- Synopsis** `ArrayDef create_array(in unsigned long length,
 in IDLType element_type);`
- Description** Returns a new array object defining an anonymous (unnamed) type. The new array object must be used in the definition of exactly one other object; it is deleted when the object it is contained in is deleted. It is the application's responsibility to delete any anonymous type object it creates if subsequently that object is not successfully used in the definition of a `Contained` object.
- Parameters**
- | | |
|---------------------------|--|
| <code>length</code> | The number of elements in the array. |
| <code>element_type</code> | The type of element that the array contains. |
- Notes** CORBA-defined.
- See Also** “CORBA::ArrayDef” on page 363
 “CORBA::IObject” on page 397

Repository::create_sequence()

- Synopsis** `SequenceDef create_sequence (in unsigned long bound,
 in IDLType element_type);`
- Description** Returns a new sequence object defining an anonymous (unnamed) type. The new sequence object must be used in the definition of exactly one other object; it is deleted when the object it is contained in is deleted. It is the application's responsibility to delete any anonymous type object it creates if subsequently that object is not successfully used in the definition of a `Contained` object.
- Parameters**
- | | |
|---------------------------|--|
| <code>bound</code> | The number of elements in the sequence. A <code>bound</code> of 0 indicates an unbounded sequence. |
| <code>element_type</code> | The type of element that the sequence contains. |
- Notes** CORBA-defined.
- See Also** “CORBA::SequenceDef” on page 411

Repository::create_string()

- Synopsis** `StringDef create_string (in unsigned long bound);`
- Description** Returns a new string object defining an anonymous (unnamed) type. The new string object must be used in the definition of exactly one other object; it is deleted when the object it is contained in is deleted. It is the application's responsibility to delete any anonymous type object it creates if subsequently that object is not successfully used in the definition of a `Contained` object.
- Parameters**
- `bound` The maximum number of characters in the string. This cannot be 0.
- Notes** CORBA-defined.
- See Also** "CORBA::StringDef" on page 415

Repository::get_primitive()

- Synopsis** `PrimitiveDef get_primitive(in PrimitiveKind kind);`
- Description** Returns a reference to a `PrimitiveDef` of the specified `PrimitiveKind`. All `PrimitiveDefs` are owned by the `Repository`, one primitive object per primitive type (for example, `short`, `long`, `unsigned short`, `unsigned long` and so on).
- Notes** CORBA-defined.
- See Also** "CORBA::PrimitiveDef" on page 406

Repository::describe_contents()

- Synopsis** `sequence<Description> describe_contents (`
`in InterfaceName restrict_type,`
`in boolean exclude_inherited,`
`in long max_returned_objs);`
- Description** The operation `describe_contents()` is inherited from interface `Container`. It returns a sequence of `Container::Description` structures; one such structure for each top level item in the repository. The structure is defined as:

```
// IDL
```

```
struct Description {
    Contained contained_object;
    DefinitionKind kind;
    any value;
};
```

Each structure has the following members:

<code>contained_object</code>	The object reference, of type <code>Contained</code> , of the contained top level object. You can call <code>describe()</code> an object reference of type <code>Contained</code> , to get further information on a top level object in the <code>Repository</code> .
<code>kind</code>	The kind of the object being described.
<code>value</code>	An any that may contain one of the following structs: <ul style="list-style-type: none">• <code>ModuleDescription</code>• <code>ConstantDescription</code>• <code>TypeDescription</code>• <code>ExceptionDescription</code>• <code>AttributeDescription</code>• <code>ParameterDescription</code>• <code>OperationDescription</code>• <code>InterfaceDescription</code>

Notes CORBA-defined.

See Also “`Container::describe_contents()`” on page 383

Repository::lookup_id()

Synopsis `Contained lookup_id(in RepositoryId search_id);`

Description Returns an object contained within the `Repository` given its `RepositoryId`.

Notes CORBA-defined.

See Also “`CORBA::Contained`” on page 370

CORBA::SequenceDef

Synopsis Interface `SequenceDef` represents an IDL sequence definition. It inherits from the interface `IDLType`.

CORBA

```
// IDL
// In module CORBA.
interface SequenceDef : IDLType {
    attribute unsigned long bound;
    readonly attribute TypeCode element_type;
    attribute IDLType element_type_def;
};
```

Notes CORBA-defined.

See Also “CORBA::IDLType” on page 390
“Repository::create_sequence()” on page 408

SequenceDef::bound

Synopsis `attribute unsigned long bound;`

Description The bound of the sequence. A bound of 0 indicates an unbounded sequence type. Changing the `bound` attribute also updates the inherited `type` attribute.

Notes CORBA-defined.

See Also “SequenceDef::type” on page 412

SequenceDef::element_type

Synopsis `readonly attribute TypeCode element_type;`

Description Describes the type of the element contained within this sequence. The attribute `element_type_def` contains the same information.

Notes CORBA-defined.

See Also “SequenceDef::element_type_def” on page 412

SequenceDef::element_type_def

- Synopsis** `attribute IDLType element_type_def;`
- Description** Describes the type of element contained within this sequence. The attribute `element_type` contains the same information. Setting the `element_type_def` attribute also updates the `element_type` and `IDLType::type` attributes.
- Notes** CORBA-defined.
- See Also** “SequenceDef::element_type” on page 411
 “IDLType::type” on page 391

SequenceDef::type

- Synopsis** `readonly attribute TypeCode type;`
- Description** The `type` attribute is inherited from interface `IDLType`. This attribute is a `tk_sequence TypeCode` that describes the sequence. It is updated automatically whenever the attributes `bound` or `element_type_def` are changed.
- Notes** CORBA-defined.
- See Also** “SequenceDef::element_type” on page 411
 “SequenceDef::bound” on page 411

CORBA::StructDef

Synopsis Interface StructDef describes an IDL structure.

CORBA

```
// IDL
// In module CORBA.
struct StructMember {
    Identifier name;
    TypeCode type;
    IDLType type_def;
};

typedef sequence<StructMember> StructMemberSeq;

interface StructDef : TypedefDef {
    attribute StructMemberSeq members;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“Container::create_struct()” on page 382

StructDef::describe()

Synopsis Description describe();

Description Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Struct. The value member is an any whose TypeCode is _tc_TypeDescription and whose value is a structure of type TypeDescription:

```
// IDL
// In module CORBA.
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

Notes CORBA-defined.

See Also “TypedefDef::describe()” on page 416

StructDef::members

Synopsis attribute StructMemberSeq members;

Description Describes the members of the structure.

You can modify this attribute to change the members of a structure. Only the `name` and `type_def` fields of each `StructMember` should be set (the `type` field should be set to `_tc_void` and it is set automatically to the `TypeCode` of the `type_def` field).

Notes CORBA-defined.

See Also “CORBA::TypedefDef” on page 416

CORBA::StringDef

Synopsis Interface `StringDef` represents a bounded string type. Unbounded strings are primitive types. A `StringDef` object is anonymous, that is, unnamed.

CORBA

```
// IDL
// In module CORBA.
interface StringDef : IDLType {
    attribute unsigned long bound;
};
```

Notes CORBA-defined.

See Also “CORBA::IDLType” on page 390
“CORBA::PrimitiveDef” on page 406
“Repository::create_string()” on page 409

StringDef::bound

Synopsis attribute unsigned long bound;

Description Specifies the bound of the string. This cannot be zero.

Notes CORBA-defined.

CORBA::TypedefDef

Synopsis The abstract interface `TypedefDef` is inherited by all Interface Repository interfaces (except `InterfaceDef`) that define named types. Named types are types for which a name must appear in their definition such as structures, unions, enumerations and aliases.

Anonymous types (`PrimitiveDef`, `StringDef`, `SequenceDef` and `ArrayDef`) do not inherit from `TypedefDef`.

The role of interface `TypedefDef` in the Interface Repository is not of particular importance; it is merely a base interface for `StructDef`, `UnionDef`, `EnumDef` and `AliasDef`.

CORBA

```
// IDL
// In module CORBA.

interface TypedefDef : Contained, IDLType {
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370

TypedefDef::describe()

Synopsis Description `describe()`;

Description Inherited from `Contained`, the `describe()` operation returns a structure of type `Contained::Description`:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The `DefinitionKind` for the `kind` member is `dk_Typedef`. The `value` member is an any whose `TypeCode` is `_tc_TypeDescription` and whose `value` is a structure of type `TypeDescription`.


```
// IDL
// In module CORBA.
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

Notes CORBA-defined.

See Also “Contained::describe()” on page 372

CORBA::UnionDef

Synopsis Interface UnionDef represents an IDL union.

```
CORBA // IDL
// In module CORBA.

struct UnionMember {
    Identifier name;
    any label;
    TypeCode type;
    IDLType type_def;
};

typedef sequence <UnionMember> UnionMemberSeq;

interface UnionDef : TypedefDef {
    readonly attribute TypeCode discriminator_type;
    attribute IDLType discriminator_type_def;
    attribute UnionMemberSeq members;
};
```

Notes CORBA-defined.

See Also “CORBA::Contained” on page 370
“CORBA::TypedefDef” on page 416
“Container::create_union()” on page 382

UnionDef::describe()**Synopsis**

```
Description describe();
```

Description

Inherited from Contained, the describe() operation returns a structure of type Contained::Description:

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

The DefinitionKind for the kind member is dk_Union. The value member is an any whose TypeCode is _tc_TypeDescription and whose value is a structure of type TypeDescription:

```
// IDL
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

Notes

CORBA-defined.

See Also

“TypedefDef::describe()” on page 416

UnionDef::discriminator_type**Synopsis**

```
readonly attribute TypeCode discriminator_type;
```

Description

Describes the discriminator type for this union. For example, if the union currently contains a long, the discriminator_type is _tc_long. The attribute discriminator_type_def contains the same information.

Notes

CORBA-defined.

UnionDef::discriminator_type_def


- Synopsis** `attribute IDLType discriminator_type_def;`
- Description** Describes the discriminator type for this union. The attribute `discriminator_type` contains the same information.
- Changing this attribute automatically updates the `discriminator_type` attribute and the `IDLType::type` attribute.
- Notes** CORBA-defined.
- See Also** “IDLType::type” on page 391
 “UnionDef::discriminator_type” on page 419

UnionDef::members

- Synopsis** `attribute UnionMemberSeq members;`
- Description** Contains a description of each union member: its name, label and type (`type` and `type_def` contain the same information).
- The `members` attribute can be modified to change the union's members. You should set only the `name`, `label` and `type_def` fields of each `UnionMember`. You should set the `type` field to `_tc_void`, and it is then set automatically to the `TypeCode` of the `type_def` field.
- Notes** CORBA-defined.
- See Also** “CORBA::TypedefDef” on page 416

Part VI

IDL Interface to the Orbix Java Daemon



IDL Interface to the Orbix Java Daemon

Synopsis The Orbix Java daemon is itself an Orbix Java server whose IDL interface is called `IT_daemon`. The Orbix Java daemon is responsible for launching servers (if an appropriate server is not already running) and dispatching operation requests. The daemon is involved, if at all, only with the first operation request from a client—it is not involved with subsequent requests. Two Orbix Java daemon executables are available: `orbixd` and `orbixdj` (the Java daemon).

The Orbix Java daemon is also responsible for managing the Implementation Repository. It accepts requests from the Orbix Java utilities—`putit`, `catit`, `lsit`, and so on. `orbixdj` implements a subset of the `IT_daemon` operations, and these are indicated clearly in the operation descriptions in this section.

Orbix Java

```
// IDL
interface IT_daemon{
    boolean lookUp(in string service,
                  out stringSeq hostList,
                  in octet hops,
                  in string tag);

    boolean addHostsToServer(in string server,
                            in stringSeq hostList);
    boolean addHostsToGroup(in string group,
                            in stringSeq hostList);
    boolean addGroupsToServer(in string server,
                              in stringSeq groupList);
    boolean delHostsFromServer(in string server,
                              in stringSeq hostList);
    boolean delHostsFromGroup(in string group,
                              in stringSeq hostList);
    boolean delGroupsFromServer(in string server,
                                in stringSeq groupList);

    boolean listHostsInServer(in string server,
                             out stringSeq hostList);
    boolean listHostsInGroup(in string group,
                             out stringSeq hostList);
```

```
boolean listGroupsInServer(in string server,
    out stringSeq groupList);

enum LaunchStatus {
    inactive,
    manualLaunch,
    automaticLaunch
};

struct serverDetails {
    string server;
    string marker;
    string principal;
    string code;
    string comms;
    string port;
    unsigned long OSspecific;
    LaunchStatus status;
};

void listActiveServers(out serverDetailsSeq servers);

void killServer(in string name, in string marker);
void newSharedServer(in string serverName,
    in stringSeq marker,
    in stringSeq launchCommand,
    in unsigned long mode_flags);
public void newSharedServer2 (String serverName,
    String[] marker,
    String[] launchCommand,
    int mode_flags,
    int nservers,
    int wellKnownPort);
void newUnSharedServer(in string serverName,
    in stringSeq marker,
    in stringSeq launchCommand,
    in unsigned long mode_flags);

void newPerMethodServer(in string serverName,
    in stringSeq method,
    in stringSeq launchCommand);

void listServers(in string subdir,
```


IDL Interface to the Orbix Java Daemon

```
    out stringSeq servers);

void deleteServer(in string serverName);

boolean serverExists(in string serverName);

public void getIIOPDetails(
    String serverName,
    String markerName,
    String methodName,
    org.omg.CORBA.StringHolder iiopPort,
    org.omg.CORBA.StringHolder activationPolicy);

public void getImplementationDetails(
    String serverName,
    String markerName,
    String methodName,
    org.omg.CORBA.StringHolder codeProtocol,
    org.omg.CORBA.StringHolder commsProtocol,
    org.omg.CORBA.StringHolder commsPort,
    org.omg.CORBA.StringHolder activationPolicy ) ;

void getServer(in string serverName,
    out string commsProtocol,
    out string codeProtocol,
    out string activationPolicy,
    out unsigned long mode_flags,
    out string owner,
    out string invokeList,
    out string launchList,
    out stringSeq markers,
    out stringSeq methods,
    out stringSeq commands);

public void getServer2(String serverName,
    org.omg.CORBA.StringHolder commsProtocol,
    org.omg.CORBA.StringHolder codeProtocol,
    org.omg.CORBA.StringHolder activationPolicy,
    org.omg.CORBA.IntHolder mode_flags,
    org.omg.CORBA.StringHolder owner,
    org.omg.CORBA.StringHolder invokeList,
    org.omg.CORBA.StringHolder launchList,
    org.omg.CORBA.IntHolder nservers,
```

```
        org.omg.CORBA.IntHolder port,
        stringSeqHolder markers,
        stringSeqHolder methods,
        stringSeqHolder commands) ;

void addUnsharedMarker(in string serverName,
    in string markerName,
    in string newCommand);
void removeUnsharedMarker(in string serverName,
    in string markerName);
void addSharedMarker(in string serverName,
    in string markerName,
    in string newCommand);
void removeSharedMarker(in string serverName,
    in string markerName);

void addMethod(in string serverName,
    in string methodName,
    in string newCommand);
void removeMethod(in string serverName,
    in string methodName);
void newDirectory(in string dirName);
void deleteDirectory(in string dirName,
    in boolean deleteChildren);
void changeOwnerServer(in string new_owner,
    in string serverName);
void addInvokeRights(in string userGroup,
    in string serverName);

public void registerPersistentServer(
    String serverName,
    int serverPid,
    org.omg.CORBA.StringHolder codeProtocol,
    org.omg.CORBA.StringHolder commsProtocol,
    org.omg.CORBA.StringHolder commsPort);
void removeInvokeRights(in string userGroup,
    in string serverName);
void addLaunchRights(in string userGroup,
    in string serverName);
void removeLaunchRights(in string userGroup,
    in string serverName);
void addInvokeRightsDir(in string userGroup,
    in string dirName);
```

```
void removeInvokeRightsDir(in string userGroup,
    in string dirName);
void addLaunchRightsDir(in string userGroup,
    in string dirName);
void removeLaunchRightsDir(in string userGroup,
    in string dirName);
};
```

Notes PROGRESS-specific.

IT_daemon::addLaunchRightsDir()

Synopsis void addLaunchRightsDir (in string userGroup,
in string dirName);

Description Adds the user or group in `userGroup` to the list of owners for the directory `dirName`.

Notes PROGRESS-specific.

IT_daemon::addInvokeRights()

Synopsis void addInvokeRights(
in string userGroup,
in string serverName);

Description Adds the user or group in `userGroup` to the *invoke* access control list (ACL) for the server `serverName`. A user who has invoke rights on a server can invoke operations on any object controlled by that server. By default, only the owner of an Implementation Repository entry has invoke rights on the server registered.

Notes PROGRESS-specific.

See Also “IT_daemon::removeInvokeRights()” on page 441
“IT_daemon::addLaunchRights()” on page 428
“IT_daemon::addInvokeRightsDir()” on page 428

IT_daemon::addInvokeRightsDir()

- Synopsis** `void addInvokeRightsDir(
 in string userGroup,
 in string dirName);`
- Description** Adds the user or group in `userGroup` to the *invoke* access control list (ACL) for the directory `dirName`.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::removeInvokeRightsDir()” on page 441
 “IT_daemon::addInvokeRights()” on page 427

IT_daemon::addLaunchRights()

- Synopsis** `void addLaunchRights(
 in string userGroup,
 in string serverName);`
- Description** Adds the user or group in `userGroup` to the *launch* access control list for the server `serverName`. By default, only the owner of an Implementation Repository entry has launch rights on the server registered.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::removeLaunchRights()” on page 441

IT_daemon::addLaunchRightsDir()

- Synopsis** `void addLaunchRightsDir(
 in string userGroup,
 in string dirName);`
- Description** Adds the user or group in `userGroup` to the *launch* access control list for the directory `dirName`.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::addLaunchRights()” on page 428
 “IT_daemon::removeLaunchRightsDir()” on page 442

IT_daemon::addMethod()

Synopsis

```
void addMethod(  
    in string serverName,  
    in string methodName,  
    in string newCommand);
```

Description

Adds an *activation order* to the Implementation Repository entry for the per-method server, `serverName`. This activation order specifies that an invocation of a method whose name matches the method (or method pattern) indicated in `methodName` should cause the server to be launched using the command `newCommand`.

Notes

PROGRESS-specific.

Not supported by `orbixdj`.

See Also

“IT_daemon::removeMethod()” on page 442

IT_daemon::addSharedMarker()

Synopsis

```
void addSharedMarker(  
    in string serverName,  
    in string markerName,  
    in string newCommand);
```

Description

Adds an *activation order* to the Implementation Repository entry for the shared server, `serverName`. This activation order specifies that an invocation for an object whose marker matches the marker (or marker pattern) indicated in `markerName` should cause the server to be launched (if not already running) using the command, `newCommand`.

Notes

PROGRESS-specific.

Not supported by `orbixdj`.

See Also

“IT_daemon::removeSharedMarker()” on page 442

IT_daemon::addUnsharedMarker()

Synopsis

```
void addUnsharedMarker(  
    in string serverName,  
    in string markerName,  
    in string newCommand);
```

Description

Adds an *activation order* to the Implementation Repository entry for the unshared server, `serverName`. This activation order specifies that an invocation for an object whose marker matches the marker (or marker pattern) indicated in `markerName` should cause the server to be launched using the command, `newCommand`.

Notes

PROGRESS-specific.

Not supported by `orbixdj`.

See Also

“`IT_daemon::removeUnsharedMarker()`” on page 443

IT_daemon::changeOwnerServer()

Synopsis

```
void changeOwnerServer(  
    in string new_owner,  
    in string serverName);
```

Description

Changes the ownership of the Implementation Repository entry for the server `serverName`. The *principal* (user) invoking this operation must be the current owner of the Implementation Repository entry.

Notes

PROGRESS-specific.

IT_daemon::deleteDirectory()

- Synopsis** `void deleteDirectory(
 in string dirName,
 in boolean deleteChildren);`
- Description** Removes a registration directory from the Implementation Repository. If `deleteChildren` is `true`, server entries and sub-directories are also deleted.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::newDirectory()” on page 436

IT_daemon::deleteServer()

- Synopsis** `void deleteServer(
 in string serverName);`
- Description** Deletes the entry for the server, `serverName`, from the Implementation Repository.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::newPerMethodServer()” on page 436
 “IT_daemon::newSharedServer()” on page 437
 “IT_daemon::newUnSharedServer()” on page 439

IT_daemon::getServer()

- Synopsis** `void getServer(
 in string serverName,
 out string commsProtocol,
 out string codeProtocol,
 out string activationPolicy,
 out unsigned long mode_flags,
 out string owner,
 out string invokeList,
 out string launchList,
 out stringSeq markers,
 out stringSeq methods,
 out stringSeq commands);`

Description Gets full information about the Implementation Repository entry for `serverName`.
Notes PROGRESS-specific.

IT_daemon::getServer2()

Synopsis

```
public void getServer2(String serverName,  
                      org.omg.CORBA.StringHolder commsProtocol,  
                      org.omg.CORBA.StringHolder codeProtocol,  
                      org.omg.CORBA.StringHolder activationPolicy,  
                      org.omg.CORBA.IntHolder mode_flags,  
                      org.omg.CORBA.StringHolder owner,  
                      org.omg.CORBA.StringHolder invokeList,  
                      org.omg.CORBA.StringHolder launchList,  
                      org.omg.CORBA.IntHolder nservers,  
                      org.omg.CORBA.IntHolder port,  
                      stringSeqHolder markers,  
                      stringSeqHolder methods,  
                      stringSeqHolder commands) ;;
```

Description Gets full information about the Implementation Repository entry for `serverName`. This method was added to the `IT_daemon` interface to allow users to query the daemon for information on flags that were added to the `putitj` command, for example, `putitj -n` or `putitj -port`.

Notes PROGRESS-specific.

IT_daemon::getIIOPDetails

Synopsis

```
public void getIIOPDetails(String serverName,  
                           String markerName,  
                           String methodName,  
                           org.omg.CORBA.StringHolder iiopPort,  
                           org.omg.CORBA.StringHolder activationPolicy);
```

Description This method get information about the server specified by `serverName` from the Implementation Repository. If the server is not currently running then the daemon launches the server. If the `serverName` or the `markerName` are null an `org.omg.CORBA.BAD_PARAM` exception is raised.

This method should only be used to launch server for the IIOP Protocol.

Parameters

<code>serverName</code>	The name of the server.
<code>markerName</code>	The marker name associated with this launch command.
<code>methodName</code>	The method name associated with this launch command.
<code>iiopPort</code>	The returned port number on which the server is listening.
<code>activationPolicy</code>	Further activation mode details: 0 (shared activation mode) 1 (unshared activation mode) 2 (per-method activation mode)

Notes PROGRESS-specific.

See Also “IT_daemon::getImplementationDetails” on page 433

IT_daemon::getImplementationDetails

Synopsis

```
public void getImplementationDetails(  
    String serverName,  
    String markerName,  
    String methodName,  
    org.omg.CORBA.StringHolder codeProtocol,  
    org.omg.CORBA.StringHolder commsProtocol,  
    org.omg.CORBA.StringHolder commsPort,  
    org.omg.CORBA.StringHolder activationPolicy ) ;
```

Description

This method gets information about the server specified by `serverName` from the Implementation Repository. If the server is not currently running, the daemon launches the server. If the `serverName` or the `markerName` are null, an `org.omg.CORBA.BAD_PARAM` exception is raised.

This method should only be used to launch a server for the Orbix protocol.

Parameters

<code>serverName</code>	The name of the server.
<code>markerName</code>	The marker name associated with this launch command.
<code>methodName</code>	The method name associated with this launch command.
<code>codeProtocol</code>	The protocol used for encoding object sent across the network (for example, xdr encoding)
<code>commsProtocol</code>	The returned communications protocol used (for example, TCP).
<code>commsPort</code>	The returned port number the server is listening on.
<code>activationPolicy</code>	Further activation mode details: 0 (shared activation mode) 1 (unshared activation mode) 2 (per-method activation mode).

Notes PROGRESS-specific.

See Also “IT_daemon::getIOPDetails” on page 432

IT_daemon::killServer()

Synopsis

```
void killServer(  
    in string name,  
    in string marker);
```

Description

Kills a server process. Where there is more than one server process, the marker parameter is used to select between different processes. The marker parameter is required when killing a process in the unshared mode.

Notes PROGRESS-specific.

IT_daemon::LaunchStatus

Synopsis

```
enum LaunchStatus (  
    inActive,  
    manuallaunch,
```

```
        automaticLaunch
    };
```

Description Possible values for the `launchStatus` of a server.

Notes PROGRESS-specific.

IT_daemon::listActiveServers()

Synopsis

```
typedef sequence<serverDetails> serverDetailsSeq;
void listActiveServers(
    out serverDetailsSeq servers);
```

Description Returns a list of active server processes known to the Orbix daemon and includes information about each process.

Notes PROGRESS-specific.

See Also “IT_daemon::serverDetails” on page 443

IT_daemon::listHostsInServer()

Synopsis

```
boolean listHostsInServer(
    in string server,
    out stringSeq hostList);
```

Description Returns a list of the hosts on which the server, `server`, runs as listed in the *server location* configuration file.

Notes PROGRESS-specific.

IT_daemon::listServers()

Synopsis

```
void listServers(
    in string subdir,
    out stringSeq servers);
```

Description Lists all servers in the Implementation Repository directory `subdir`.

Notes PROGRESS-specific.

IT_daemon::lookUp()

Synopsis

```
boolean lookUp(  
    in string service,  
    out stringSeq hostList,  
    in octet hops,  
    in string tag)
```

Description

Invokes the corresponding `lookUp()` function on the locator. This is normally the default locator—unless an alternative locator has been installed.

Notes

PROGRESS-specific.

See Also

IT_daemon::newDirectory()

Synopsis

```
void newDirectory(in string dirName);
```

Description

Creates a new Implementation Repository directory. The name is specified in `dirName` and may be a new directory or a subdirectory of an existing directory. Use the `'/'` character to indicate a subdirectory—for example, the name `“server/banks”` is a valid directory name.

Notes

PROGRESS-specific.

See Also

`“IT_daemon::deleteDirectory()”` on page 431

IT_daemon::newPerMethodServer()

Synopsis

```
void newPerMethodServer(  
    in string serverName,  
    in stringSeq methods,  
    in stringSeq launchCommands);
```

Description

Creates a new entry in the Implementation Repository for the per-method server `serverName`. The new entry has an activation order for each element of the sequences in `methods` and `launchCommands`.

Parameters

<code>serverName</code>	The name of the server.
-------------------------	-------------------------

<code>methods</code>	A sequence of methods. Each element in the sequence has a corresponding element in the sequence <code>launchCommands</code> .
<code>launchCommands</code>	A sequence of launch commands (the full path name of an executable file). Each element in the sequence has a corresponding element in the sequence <code>methods</code> .

Notes PROGRESS-specific.
Not supported by `orbixdj`.

IT_daemon::newSharedServer()

Synopsis

```
void newSharedServer(  
    in string serverName,  
    in stringSeq markers,  
    in stringSeq launchCommands,  
    in unsigned long mode_flags);
```

Description Creates a new Implementation Repository entry for the shared server `serverName`. The new entry has an activation order for each element of the sequences in `markers` and `launchCommands`.

Parameters

<code>serverName</code>	The name of the server.
<code>markers</code>	A sequence of markers. Each element in the sequence has a corresponding element in the sequence <code>launchCommands</code> .
<code>launchCommands</code>	A sequence of launch commands (the full path name of an executable file and possibly command line switches). Each element in the sequence has a corresponding element in the sequence <code>markers</code> .
<code>mode_flags</code>	Further activation mode details: <ul style="list-style-type: none">0 Multiple-client activation mode.1 Per-client activation mode.2 Per-client-process activation mode.

Notes PROGRESS-specific.

IT_daemon::newSharedServer2()

Synopsis

```
void newSharedServer2 (String serverName,  
                       String[] marker,  
                       String[] launchCommand,  
                       int mode_flags,  
                       int nservers,  
                       int wellKnownPort);
```

Description Creates a new Implementation Repository entry for the shared server `serverName`. The new entry has an activation order for each element of the sequences in `markers` and `launchCommands`. This method allows servers to be registered with extra information equivalent to the `putitj -port` and `putitj -n` commands.

Parameters

<code>serverName</code>	The name of the server.
<code>markers</code>	A sequence of markers. Each element in the sequence has a corresponding element in the sequence <code>launchCommands</code> .
<code>launchCommands</code>	A sequence of launch commands (the full path name of an executable file and possibly command line switches). Each element in the sequence has a corresponding element in the sequence <code>markers</code> .
<code>mode_flags</code>	Further activation mode details: <ul style="list-style-type: none">0 Multiple-client activation mode.1 Per-client activation mode.2 Per-client-process activation mode.
<code>nservers</code>	Specifies the numbers of servers to use for round-robin load balancing on this host; equivalent to <code>putitj -n</code> command.
<code>wellKnownPort</code>	Specifies the well-known port number that this method should use in its IORs when exporting object references.

Notes PROGRESS-specific.

IT_daemon::newUnSharedServer()

Synopsis

```
void newUnSharedServer(  
    in string serverName,  
    in stringSeq markers,  
    in stringSeq launchCommands,  
    in unsigned long mode_flags);
```

Description

Creates a new Implementation Repository entry for the unshared server `serverName`. The new entry has an activation order for each element of the sequences in `markers` and `launchCommands`.

Parameters

<code>serverName</code>	The name of the server.
<code>markers</code>	A sequence of markers. Each element in the sequence has a corresponding element in the sequence <code>launchCommands</code> .
<code>launchCommands</code>	A sequence of launch commands (the full path name of an executable file and possibly command line switches). Each element in the sequence has a corresponding element in the sequence <code>markers</code> .
<code>mode_flags</code>	Further activation mode details: <ul style="list-style-type: none">0 Multiple-client activation mode.1 Per-client activation mode.2 Per-client-process activation mode.

Notes

PROGRESS-specific.
Not supported by `orbixdj`.

IT_daemon::registerPersistentServer()

Synopsis

```
public void registerPersistentServer(  
    String serverName,  
    int serverPid,  
    org.omg.CORBA.StringHolder codeProtocol,  
    org.omg.CORBA.StringHolder commsProtocol,  
    org.omg.CORBA.StringHolder commsPort);
```

Description This method contacts the daemon with the servers' `serverName` and `serverPid`. The daemon returns all the information the server needs to know in order to listen for incoming events—which protocols to use and what port to listen on.

Parameters

<code>serverName</code>	The name of this server.
<code>serverPid</code>	A process ID to be associated with this server .
<code>codeProtocol</code>	The returned coding protocol that this server should use.
<code>commsProtocol</code>	The communications protocol that this server should use.
<code>commsPort</code>	The port that this server should listen on.

Notes PROGRESS-specific.

IT_daemon::removeDirRights()

Synopsis `removeDirRights(in string userGroup, in string dirName);`

Description Removes the user or group in `userGroup` to the list of owners for the directory `dirName`.

Notes PROGRESS-specific.

IT_daemon::removeInvokeRights()

- Synopsis** `void removeInvokeRights (
 in string userGroup,
 in string serverName);`
- Description** Removes the user or group in `userGroup` from the `invoke` access control list for server `serverName`.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::addInvokeRights()” on page 427

IT_daemon::removeInvokeRightsDir()

- Synopsis** `void removeInvokeRightsDir (
 in string userGroup,
 in string dirName);`
- Description** Removes the user or group in `userGroup` from the *invoke* access control list for directory `dirName`.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::addInvokeRightsDir()” on page 428

IT_daemon::removeLaunchRights()

- Synopsis** `void removeLaunchRights (
 in string userGroup,
 in string serverName);`
- Description** Removes the user or group in `userGroup` from the *launch* access control list for server `serverName`.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::addLaunchRights()” on page 428

IT_daemon::removeLaunchRightsDir()

- Synopsis** `void removeLaunchRightsDir(
 in string userGroup,
 in string dirName);`
- Description** Removes the user or group in `userGroup` from the *launch* access control list for the directory `dirName`.
- Notes** PROGRESS-specific.
- See Also** “IT_daemon::addLaunchRightsDir()” on page 428

IT_daemon::removeMethod()

- Synopsis** `void removeMethod(
 in string serverName,
 in string methodName);`
- Description** Removes the activation order for the method (or method pattern) in `methodName` from the Implementation Repository entry for the per-method server, `serverName`.
- Notes** PROGRESS-specific.
Not supported by `orbixdj`.
- See Also** “IT_daemon::addMethod()” on page 429

IT_daemon::removeSharedMarker()

- Synopsis** `void removeSharedMarker(
 in string serverName,
 in string markerName);`
- Description** Removes the activation order for the marker (or marker pattern) in `markerName` from the Implementation Repository entry for the shared server, `serverName`.
- Notes** PROGRESS-specific.
Not supported by `orbixdj`.
- See Also** “IT_daemon::addSharedMarker()” on page 429

IT_daemon::removeUnsharedMarker()

Synopsis

```
void removeUnsharedMarker(  
    in string serverName,  
    in string markerName);
```

Description

Removes the activation order for the marker (or marker pattern) in `markerName` from the Implementation Repository entry for the unshared server, `serverName`.

Notes

PROGRESS-specific.

Not supported by `orbixdj`.

See Also

“`IT_daemon::addUnsharedMarker()`” on page 430

IT_daemon::serverDetails

Synopsis

```
struct serverDetails {  
    string server;  
    string marker;  
    string principal;  
    string code;  
    string comms;  
    string port;  
    unsigned long OSspecific;  
    LaunchStatus status;  
};
```

Description

The members of the `struct` are as follows:

<code>server</code>	The name of the server.
<code>marker</code>	The marker (if any).
<code>principal</code>	The name of the principal (end-user) for whom the server was launched. This is null if the server is not a per-client server.
<code>code</code>	The encoding protocol (for example, <code>xdr</code>).
<code>comms</code>	The transport protocol (for example, <code>TCP/IP</code>).
<code>port</code>	The port used by the communications system.
<code>OSspecific</code>	On UNIX, this is the operating system process identifier of the server process.

status One of the enumerated values, `inactive`, `manualLaunch` or `automaticLaunch`.

Notes PROGRESS-specific.

See Also “IT_daemon::LaunchStatus” on page 434

IT_daemon::serverExists()


Synopsis `boolean serverExists(in string serverName);`

Description Determines whether there is an entry for the server `serverName` in the Implementation Repository.

Notes PROGRESS-specific.

Part VII

Appendices



Appendix A

IDL Reference

This appendix presents reference material on the Interface Definition Language.

IDL Grammar

This section presents the grammar of IDL.

The notation is as follows:

Note that the two characters >> are always interpreted as a right shift operator.

This means that a declaration of the form:

```
// IDL
typedef sequence<sequence<long>>  sslong;
```

cannot be written without a white space between the two > characters:

```
// IDL
// Illegal
typedef sequence<sequence<long>>  sslong;
```

IDL Grammar: EBNF

```
(1) <specification>      ::= <definition>+
(2) <definition>         ::= <type_dcl> ";"
                           | <const_dcl> ";"
                           | <except_dcl> ";"
                           | <interface> ";"
                           | <module> ";"
(3) <module>             ::= "module" <identifier>
                           "{" <definition>+ "}"
```

```
(4) <interface> ::= <interface_dcl>
      | <forward_dcl>
(5) <interface_dcl> ::= <interface_header>
      {" <interface-body> "}
(6) <forward_dcl> ::= "interface" <identifier>
(7) <interface_header> ::= "interface" <identifier>
      [<inheritance_spec>]
(8) <interface_body> ::= <export>*
(9) <export> ::= <type_dcl> ";"
      | <const_dcl> ";"
      | <except_dcl> ";"
      | <attr_dcl> ";"
      | <op_dcl> ";"
(10) <inheritance_spec> ::= ":" <scoped_name> {"," <scoped_name>}*
(11) <scoped_name> ::= <identifier>
      | "::" <identifier>
      | <scoped_name> "::" <identifier>
(12) <const_dcl> ::= "const" <const_type> <identifier>
      "="<const_exp>
(13) <const_type> ::= <integer_type>
      | <char_type>
      | <boolean_type>
      | <floating_pt_type>
      | <string_type>
      | <scoped_name>
(14) <const_exp> ::= <or_expr>
(15) <or_expr> ::= <xor_expr>
      | <or_expr> "|" <xor_expr>
(16) <xor_expr> ::= <and_expr>
      | <xor_expr> "^" <and_expr>
(17) <and_expr> ::= <shift_expr>
      | <and_expr> "&" <shift_expr>
(18) <shift_expr> ::= <add_expr>
      | <shift_expr> ">>"<add_expr>
```

(19) <add_expr>	<shift_expr> "<<"<add_expr> ::= <mult_expr> <add_expr> "+" <mult_expr> <add_expr> "-" <mult_expr>
(20) <mult_expr>	::= <unary_expr> <mult_expr> "*" <unary_expr> <mult_expr> "/" <unary_expr> <mult_expr> "%" <unary_expr>
(21) <unary_expr>	::= <unary_operator> <primary_expr> <primary_expr>
(22) <unary_operator>	::= "-" "+" "~"
(23) <primary_expr>	::= <scoped_name> <literal> "(" <const_exp> ")"
(24) <literal>	::= <integer_literal> <string_literal> <character_literal> <floating_pt_literal> <boolean_literal>
(25) <boolean_literal>	::= "TRUE" "FALSE"
(26) <positive_int_const>	::= <const_exp>
(27) <type_dcl>	::= "typedef" <type_declarator> <struct_type> <union_type> <enum_type>
(28) <type_declarator>	::= <type_spec> <declarators>
(29) <type_spec>	::= <simple_type_spec> <constr_type_spec>
(30) <simple_type_spec>	::= <base_type_spec> <template_type_spec> <scoped_name>

```
(31) <base_type_spec> ::= <floating_pt_type>
| <integer_type>
| <char_type>
| <boolean_type>
| <octet_type>
| <any_type>

(32) <template_type_spec> ::= <sequence_type>
| <string_type>

(33) <constr_type_spec> ::= <struct_type>
| <union_type>
| <enum_type>

(34) <declarators> ::= <declarator> { "," <declarator> }*
(35) <declarator> ::= <simple_declarator>
| <complex_declarator>

(36) <simple_declarator> ::= <identifier>
(37) <complex_declarator> ::= <array_declarator>
(38) <floating_pt_type> ::= "float"
| "double"

(39) <integer_type> ::= <signed_int>
| <unsigned_int>

(40) <signed_int> ::= <signed_long_int>
| <signed_short_int>

(41) <signed_long_int> ::= "long"
(42) <signed_short_int> ::= "short"
(43) <unsigned_int> ::= <unsigned_long_int>
| <unsigned_short_int>

(44) <unsigned_long_int> ::= "unsigned" "long"
(45) <unsigned_short_int> ::= "unsigned" "short"
(46) <char_type> ::= "char"
(47) <boolean_type> ::= "boolean"
(48) <octet_type> ::= "octet"
(49) <any_type> ::= "any"
(50) <struct_type> ::= "struct" <identifier>
| "{" <member_list> "}"
```

(51) <member_list>	::= <member>+
(52) <member>	::= <type_spec> <declarators> ";"
(53) <union_type>	::= "union" <identifier> "switch" "(" <switch_type_spec> ")" "{" <switch_body> "}"
(54) <switch_type_spec>	::= <integer_type> <char_type> <boolean_type> <enum_type> <scoped_name>
(55) <switch_body>	::= <case>+
(56) <case>	::= <case_label>+ <element_spec> ";"
(57) <case_label>	::= "case" <const_exp> ":" "default" ":"
(58) <element_spec>	::= <type_spec> <declarator>
(59) <enum_type>	::= "enum" <identifier> "{" <enumerator> { "," <enumerator> }* "}"
(60) <enumerator>	::= <identifier>
(61) <sequence_type>	::= "sequence" "<" <simple_type_spec> "," <positive_int_const> ">" "sequence" "<" <simple_type_spec> ">"
(62) <string_type>	::= "string" "<" <positive_int_const> ">" "string"
(63) <array_declarator>	::= <identifier> <fixed_array_size>+
(64) <fixed_array_size>	::= "[" <positive_int_const> "]"
(65) <attr_dcl>	::= ["readonly"] "attribute" <param_type_spec> <simple_declarator> {"","<simple_declarator>}*
(66) <except_dcl>	::= "exception" <identifier> {" <member>* "}"
(67) <op_dcl>	::= [<op_attribute>] <op_type_spec> <identifier> <parameter_dcls>

```

                                [<raises_expr>] [<context_expr>]
(68) <op_attribute>           := "oneway"
(69) <op_type_spec>          ::= <param_type_spec>
                                | "void"
(70) <parameter_dcls>        ::= "(" <param_dcl> {"," <param_dcl>}* ")"
                                | "(" " ")"
(71) <param_dcl>             ::= <param_attribute> <param_type_spec>
                                <simple_declarator>
(72) <param_attribute>       ::= "in"
                                | "out"
                                | "inout"
(73) <raises_expr>           ::= "raises" "(" <scoped_name>
                                { "," <scoped_name> }* ")"
(74) <context_expr>          ::= "context" "(" <string_literal>
                                { "," <string_literal>}* ")"
(75) <param_type_spec>       ::= <base_type_spec> <string_type>
                                <scoped_name>
```

Keywords

The following are keywords in IDL.

any	default	interface	readonly	unsigned
attribute	double	long	sequence	union
boolean	enum	module	short	void
case	exception	octet	string	FALSE
char	float	oneway	struct	Object
const	in	out	switch	TRUE
context	inout	raises	typedef	

You must write keywords exactly as shown. For example, writing `Boolean` rather than `boolean` gives a compiler error.

Appendix B

Naming Service: IDL Definitions

This appendix lists the IDL definitions in the Naming Service CosNaming module.

The CosNaming Module

```
// IDL
module CosNaming {

    typedef string Istring;
    struct NameComponent {
        Istring id;
        Istring kind;
    };
    typedef sequence<NameComponent> Name;

    enum BindingType {nobject, ncontext};
    struct Binding {
        Name          binding_name;
        BindingType   binding_type;
    };
    typedef sequence <Binding> BindingList;

    interface BindingIterator;

    interface NamingContext {
        enum NotFoundReason {missing_node,
                             not_context, not_object};
        exception NotFound {
            NotFoundReason why;
            Name           rest_of_name;
        };
        exception CannotProceed {
```

```
        NamingContext  cxt;
        Name           rest_of_name;
    };
    exception InvalidName {};
    exception AlreadyBound {};
    exception NotEmpty {};

    void bind(in Name n, in Object obj)
        raises (NotFound, CannotProceed,
              InvalidName, AlreadyBound);
    void rebind(in Name n, in Object obj)
        raises (NotFound, CannotProceed,
              InvalidName);
    void bind_context(in Name n,
                     in NamingContext nc)
        raises (NotFound, CannotProceed,
              InvalidName, AlreadyBound);
    void rebind_context(in Name n,
                       in NamingContext nc)
        raises (NotFound, CannotProceed,
              InvalidName);
    Object resolve(in Name n)
        raises (NotFound, CannotProceed,
              InvalidName);
    void unbind(in Name n)
        raises (NotFound, CannotProceed,
              InvalidName);
    NamingContext new_context();
    NamingContext bind_new_context(in Name n)
        raises (NotFound, CannotProceed,
              InvalidName, AlreadyBound);
    void destroy() raises (NotEmpty);
    void list(in unsigned long how_many,
             out BindingList bl,
             out BindingIterator bi);

    interface BindingIterator {
        boolean next_one(out Binding b);
        boolean next_n(in unsigned long how_many,
                      out BindingList bl);
        void destroy();
    };
};
```

Appendix C

System Exceptions

The following tables shows the system exceptions defined by CORBA, and the system exceptions that are specific to Orbix Java.

System Exceptions Defined by CORBA

Exception	Description
BAD_CONTEXT	Error processing context object.
BAD_INV_ORDER	Routine invocations out of order.
BAD_OPERATION	Invalid operation.
BAD_PARAM	An invalid parameter was passed.
Bounds	Bounds exception.
BAD_TYPECODE	Bad TypeCode .
COMM_FAILURE	Communication failure.
DATA_CONVERSION	Data conversion error.
IMP_LIMIT	Violated implementation limit.
INITIALIZE	ORB initialization failure.
INTERNAL	ORB internal error.

Table C.1: *CORBA System Exceptions*

Exception	Description
INTF_REPOS	Error accessing interface repository.
INV_IDENT	Invalid identifier syntax.
INV_FLAG	Invalid flag was specified.
INV_OBJREF	Invalid object reference.
MARSHAL	Request marshalling error.
NO_MEMORY	Dynamic memory allocation failure.
NO_PERMISSION	No permission for attempted operation.
NO_IMPLEMENT	Operation implementation unavailable.
NO_RESOURCES	Insufficient resources for request.
NO_RESPONSE	Response to request not yet available.
OBJ_ADAPTOR	Failure detected by object adaptor.
PERSIST_STORE	Persistent storage failure.
TRANSACTION	Transaction exception.
TRANSIENT	Transient failure—reissue request.
UNKNOWN	The unknown exception.

Table C.1: *CORBA System Exceptions*

System Exceptions Specific to Orbix Java

Orbix Java Exception	Description
<code>FILTER_SUPPRESS</code>	Suppress exception raised in per-object pre-filter.

Table C.2: *Orbix Java-Specific System Exceptions*

Index

A

- absolute_name() 371
- access_name() 246
- active_transactions() 400
- add() 140, 148, 161
- add_arg() 253
- add_in_arg() 254
- add_inout_arg() 254
- addInvokeRights() 427
- addInvokeRightsDir() 428
- add_item() 140, 148, 162
- addLaunchRights() 428
- addLaunchRightsDir() 427, 428
- addMethod() 429
- add_named_in_arg() 254
- add_named_inout_arg() 255
- add_named_out_arg() 255
- add_out_arg() 256
- addSharedMarker() 429
- addUnsharedMarker() 430
- add_value() 162
- any 81
- Any class 81
- Any() 84, 86, 87
 - _OrbixWeb conversion 350
- anyClientsConnected() 103
- ARG_IN class 29
- ARG_INOUT class 30
- ARG_OUT class 31
- arguments() 256
- AuthenticationFilter class 297
- AuthenticationFilter() 298

B

- BadKind() 74
- base_interfaces 393
- baseInterfacesOf() 193
- Basic Object Adapter 98
- BOA interface 98
- bound 411, 415
- Bounds class 32, 75
- Bounds() 32, 75

C

- changeImplementation() 103
- changeOwnerServer() 430
- clear() 146
- clone() 88, 155, 161
- CloseCallback() 314
- closeConnection() 194
- collocated() 194, 195
- commit() 400
- compare() 288
- CompletionStatus class 33
- Config class 299
- Config() 299
- config() 195
- connect() 104
- containing_repository() 371
- containsType() 88
- contents() 377
- content_type() 293
- Context class 35, 130
- Context()
 - _OrbixWeb conversion 351
- Context() constructor 132, 133
- ContextIterator class 142
- ContextIterator() 142, 143
- ContextList class 37, 139
- ContextList()
 - _OrbixWeb conversion 351
- context_name() 134
- contexts 403
- contexts() 256, 257
- continueThreadDispatch() 106
- copy() 89
- _CORBA class 343
- CORBA::AliasDef::
 - describe() 361
 - original_type_def 362
- CORBA::ArrayDef::
 - element_type 363
 - element_type_def 364
 - length 364
- CORBA::AttributeDef::
 - describe() 365
 - mode 366

- type 366
- type_def 366
- CORBA::ConstantDef::
 - describe() 367
 - type 368
 - type_def 368
 - value 369
- CORBA::Contained::
 - absolute_name() 371
 - containing_repository() 371
 - defined_in 371
 - describe() 372
 - id 373
 - move() 373
 - name() 374
 - version 374
- CORBA::Container::
 - contents() 377
 - create_alias() 378
 - create_constant() 378
 - create_enum() 379
 - create_exception() 380
 - create_interface() 380
 - create_module() 381
 - create_struct() 382
 - create_union() 382
 - describe_contents() 383
 - lookup() 384
 - lookup_name() 385
- CORBA::DefinitionKind 359
- CORBA::EnumDef::
 - describe() 386
 - members 387
- CORBA::ExceptionDef::
 - describe() 388
 - members 389
 - type 389
- CORBA::Identifier 359
- CORBA::IDLType::
 - type 391
- CORBA::InterfaceDef::
 - base_interfaces 393
 - create_attribute() 393
 - create_operation() 394
 - describe() 395
 - describe_interface() 396
 - is_a() 396
- CORBA::IObject::
 - def_kind 397
 - destroy() 397
- CORBA::IT_Repository::
 - active_transactions() 400
 - commit() 400
 - start() 399
- CORBA::IT_Repository::rollback() 400
- CORBA::ModuleDef::
 - describe() 401
- CORBA::OperationDef::
 - contexts 403
 - describe() 403
 - exceptions 403
 - mode 404
 - params 404
 - result 405
 - result_def 405
- CORBA::PrimitiveDef::
 - kind 406
- CORBA::Repository::
 - create_array() 408
 - create_sequence() 408
 - create_string() 409
 - describe_contents() 409
 - get_primitive() 409
 - lookup_id() 410
- CORBA::RepositoryId 360
- CORBA::ScopedName 360
- CORBA::SequenceDef::
 - bound 411
 - element_type 411
 - element_type_def 412
 - type 412
- CORBA::StringDef::
 - bound 415
- CORBA::StructDef::
 - members 414
- CORBA::StructDef::describe() 413
- CORBA::TypedefDef::
 - describe() 416
- CORBA::UnionDef::
 - describe() 419
 - discriminator_type() 419
 - discriminator_type_def() 420
 - members 420
- count() 140, 148, 163
- create() 107
- create_alias() 378
- create_alias_tc() 196, 276
- create_any() 198, 271
- create_array() 408
- create_array_tc() 196, 276

create_attribute() 393
 create_child() 134
 create_constant() 378
 create_context_list() 199, 271
 create_enum() 379
 create_enum_tc() 196, 276
 create_environment() 199, 272
 create_exception() 380
 create_exception_list() 200, 272
 create_exception_tc() 196, 276
 create_input_stream() 90, 257
 create_interface() 380
 create_interface_tc() 196, 276
 create_list() 200, 273
 create_module() 381
 create_named_value() 201, 274
 create_operation() 394
 create_operation_list() 202
 create_output_stream() 89, 204, 257, 275
 create_recursive_sequence_tc() 196, 276
 _create_request() 45, 171
 create_sequence() 408
 create_sequence_tc() 196, 276
 create_string() 409
 create_string_tc() 196, 276
 create_struct() 382
 create_struct_tc() 196, 276
 create_tc() 196, 276
 create_union() 382
 create_union_tc() 196, 277
 create_wstring_tc() 197, 277
 ctx() 62, 258
 CTX_RESTRICT_SCOPE class 38
 Current class 39
 Current()
 _OrbixWeb conversion 351, 352

D

daemon
 IDL definition 423
 deactivate_impl() 108
 deactivate_obj() 108
 defaultConfigFile() 331
 default_index() 292
 defaultTxTimeout() 205
 defined_in 371
 def_kind 397
 _delete() 303
 deleteDirectory() 431
 deleteServer() 431

delete_values() 135
 _deref() 172
 describe() 361, 365, 367, 372, 386, 388, 395, 401, 403, 413, 416, 419
 describe_contents() 383, 409
 describe_interface() 396
 destroy() 397
 disconnect() 109
 discriminator_type() 291, 419
 discriminator_type_def() 420
 dispose() 110
 DynamicImplementation class 40

E

element_type 363, 411
 element_type_def 364, 412
 enableLoaders() 110
 enableProxyServer() 111
 env() 258, 259
 Environment class 41, 145
 equal() 90, 287
 equals() 155, 160, 287
 except() 65
 exception() 145, 146
 ExceptionList class 42, 147
 ExceptionList() 148
 Exceptions
 system exceptions 455
 exceptions 403
 exceptions() 259
 explicit_call 344
 extract() 91
 extract_any() 91
 extract_boolean() 91
 extract_char() 91
 extract_double() 91
 extract_float() 91
 extract_long() 91
 extract_longlong() 91
 extract_Object() 91
 extract_octet() 91
 extract_Principal() 91
 extract_short() 91
 extract_Streamable() 91
 extract_string() 91
 extract_TypeCode() 91
 extract_ulong() 91
 extract_wchar() 91
 extract_wstring() 91

F

Filter class 301
Filter() 302
finalize() 111, 205
flags() 157
from_int() 34, 69
fromString() 92
fully-functional ORB 268

G

getClientConnection() 260
getConfigFile() 331
getConfigItem() 206, 300, 332
getConfiguration() 207, 332
get_count() 135
get_count_all() 135
get_current() 112
getDaemonConnections() 207
get_default_context() 208, 275
_getException() 260
getHostPort() 209
get_id() 112
_get_implementation() 173
getImplementationDetails() 432, 433
_get_interface_def() 173
getMessageLength() 260
get_my_principal() 209
getMyReqTransformer() 210
get_next_response() 210
get_object() 240
get_primitive() 409
get_principal() 113, 211, 240
get_principal_string() 113, 212, 241
get_protocol() 241
get_request() 242
getResponse() 261
getServer() 431
get_server() 242
getServer2() 432
get_socket() 243
getTransformer() 211
get_values() 136

H

_hash() 174
_hasValidOpenChannel() 174
hasValidOpenChannel() 213
_host() 175

I

id 373
_id() 175
id() 289
IDL
 definitions for Implementation Repository 423
 grammar 447
 keywords 452
IE.Iona.OrbixWeb
 _CORBA 343
 explicit_call 344
 IT_INFINITE_TIMEOUT 345
 IT_INTEROPERABLE_OR_KIND 345
 IT_ORBIX_OR_KIND 345
 _MAX_LOCATOR_HOPS 346
 objectDeletion 346, 347
 _ORBIX_VERSION 345
 processTermination 348
CORBA
 Any 81, 93
 Any() 84, 86
 clone() 88
 containsType() 88
 copy() 89
 create_input_stream() 90
 create_output_stream() 89
 equal() 90
 extract() 91
 extract_any() 91
 extract_boolean() 91
 extract_char() 91
 extract_double() 91
 extract_float() 91
 extract_long() 91
 extract_longlong() 91
 extract_Object() 91
 extract_octet() 91
 extract_Principal() 91
 extract_short() 91
 extract_Streamable() 91
 extract_string() 91
 extract_TypeCode() 91
 extract_ulong() 91
 extract_ulonglong() 91
 extract_wchar() 91
 extract_wstring() 91
 fromString() 92

-
- insert() 93, 94
 - insert_any() 93
 - insert_boolean() 93
 - insert_char() 93
 - insert_double() 93
 - insert_long() 93
 - insert_longlong() 93
 - insert_Object() 94
 - insert_octet() 93
 - insert_Principal() 94
 - insert_short() 93
 - insert_Streamable() 94
 - insert_string() 93
 - insert_ulong() 93
 - insert_ulonglong() 93
 - insert_ushort() 93
 - insert_wchar() 94
 - insert_wstring() 94
 - read_value() 95
 - reset() 96
 - toString() 96
 - type() 97
 - write_value() 97
 - Any() 86, 87
 - BOA 98
 - anyClientsConnected () 103
 - change_implementation() 103
 - connect() 104
 - continueThreadDispatch() 106
 - create() 107
 - deactivate_impl() 108
 - deactivate_obj() 108
 - disconnect() 109
 - dispose() 110
 - enableLoaders() 110
 - enableProxyServer() 111
 - finalize() 111
 - get_current() 112
 - get_id() 112
 - get_principal() 113
 - get_principal_string() 113
 - impl_is_ready() 114
 - isEventPending() 117
 - myActivationMode() 117
 - myHost() 118
 - myHostIP() 119
 - myImplementationName() 119
 - myMarkerName() 120
 - myMarkerPattern() 120
 - myMethodName() 120
 - numClientsConnected() 121
 - obj_is_ready() 121
 - processEvents() 122
 - processNextEvent() 125
 - setNoHangup() 127
 - setProxyServer() 128
 - setServerName() 128
 - shutdown() 129, 206
 - toString() 129
 - Context 130
 - Context() 132, 133
 - context_name() 134
 - create_child() 134
 - delete_values() 135
 - get_count() 135
 - get_count_all() 135
 - get_values() 136
 - IT_create() 137
 - _nil() 134
 - parent() 137
 - set_one_value() 137
 - set_values() 138
 - ContextIterator 142
 - ContextIterator() 142, 143
 - next() 143
 - setList() 143
 - ContextList 139
 - add() 140
 - ContextList() 140
 - count() 140
 - item() 141
 - remove() 141
 - Environment 145
 - clear() 146
 - exception() 145, 146
 - ExceptionList 147
 - add() 148
 - count() 148
 - ExceptionList() 148
 - item() 149
 - remove() 149
 - InitService 150

- initialise() 151
- InitService() 150
- NamedValue 152
 - clone() 155
 - equals() 155
 - flags() 157
 - name() 156
 - NamedValue() 153, 154
 - _nil() 157
 - toString() 156
 - value() 156
- NVList 158
 - add() 161
 - add_item() 140, 148, 162
 - add_value() 162
 - clone() 161
 - count() 163
 - equals() 160
 - item() 163
 - _nil() 164
 - NVList() 159, 160
 - remove() 164
- NVList() 140, 148, 159
- NVListIterator 165
 - next() 166
 - NVListIterator() 165, 166
- ObjectRef 168
 - _create_request() 170, 171
 - _deref() 172
 - _get_implementation() 173
 - _get_interface_def() 173
 - _hash() 174
 - _hasValidOpenChannel() 174
 - _host() 175
 - _id() 175
 - _implementation() 175
 - _interfaceHost() 176
 - _interfaceImplementation() 176
 - _interfaceMarker() 176
 - _is_a() 176
 - _is_equivalent() 177
 - _isRemote() 178
 - _loader() 179
 - _marker() 178, 179
 - _name() 180
 - _non_existent() 180
 - _object_to_string() 181, 182
 - _port() 180
 - _request() 180
 - _save() 182
- ORB 184, 196, 198
 - baseInterfacesOf() 193
 - closeConnection() 194
 - collocated() 194, 195
 - config() 195
 - create_alias_tc() 196
 - create_array_tc() 196
 - create_context_list() 199
 - create_enum_tc() 196
 - create_environment() 199
 - create_exception_list() 200
 - create_exception_tc() 196
 - create_interface_tc() 196
 - create_list() 200
 - create_named_value() 201
 - create_operation_list() 202
 - create_output_stream() 204
 - create_recursive_sequence_tc() 196
 - create_sequence_tc() 196
 - create_string_tc() 196
 - create_struct_tc() 196
 - create_tc() 196
 - create_wstring_tc() 197
 - defaultTxTimeout() 205
 - finalize() 205
 - getConfigItem() 206
 - getConfiguration() 207
 - getDaemonConnections() 207
 - get_default_context() 208
 - getHostPort() 209
 - get_my_principal() 209
 - getMyReqTransformer() 210
 - get_next_response() 210
 - get_principal() 211
 - get_principal_string() 212
 - getTransformer() 211
 - hasValidOpenChannel() 213
 - init() 213
 - isBaseInterfaceOf() 217
 - list_initial_services() 217
 - locator() 218

-
- makeIOR() 218
 - maxConnectRetries() 220
 - myHost() 221
 - _nil() 221
 - noReconnectOnFailure() 221
 - object_to_string() 222
 - pingDuringBind() 223
 - poll_next_response() 224
 - registerIOCallback() 225
 - resizeConnectionTable() 224
 - resolve_initial_references() 226
 - send_multiple_requests_deferred() 227
 - send_multiple_requests_oneway() 228
 - setConfigItem() 228
 - setConfiguration() 229
 - setDiagnostics() 229
 - setHostPort() 230
 - setMyReqTransformer() 231
 - set_parameters() 231
 - set_principal() 232
 - setReqTransformer() 232
 - string_to_object() 234
 - toString() 235
 - unregisterIOCallback() 236
 - OrbCurrent 237
 - get_object() 240
 - get_principal() 240
 - get_principal_string() 241
 - get_protocol() 241
 - get_request() 242
 - get_server() 242
 - get_socket() 243
 - Principal 244
 - access_name 246
 - name() 246
 - Principal() 245
 - toString() 247
 - Request 98, 248
 - add_arg() 253
 - add_in_arg () 254
 - add_inout_arg() 254
 - add_named_in_arg () 254
 - add_named_inout_arg () 255
 - add_named_out_arg () 255
 - add_out_arg () 256
 - arguments() 256
 - contexts() 256, 257
 - create_input_stream() 257
 - create_output_stream() 257
 - ctx() 258
 - env() 258, 259
 - exceptions() 259
 - getClientConnection() 260
 - _getException() 260
 - getMessageLength() 260
 - getResponse() 261
 - invoke() 261
 - isDynamic() 262
 - isException() 262
 - _nil() 262
 - operation() 263
 - poll_response() 263
 - Request() 252, 253
 - reset() 263
 - result() 264
 - return_value() 264
 - send_deferred() 265
 - send_oneway() 265
 - setOperation() 266
 - set_return_type() 266
 - setTarget() 267
 - target() 267
 - singletonORB 268
 - create_alias_tc() 276
 - create_any() 271
 - create_array_tc() 276
 - create_context_list() 271
 - create_enum_tc() 276
 - create_environment() 272
 - create_exception_list() 272
 - create_exception_tc() 276
 - create_interface_tc() 276
 - create_list() 273
 - create_named_value() 274
 - create_output_stream() 275
 - create_recursive_sequence_tc() 276
 - create_sequence_tc() 276
 - create_string_tc() 276
 - create_struct_tc() 276

- create_tc() 276
- create_union_tc() 277
- create_wstring_tc() 277
- get_default_context() 275
- TypeCode 279
 - compare() 288
 - content_type() 293
 - default_index() 292
 - discriminator_type() 291
 - equal() 287
 - equals() 287
 - id() 289
 - kind() 286
 - length() 292
 - member_count() 289
 - member_label() 291
 - member_name() 290
 - member_type() 290
 - name() 289
 - orbixTypeCode() 293
 - toString() 294
 - TypeCode() 285, 286
- Features
 - AuthenticationFilter 297
 - AuthenticationFilter() 298
 - Config 299
 - Config() 299
 - getConfigItem() 300
 - setConfigItem() 300
 - Filter 301
 - _delete() 303
 - Filter() 302
 - inReplyFailure() 304
 - inReplyPostMarshal() 304
 - inReplyPreMarshal() 305
 - inRequestPostMarshal() 306
 - inRequestPreMarshal() 307
 - outReplyFailure() 308
 - outReplyPostMarshal() 309
 - outReplyPreMarshal() 310
 - outRequestPostMarshal() 311
 - outRequestPreMarshal() 312
 - ioCallback 313
 - CloseCallback() 314
 - OpenCallback() 315
 - IT_reqTransformer 316
 - transform() 317
 - transform_error() 318
 - LoaderClass 319
 - load() 321
 - LoaderClass() 320, 321
 - record() 323
 - rename() 324
 - save() 325
 - locatorClass 327
 - locator() 327
 - lookUp() 328
 - OrbConfig 330
 - defaultConfigFile() 331
 - getConfigFile() 331
 - getConfigItem() 332
 - getConfiguration() 332
 - OrbConfig() 331
 - setConfigItem() 333
 - zeroConfiguration() 333
 - ProxyFactory 334
 - New() 335
 - ProxyFactory() 334, 335
 - ThreadFilter 337
 - inRequestPreMarshal() 339
 - ThreadFilter() 338
- _OrbixWeb 349
 - Any() 350
 - Context() 351
 - ContextList() 351
 - Current() 351, 352
 - NamedValue() 353
 - NVList() 353
 - Object() 354
 - Principal() 354
 - Request() 355
 - ServerRequest() 355
 - TypeCode() 356
 - _implementation() 175
 - impl_is_ready() 114
 - init() 50, 51, 213
 - initialise() 151
 - InitService class 150
 - InitService() 150
 - InputStream, class 53
 - inReplyFailure() 304
 - inReplyPostMarshal() 304
 - inReplyPreMarshal() 305
 - inRequestPostMarshal() 306

-
- inRequestPreMarshal() 307, 339
 - insert() 93
 - insert_any() 93
 - insert_boolean() 93
 - insert_char() 93
 - insert_double() 93
 - insert_float() 93
 - insert_long() 93
 - insert_longlong() 93
 - insert_Object() 94
 - insert_octet() 93
 - insert_Principal() 94
 - insert_short() 93
 - insert_Streamable() 94
 - insert_string() 93
 - insert_TypeCode() 94
 - insert_ulong() 93
 - insert_ulonglong() 93
 - insert_ushort() 93
 - insert_wchar() 94
 - insert_wstring() 94
 - _interfaceHost() 176
 - _interfaceImplementation() 176
 - _interfaceMarker() 176
 - InterfaceName 409
 - InvalidName class 52
 - invoke() 261
 - ioCallback interface 313
 - _is_a() 176
 - is_a() 396
 - isBaseInterfaceOf() 217
 - isDynamic() 262
 - _is_equivalent() 177
 - isEventPending() 117
 - isException() 262
 - _isRemote() 178
 - IT_create()
 - context 137
 - IT_daemon 423
 - operations
 - addInvokeRights() 427
 - addInvokeRightsDir() 428
 - addLaunchRights() 428
 - addLaunchRightsDir() 427, 428
 - addMethod() 429
 - addSharedMarker() 429
 - addUnsharedMarker() 430
 - changeOwnerServer() 430
 - deleteDirectory() 431
 - deleteServer() 431
 - getImplementationDetails() 432, 433
 - getServer() 431
 - getServer2() 432
 - killServer() 434
 - LaunchStatus 434
 - listActiveServers() 435
 - listHostsInServer() 435
 - listServers() 435
 - lookup() 436
 - newDirectory() 436
 - newPerMethodServer() 436
 - newSharedServer() 437
 - newSharedServer2() 438
 - newUnSharedServer() 439
 - removeDirRights() 440
 - removeInvokeRights() 441
 - removeInvokeRightsDir() 441
 - removeLaunchRights() 441
 - removeLaunchRightsDir() 442
 - removeMethod() 442
 - removeSharedMarker() 442
 - removeUnsharedMarker() 443
 - serverExists() 444
 - serverDetails 443
 - item() 141, 149, 163
 - IT_INFINITE_TIMEOUT 345
 - IT_INTEROPERABLE_OR_KIND 345
 - IT_ORBIX_OR_KIND 345
 - IT_reqTransformer class 316
- K**
- killServer() 434
 - kind 406
 - kind() 286
- L**
- LaunchStatus 434
 - length 364
 - length() 292
 - listActiveServers() 435
 - listHostsInServer() 435
 - list_initial_services() 217
 - listServers() 435
 - load() 321
 - _loader() 179
 - LoaderClass class 319
 - loaders 319
 - locator() 218
 - locatorClass class 327

locators
 default locator 423
lookup() 328, 436
lookup() 384
lookup_id() 410
lookup_name() 385

M

makeIOR() 218
_marker() 178, 179
maxConnectRetries() 220
_MAX_LOCATOR_HOPS 346
max_returned_objs 409
member_count() 289
member_label() 291
member_name() 290
members 387, 389, 414, 420
member_type() 290
mode 366, 404
move() 373
myActivationMode() 117
myHost() 118, 221
myHostIP() 119
myImplementationName() 119
myMarkerName() 120
myMarkerPattern() 120
myMethodName() 120

N

_name() 180
name() 156, 246, 289, 374
NamedValue class 43, 152
NamedValue() 153, 154
 _OrbixWeb conversion 353
New() 335
newDirectory() 436
newMethodPerServer() 436
newSharedServer() 437
newSharedServer2() 438
newUnsharedServer() 439
next() 143, 166
_nil() 134, 157, 164, 221, 262
_non_existent() 180
noReconnectOnFailure() 221
numClientsConnected() 121
NVList class 44, 158
NVList() 140, 148, 159, 160
 _OrbixWeb conversion 353
NVListIterator class 165

NVListIterator() 165, 166

O

Object class 45
Object()
 _OrbixWeb conversion 354
objectDeletion 346, 347
ObjectRef interface 168
_object_to_string() 181, 182
object_to_string() 222
obj_is_ready() 121
OpenCallback() 315
operation() 263
op_name() 62
ORB class 46, 184
OrbConfig class 330
OrbConfig() 331
OrbCurrent class 237
orbixd
 IDL definition 423
orbixTypeCode() 293
_ORBIX_VERSION 345
_OrbixWeb class 349
org.omg.CORBA
 ARG_IN 29
 ARG_INOUT 30
 ARG_OUT 31
 Bounds 32
 Bounds() 32
 CompletionStatus 33
 from_int() 34
 value() 33
Context 35
ContextList 37
ContextList class 37
 _create_request() 45
CTX_RESTRICT_SCOPE 38
Current 39
DynamicImplementation 40
Environment 41
ExceptionList 42
NamedValue 43
NVList 44
Object 45
ORB 46
 init() 50, 51
ORBPackage
 InvalidName 52
 InvalidName() 52
portable

- InputStream 53
- OutputStream 55
- Streamable 57
- Principal 58
- Request 59
- ServerRequest
 - ctx() 62
 - except() 65
 - op_name() 62
 - params() 62
 - result() 65
- SystemException 66
- TCKind 67
 - from_int() 69
 - value() 69
- TypeCode 71
- TypeCodePackage
 - BadKind class 74
 - BadKind() 74
 - Bounds 75
 - Bounds() 75
- UnknownUserException 76
- UnknownUserException() 76
- UserException 77
- original_type_def 362
- OutputStream class 55
- outReplyFailure() 308
- outReplyPostMarshal() 309
- outReplyPreMarshal() 310
- outRequestPostMarshal() 311
- outRequestPreMarshal() 312

P

- params 404
- params() 62
- parent() 137
- pingDuringBind() 223
- poll_next_response() 224
- poll_response() 263
- _port() 180
- Principal class 58, 244
- Principal() 245
- _OrbixWeb conversion 354
- processEvents() 122
- processNextEvent() 125
- processTermination 348
- ProxyFactory class 334
- ProxyFactory() 334, 335

R

- read_value() 95
- record() 323
- registerIOCallback() 225
- remove() 141, 149, 164
- removeDirRights() 440
- removeInvokeRights() 441
- removeInvokeRightsDir() 441
- removeLaunchRights() 441
- removeLaunchRightsDir() 442
- removeMethod() 442
- removeSharedMarker() 442
- removeUnsharedMarker() 443
- rename() 324
- Request class 59, 98, 248
- Request() 252, 253
- _OrbixWeb conversion 355
- _request() 170, 180
- reset() 96, 263
- reSizeConnectionTable() 224
- resolve_initial_references() 226
- result 405
- result() 65, 264
- return_value() 264
- rollback() 400

S

- _save() 182
- save() 325
- send_deferred() 265
- send_multiple_requests_deferred() 227
- send_multiple_requests_oneway() 228
- send_oneway() 265
- serverDetails 443
- serverExists() 444
- ServerRequest class 61
- ServerRequest()
 - _OrbixWeb conversion 355
- setConfigItem() 228, 300, 333
- setConfiguration() 229
- setDiagnostics() 229
- setHostPort() 230
- setList() 143
- setMyReqTransformer() 231
- setNoHangup() 127
- set_one_value() 137
- setOperation() 266
- set_parameters() 231
- set_principal() 232
- setProxyServer() 128

setReqTransformer() 232
set_return_type() 266
setServerName() 128
setTarget() 267
set_values() 138
shutdown() 129, 206
singleton ORB 268
start() 399
Streamable class 57
string_to_object() 234
SystemException class 66

T

target() 267
TCKind class 67
ThreadFilter class 337
ThreadFilter() 338
threads
 used by ioCallbacks 313
toString() 96, 129, 156, 235, 247, 294
transform() 317
transform_error() 318
type 366, 368, 389, 391, 412
type() 97
TypeCode
 constants 343
TypeCode class 71
TypeCode, Class 279
TypeCode() 285, 286
 _OrbixWeb conversion 356
type_def 366, 368

U

UnknownUserException class 76
UnknownUserException() 76
unregisterIOCallback() 236
UserException class 77

V

value 369
value() 33, 69, 156
version 374

W

write_value() 97

Z

zeroConfiguration() 333